

# Hortonworks DataFlow

## User Guide

(February 28, 2018)

## Hortonworks DataFlow: User Guide

Copyright © 2012-2018 Hortonworks, Inc. Some rights reserved.



Except where otherwise noted, this document is licensed under  
**Creative Commons Attribution ShareAlike 4.0 License.**  
<http://creativecommons.org/licenses/by-sa/4.0/legalcode>

# Table of Contents

1. Apache NiFi User Guide .....	1
1.1. Apache NiFi User Guide .....	1
1.1.1. Browser Support .....	1
1.1.2. Terminology .....	1
1.1.3. NiFi User Interface .....	3
1.1.4. Accessing the UI with Multi-Tenant Authorization .....	6
1.1.5. Logging In .....	7
1.1.6. Building a DataFlow .....	7
1.1.7. Command and Control of the DataFlow .....	66
1.1.8. Navigating within a DataFlow .....	70
1.1.9. Monitoring of DataFlow .....	74
1.1.10. Versioning a DataFlow .....	85
1.1.11. Templates .....	101
1.1.12. Data Provenance .....	104
1.1.13. Other Management Features .....	118

# 1. Apache NiFi User Guide

## 1.1. Apache NiFi User Guide

See the [System Administrator's Guide](#) for information about system requirements, installation, and configuration. Once NiFi is installed, use a supported web browser to view the UI.

### 1.1.1. Browser Support

Browser	Version
Chrome	Current and Current - 1
FireFox	Current and Current - 1
Edge	Current and Current - 1
Safari	Current and Current - 1

Current and Current - 1 indicates that the UI is supported in the current stable release of that browser and the preceding one. For instance, if the current stable release is 45.X then the officially supported versions will be 45.X and 44.X.

For Safari, which releases major versions much less frequently, Current and Current - 1 simply represent the two latest releases.

The supported browser versions are driven by the capabilities the UI employs and the dependencies it uses. UI features will be developed and tested against the supported browsers. Any problem using a supported browser should be reported to Apache NiFi.

#### 1.1.1.1. Unsupported Browsers

While the UI may run successfully in unsupported browsers, it is not actively tested against them. Additionally, the UI is designed as a desktop experience and is not currently supported in mobile browsers.

#### 1.1.1.2. Viewing the UI in Variably Sized Browsers

In most environments, all of the UI is visible in your browser. However, the UI has a responsive design that allows you to scroll through screens as needed, in smaller sized browsers or tablet environments.

In environments where your browser width is less than 800 pixels and the height less than 600 pixels, portions of the UI may become unavailable.

### 1.1.2. Terminology

**DataFlow Manager:** A DataFlow Manager (DFM) is a NiFi user who has permissions to add, remove, and modify components of a NiFi dataflow.



**FlowFile:** The FlowFile represents a single piece of data in NiFi. A FlowFile is made up of two components: FlowFile Attributes and FlowFile Content. Content is the data that is represented by the FlowFile. Attributes are characteristics that provide information or context about the data; they are made up of key-value pairs. All FlowFiles have the following Standard Attributes:

- **uuid:** A unique identifier for the FlowFile
- **filename:** A human-readable filename that may be used when storing the data to disk or in an external service
- **path:** A hierarchically structured value that can be used when storing data to disk or an external service so that the data is not stored in a single directory

**Processor:** The Processor is the NiFi component that is used to listen for incoming data; pull data from external sources; publish data to external sources; and route, transform, or extract information from FlowFiles.

**Relationship:** Each Processor has zero or more Relationships defined for it. These Relationships are named to indicate the result of processing a FlowFile. After a Processor has finished processing a FlowFile, it will route (or "transfer") the FlowFile to one of the Relationships. A DFM is then able to connect each of these Relationships to other components in order to specify where the FlowFile should go next under each potential processing result.

**Connection:** A DFM creates an automated dataflow by dragging components from the Components part of the NiFi toolbar to the canvas and then connecting the components together via Connections. Each connection consists of one or more Relationships. For each Connection that is drawn, a DFM can determine which Relationships should be used for the Connection. This allows data to be routed in different ways based on its processing outcome. Each connection houses a FlowFile Queue. When a FlowFile is transferred to a particular Relationship, it is added to the queue belonging to the associated Connection.

**Controller Service:** Controller Services are extension points that, after being added and configured by a DFM in the User Interface, will start up when NiFi starts up and provide information for use by other components (such as processors or other controller services). A common Controller Service used by several components is the StandardSSLContextService. It provides the ability to configure keystore and/or truststore properties once and reuse that configuration throughout the application. The idea is that, rather than configure this information in every processor that might need it, the controller service provides it for any processor to use as needed.

**Reporting Task:** Reporting Tasks run in the background to provide statistical reports about what is happening in the NiFi instance. The DFM adds and configures Reporting Tasks in the User Interface as desired. Common reporting tasks include the ControllerStatusReportingTask, MonitorDiskUsage reporting task, MonitorMemory reporting task, and the StandardGangliaReporter.

**Funnel:** A funnel is a NiFi component that is used to combine the data from several Connections into a single Connection.

**Process Group:** When a dataflow becomes complex, it often is beneficial to reason about the dataflow at a higher, more abstract level. NiFi allows multiple components, such

as Processors, to be grouped together into a Process Group. The NiFi User Interface then makes it easy for a DFM to connect together multiple Process Groups into a logical dataflow, as well as allowing the DFM to enter a Process Group in order to see and manipulate the components within the Process Group.

**Port:** Dataflows that are constructed using one or more Process Groups need a way to connect a Process Group to other dataflow components. This is achieved by using Ports. A DFM can add any number of Input Ports and Output Ports to a Process Group and name these ports appropriately.

**Remote Process Group:** Just as data is transferred into and out of a Process Group, it is sometimes necessary to transfer data from one instance of NiFi to another. While NiFi provides many different mechanisms for transferring data from one system to another, Remote Process Groups are often the easiest way to accomplish this if transferring data to another instance of NiFi.

**Bulletin:** The NiFi User Interface provides a significant amount of monitoring and feedback about the current status of the application. In addition to rolling statistics and the current status provided for each component, components are able to report Bulletins. Whenever a component reports a Bulletin, a bulletin icon is displayed on that component. System-level bulletins are displayed on the Status bar near the top of the page. Using the mouse to hover over that icon will provide a tool-tip that shows the time and severity (Debug, Info, Warning, Error) of the Bulletin, as well as the message of the Bulletin. Bulletins from all components can also be viewed and filtered in the Bulletin Board Page, available in the Global Menu.

**Template:** Often times, a dataflow is comprised of many sub-flows that could be reused. NiFi allows DFMs to select a part of the dataflow (or the entire dataflow) and create a Template. This Template is given a name and can then be dragged onto the canvas just like the other components. As a result, several components may be combined together to make a larger building block from which to create a dataflow. These templates can also be exported as XML and imported into another NiFi instance, allowing these building blocks to be shared.

**flow.xml.gz:** Everything the DFM puts onto the NiFi User Interface canvas is written, in real time, to one file called the flow.xml.gz. This file is located in the nifi/conf directory by default. Any change made on the canvas is automatically saved to this file, without the user needing to click a "save" button. In addition, NiFi automatically creates a backup copy of this file in the archive directory when it is updated. You can use these archived files to rollback flow configuration. To do so, stop NiFi, replace flow.xml.gz with a desired backup copy, then restart NiFi. In a clustered environment, stop the entire NiFi cluster, replace the flow.xml.gz of one of nodes, and restart the node. Remove flow.xml.gz from other nodes. Once you confirmed the node starts up as a one-node cluster, start the other nodes. The replaced flow configuration will be synchronized across the cluster. The name and location of flow.xml.gz, and auto archive behavior are configurable. See the [System Administrator's Guide](#) for further details.


### 1.1.3. NiFi User Interface

The NiFi UI provides mechanisms for creating automated dataflows, as well as visualizing, editing, monitoring, and administering those dataflows. The UI can be broken down

into several segments, each responsible for different functionality of the application. This section provides screenshots of the application and highlights the different segments of the UI. Each segment is discussed in further detail later in the document.

When the application is started, the user is able to navigate to the UI by going to the default address of `http://<hostname>:8080/nifi` in a web browser. There are no permissions configured by default, so anyone is able to view and modify the dataflow. For information on securing the system, see the [System Administrator's Guide](#).

When a DFM navigates to the UI for the first time, a blank canvas is provided on which a dataflow can be built:




The Components Toolbar runs across the top left portion of your screen. It consists of the components you can drag onto the canvas to build your dataflow. Each component is described in more detail in [Building a Dataflow](#).


The Status Bar is under the Components Toolbar. The Status bar provides information about the number of threads that are currently active in the flow, the amount of data that currently exists in the flow, how many Remote Process Groups exist on the canvas in each state (Transmitting, Not Transmitting), how many Processors exist on the canvas in each state (Stopped, Running, Invalid, Disabled), how many versioned Process Groups exist on the canvas in each state (Up to date, Locally modified, Stale, Locally modified and stale, Sync failure) and the timestamp at which all of this information was last refreshed. Additionally, if the instance of NiFi is clustered, the Status bar shows how many nodes are in the cluster and how many are currently connected.

The Operate Palette sits to the left-hand side of the screen. It consists of buttons that are used by DFMs to manage the flow, as well as by administrators who manage user access and configure system properties, such as how many system resources should be provided to the application.

On the right side of the canvas is Search, and the Global Menu. You can use Search to easily find components on the canvas and can to search by component name, type, identifier, configuration properties, and their values. The Global Menu contains options that allow you to manipulate existing components on the canvas:



Additionally, the UI has some features that allow you to easily navigate around the canvas. You can use the Navigate Palette to pan around the canvas, and to zoom in and out. The "Birds Eye View" of the dataflow provides a high-level view of the dataflow and allows you to pan across large portions of the dataflow. You can also find breadcrumbs along the bottom of the screen. As you navigate into and out of Process Groups, the breadcrumbs show the depth in the flow, and each Process Group that you entered to reach this depth. Each of the Process Groups listed in the breadcrumbs is a link that will take you back up to that level in the flow.



## 1.1.4. Accessing the UI with Multi-Tenant Authorization

Multi-tenant authorization enables multiple groups of users (tenants) to command, control, and observe different parts of the dataflow, with varying levels of authorization. When an authenticated user attempts to view or modify a NiFi resource, the system checks whether the user has privileges to perform that action. These privileges are defined by policies that you can apply system wide or to individual components. What this means from a Dataflow Manager perspective is that once you have access to the NiFi canvas, a range of functionality is visible and available to you, depending on the privileges assigned to you.

The available global access policies are:

Policy	Privilege
view the UI	Allows users to view the UI
access the controller	Allows users to view and modify the controller including reporting tasks, Controller Services, and nodes in the cluster
query provenance	Allows users to submit a provenance search and request even lineage
access restricted components	Allows users to create/modify restricted components assuming otherwise sufficient permissions
access all policies	Allows users to view and modify the policies for all components
access users/groups	Allows users view and modify the users and user groups
retrieve site-to-site details	Allows other NiFi instances to retrieve Site-To-Site details
view system diagnostics	Allows users to view System Diagnostics
proxy user requests	Allows proxy machines to send requests on the behalf of others
access counters	Allows users to view and modify counters

The available component-level access policies are:


Policy	Privilege
view the component	Allows users to view component configuration details
modify the component	Allows users to modify component configuration details
view the data	Allows users to view metadata and content for this component through provenance data and flowfile queues in outbound connection
modify the data	Allows users to empty flowfile queues in outbound connections and to submit replays
view the policies	Allows users to view the list of users who can view and modify a component
modify the policies	Allows users to modify the list of users who can view and modify a component
retrieve data via site-to-site	Allows a port to receive data from NiFi instances
send data via site-to-site	Allows a port to send data from NiFi instances

If you are unable to view or modify a NiFi resource, contact your System Administrator or see [Configuring Users and Access Policies](#) in the [System Administrator's Guide](#) for more information.

## 1.1.5. Logging In

If NiFi is configured to run securely, users will be able to request access to the DataFlow. For information on configuring NiFi to run securely, see the [System Administrator's Guide](#). If NiFi supports anonymous access, users will be given access accordingly and given an option to log in.

Clicking the 'login' link will open the log in page. If the user is logging in with their username/password they will be presented with a form to do so. If NiFi is not configured to support anonymous access and the user is logging in with their username/password, they will be immediately sent to the login form bypassing the canvas.



## 1.1.6. Building a DataFlow

A DFM is able to build an automated dataflow using the NiFi UI. Simply drag components from the toolbar to the canvas, configure the components to meet specific needs, and connect the components together.

### 1.1.6.1. Adding Components to the Canvas

The User Interface section above outlined the different segments of the UI and pointed out a Components Toolbar. This section looks at each of the Components in that toolbar:



**Processor:**

The Processor is the most commonly used component, as it is responsible for data ingress, egress, routing, and manipulating. There are many different types of Processors. In fact, this is a very common Extension Point in NiFi, meaning that many vendors may implement their own Processors to perform whatever functions are necessary for their use case. When a Processor is dragged onto the canvas, the user is presented with a dialog to choose which type of Processor to use:

### Add Processor

Source
Displaying 219 of 219

all groups	Type	Version	Tags
	AttributeRollingWindow	1.2.0	rolling, data science, Attribute Expression Language, st...
	AttributesToJSON	1.2.0	flowfile, json, attributes
	Base64EncodeContent	1.2.0	encode, base64
	CaptureChangeMySQL	1.2.0	cdc, jdbc, mysql, sql
	CompareFuzzyHash	1.2.0	fuzzy-hashing, hashing, cyber-security
	CompressContent	1.2.0	lzma, decompress, compress, snappy framed, gzip, sna...
	ConnectWebSocket	1.2.0	subscribe, consume, listen, WebSocket
	ConsumeAMQP	1.2.0	receive, amqp, rabbit, get, consume, message
	ConsumeEWS	1.2.0	EWS, Exchange, Email, Consume, Ingest, Message, Get,...
	ConsumeIMAP	1.2.0	Imap, Email, Consume, Ingest, Message, Get, Ingress
	ConsumeJMS	1.2.0	jms, receive, get, consume, message
	ConsumeKafka	1.2.0	PubSub, Consume, Inqest, Get, Kafka, Ingress, Topic, 0...

**amazon attributes**  
**avro aws consume**  
**csv database fetch**  
**files get hadoop**  
**ingest input insert**  
**json listen logs**  
**message put**  
**remote restricted**  
**source sql text**  
**update**

**AttributeRollingWindow 1.2.0** org.apache.nifi - nifi-stateful-analysis-nar

Track a Rolling Window based on evaluating an Expression Language expression on each FlowFile and add that value to the processor's state. Each FlowFile will be emitted with the count of FlowFiles and total aggregate value of values processed in the current time window.

CANCEL
ADD

In the top-right corner, the user is able to filter the list based on the Processor Type or the Tags associated with a Processor. Processor developers have the ability to add Tags to their Processors. These tags are used in this dialog for filtering and are displayed on the left-hand side in a Tag Cloud. The more Processors that exist with a particular Tag, the larger the Tag appears in the Tag Cloud. Clicking a Tag in the Cloud will filter the available Processors to only those that contain that Tag. If multiple Tags are selected, only those Processors that contain all of those Tags are shown. For example, if we want to show only those Processors that allow us to ingest files, we can select both the `files` Tag and the `ingest` Tag:

### Add Processor

Source
Displaying 11 of 219
Filter

all groups ▾

amazon attributes  
avro aws consume  
csv database fetch  
files get hadoop  
ingest input insert  
json listen logs  
message put remote  
restricted source sql  
text update

Type ▾	Version	Tags
FetchFTP	1.2.0	input, ftp, get, fetch, retrieve, files, source, remote, ingest
FetchFile	1.2.0	ingress, input, restricted, get, files, source, local, filesystem, ingest
FetchSFTP	1.2.0	input, get, fetch, retrieve, files, sftp, source, remote, ingest
GetFTP	1.2.0	input, FTP, get, fetch, retrieve, files, source, remote, ingest
GetFile	1.2.0	ingress, input, restricted, get, files, source, local, filesystem, ingest
GetHDFS	1.2.0	restricted, get, fetch, HDFS, hadoop, source, filesystem, ingest
GetSFTP	1.2.0	input, get, fetch, retrieve, files, sftp, source, remote, ingest
ListFTP	1.2.0	input, ftp, files, source, list, remote, ingest
ListFile	1.2.0	file, get, source, list, filesystem, ingest
ListHDFS	1.2.0	get, HDFS, hadoop, source, list, filesystem, ingest
ListSFTP	1.2.0	input, files, sftp, source, list, remote, ingest

**FetchFTP 1.2.0** org.apache.nifi - nifi-standard-nar

Fetches the content of a file from a remote SFTP server and overwrites the contents of an incoming FlowFile with the content of the remote file.

CANCEL ADD

Restricted components will be marked with a



icon next to their name. These are components that can be used to execute arbitrary unsanitized code provided by the operator through the NiFi REST API/UI or can be used to obtain or alter data on the NiFi host system using the NiFi OS credentials. These components could be used by an otherwise authorized NiFi user to go beyond the intended use of the application, escalate privilege, or could expose data about the internals of the NiFi process or the host system. All of these capabilities should be considered privileged, and admins should be aware of these capabilities and explicitly enable them for a subset of trusted users.


Before a user is allowed to create and modify restricted components they must be granted access to restricted components. For more information refer to [Accessing the UI with Multi-Tenant Authorization](#).

Clicking the **Add** button or double-clicking on a Processor Type will add the selected Processor to the canvas at the location that it was dropped.

For any component added to the canvas, it is possible to select it with the mouse and move it anywhere on the canvas. Also, it is possible to select multiple items at once by either holding down the Shift key and selecting each item or by holding down the Shift key and dragging a selection box around the desired components.



Once you have dragged a Processor onto the canvas, you can interact with it by right-clicking on the Processor and selecting an option from the context menu. The options available to you from the context menu vary, depending on the privileges assigned to you.



While the options available from the context menu vary, the following options are typically available when you have full privileges to work with a Processor:

- **Configure:** This option allows the user to establish or change the configuration of the Processor (see [Configuring a Processor](#)).

For Processors, Ports, Remote Process Groups, Connections and Labels, it is possible to open the configuration dialog by double-clicking on desired component.

- **Start or Stop:** This option allows the user to start or stop a Processor; the option will be either Start or Stop, depending on the current state of the Processor.
- **Enable or Disable:** This option allows the user to enable or enable a Processor; the option will be either Enable or Disable, depending on the current state of the Processor.
- **View data provenance:** This option displays the NiFi Data Provenance table, with information about data provenance events for the FlowFiles routed through that Processor (see [Data Provenance](#)).
- **View status history:** This option opens a graphical representation of the Processor's statistical information over time.
- **View usage:** This option takes the user to the Processor's usage documentation.
- **View connections#Upstream:** This option allows the user to see and "jump to" upstream connections that are coming into the Processor. This is particularly useful when processors connect into and out of other Process Groups.

- **View connections#Downstream:** This option allows the user to see and "jump to" downstream connections that are going out of the Processor. This is particularly useful when processors connect into and out of other Process Groups.
- **Center in view:** This option centers the view of the canvas on the given Processor.
- **Change color:** This option allows the user to change the color of the Processor, which can make the visual management of large flows easier.
- **Create template:** This option allows the user to create a template from the selected Processor.
- **Copy:** This option places a copy of the selected Processor on the clipboard, so that it may be pasted elsewhere on the canvas by right-clicking on the canvas and selecting Paste. The Copy/Paste actions also may be done using the keystrokes Ctrl-C (Command-C) and Ctrl-V (Command-V).
- **Delete:** This option allows the DFM to delete a Processor from the canvas.



## Input

**Port:** Input Ports provide a mechanism for transferring data into a Process Group. When an Input Port is dragged onto the canvas, the DFM is prompted to name the Port. All Ports within a Process Group must have unique names.

All components exist only within a Process Group. When a user initially navigates to the NiFi page, the user is placed in the Root Process Group. If the Input Port is dragged onto the Root Process Group, the Input Port provides a mechanism to receive data from remote instances of NiFi via [Site-to-Site](#). In this case, the Input Port can be configured to restrict access to appropriate users, if NiFi is configured to run securely. For information on configuring NiFi to run securely, see the [System Administrator's Guide](#).



## Output

**Port:** Output Ports provide a mechanism for transferring data from a Process Group to destinations outside of the Process Group. When an Output Port is dragged onto the canvas, the DFM is prompted to name the Port. All Ports within a Process Group must have unique names.


If the Output Port is dragged onto the Root Process Group, the Output Port provides a mechanism for sending data to remote instances of NiFi via [Site-to-Site](#). In this case, the Port acts as a queue. As remote instances of NiFi pull data from the port, that data is removed from the queues of the incoming Connections. If NiFi is configured to run securely, the Output Port can be configured to restrict access to appropriate users. For information on configuring NiFi to run securely, see the [System Administrator's Guide](#).



## Process

**Group:** Process Groups can be used to logically group a set of components so that the dataflow is easier to understand and maintain. When a Process Group is dragged onto the canvas, the DFM is prompted to name the Process Group. All Process Groups within the same parent group must have unique names. The Process Group will then be nested within that parent group.

Once you have dragged a Process Group onto the canvas, you can interact with it by right-clicking on the Process Group and selecting an option from context menu. The options available to you from the context menu vary, depending on the privileges assigned to you.



While the options available from the context menu vary, the following options are typically available when you have full privileges to work with the Process Group:

- **Configure:** This option allows the user to establish or change the configuration of the Process Group.
- **Variables:** This option allows the user to create or configure variables within the NiFi UI.
- **Enter group:** This option allows the user to enter the Process Group.

It is also possible to double-click on the Process Group to enter it.

- **Start:** This option allows the user to start a Process Group.
- **Stop:** This option allows the user to stop a Process Group.


- **View status history:** This option opens a graphical representation of the Process Group's statistical information over time.
- **View connections#Upstream:** This option allows the user to see and "jump to" upstream connections that are coming into the Process Group.
- **View connections#Downstream:** This option allows the user to see and "jump to" downstream connections that are going out of the Process Group.
- **Center in view:** This option centers the view of the canvas on the given Process Group.
- **Group:** This option allows the user to create a new Process Group that contains the selected Process Group and any other components selected on the canvas.
- **Create template:** This option allows the user to create a template from the selected Process Group.
- **Copy:** This option places a copy of the selected Process Group on the clipboard, so that it may be pasted elsewhere on the canvas by right-clicking on the canvas and selecting Paste. The Copy/Paste actions also may be done using the keystrokes Ctrl-C (Command-C) and Ctrl-V (Command-V).
- **Delete:** This option allows the DFM to delete a Process Group.



## Remote

**Process Group:** Remote Process Groups appear and behave similar to Process Groups. However, the Remote Process Group (RPG) references a remote instance of NiFi. When an RPG is dragged onto the canvas, rather than being prompted for a name, the DFM is prompted for the URL of the remote NiFi instance. If the remote NiFi is a clustered instance, the URL that should be used is the URL of any NiFi instance in that cluster. When data is transferred to a clustered instance of NiFi via an RPG, the RPG will first connect to the remote instance whose URL is configured to determine which nodes are in the cluster and how busy each node is. This information is then used to load balance the data that is pushed to each node. The remote instances are then interrogated periodically to determine information about any nodes that are dropped from or added to the cluster and to recalculate the load balancing based on each node's load. For more information, see the section on [Site-to-Site](#).

Once you have dragged a Remote Process Group onto the canvas, you can may interact with it by right-clicking on the Remote Process Group and selecting an option from context menu. The options available to you from the context menu vary, depending on the privileges assigned to you.



While the options available from the context menu vary, the following options are typically available when you have full privileges to work with the Remote Process Group:

- **Configure:** This option allows the user to establish or change the configuration of the Remote Process Group.
- **Enable transmission:** Makes the transmission of data between NiFi instances active (see [Remote Process Group Transmission](#)).
- **Disable transmission:** Disables the transmission of data between NiFi instances.
- **View status history:** This option opens a graphical representation of the Remote Process Group's statistical information over time.
- **View connections#Upstream:** This option allows the user to see and "jump to" upstream connections that are coming into the Remote Process Group.
- **View connections#Downstream:** This option allows the user to see and "jump to" downstream connections that are going out of the Remote Process Group.
- **Refresh remote:** This option refreshes the view of the status of the remote NiFi instance.
- **Group:** This option allows the user to create a new Process Group that contains the selected Remote Process Group and any other components selected on the canvas.
- **Manage remote ports:** This option allows the user to see input ports and/or output ports that exist on the remote instance of NiFi that the Remote Process Group is connected to. Note that if the Site-to-Site configuration is secure, only the ports that the connecting NiFi has been given accessed to will be visible.
- **Center in view:** This option centers the view of the canvas on the given Remote Process Group.


- **Go to:** This option opens a view of the remote NiFi instance in a new tab of the browser. Note that if the Site-to-Site configuration is secure, the user must have access to the remote NiFi instance in order to view it.
- **Group:** This option allows the user to create a Process Group containing the selected Remote Process Group.
- **Create template:** This option allows the user to create a template from the selected Remote Process Group.
- **Copy:** This option places a copy of the selected Process Group on the clipboard, so that it may be pasted elsewhere on the canvas by right-clicking on the canvas and selecting Paste. The Copy/Paste actions also may be done using the keystrokes Ctrl-C (Command-C) and Ctrl-V (Command-V).
- **Delete:** This option allows the DFM to delete a Remote Process Group from the canvas.

**Funnel:**


Funnels are used to combine the data from many Connections into a single Connection. This has two advantages. First, if many Connections are created with the same destination, the canvas can become cluttered if those Connections have to span a large space. By funneling these Connections into a single Connection, that single Connection can then be drawn to span that large space instead. Secondly, Connections can be configured with FlowFile Prioritizers. Data from several Connections can be funneled into a single Connection, providing the ability to Prioritize all of the data on that one Connection, rather than prioritizing the data on each Connection independently.

**Template:**

Templates can be created by DFMs from sections of the flow, or they can be imported from other dataflows. These Templates provide larger building blocks for creating a complex flow quickly. When the Template is dragged onto the canvas, the DFM is provided a dialog to choose which Template to add to the canvas:



Clicking the drop-down box shows all available Templates. Any Template that was created with a description will show a question mark icon, indicating that there is more information. Hovering over the icon with the mouse will show this description:



#### Label:

Labels are used to provide documentation to parts of a dataflow. When a Label is dropped onto the canvas, it is created with a default size. The Label can then be resized by dragging the handle in the bottom-right corner. The Label has no text when initially created. The text of the Label can be added by right-clicking on the Label and choosing `Configure`

### 1.1.6.2. Component Versions

You have access to information about the version of your Processors, Controller Services, and Reporting Tasks. This is especially useful when you are working within a clustered environment with multiple NiFi instances running different versions of a component or if you have upgraded to a newer version of a processor. The Add Processor, Add Controller

Service, and Add Reporting Task dialogs include a column identifying the component version, as well as the name of the component, the organization or group that created the component, and the NAR bundle that contains the component.

Add Processor

Source example

all groups ▼ Displaying 2 of 221

Type	Version ▲	Tags
MyProcessor	1.0	example
MyProcessor	2.0	example

**amazon attributes**

**avro aws**

**consume csv**

**database fetch**

**files get hadoop**

**ingest input**

**insert json listen**

**logs message**

**put remote**

**restricted source**

**sql text update**

Name                      Group                      Bundle

↓                                      ↓                                      ↓

MyProcessor 1.0      org.apache.nifi - nifi-example-processors-nar

Provide a description

CANCEL
ADD

Each component displayed on the canvas also contains this information.

**MyProcessor**

MyProcessor 1.0

org.apache.nifi - nifi-example-processors-nar

In	0 (0 bytes)	5 min
Read/Write	0 bytes / 0 bytes	5 min
Out	0 (0 bytes)	5 min
Tasks/Time	0 / 00:00:00.000	5 min

### 1.1.6.2.1. Sorting and Filtering Components

When you are adding a component, you can sort on version number or filter based on originating source.

To sort based on version, click the version column to display in ascending or descending version order.



To filter based on source group, click the source drop-down in the upper left of your Add Component dialog, and select the group you want to view.

**Add Processor**

Source: all groups (dropdown)

Displaying 2 of 221

Type	Version	Tags
MyProcessor	1.0	example
MyProcessor	2.0	example

Source categories: amazon, attributes, avro, aws, consume, csv, database, fetch, files, get, hadoop, ingest, input, insert, json, listen, logs, message, put, remote, restricted, source, sql, text, update

**MyProcessor 1.0** org.apache.nifi - nifi-example-processors-nar


Provide a description

CANCEL ADD

### 1.1.6.2.2. Changing Component Versions

To change a component version, perform the following steps.

1. Right-click the component on the canvas to display configuration options.
2. Select Change version.



3. In the Component Version dialog, select the version you want to run from the Version drop-down menu.

**Component Version**

Name  
MyProcessor

Bundle  
org.apache.nifi - nifi-example-processors-nar

Version

1.0	✓
2.0	?
1.0	?

Restriction  
No restriction

Description  
Provide a description

CANCEL APPLY

### 1.1.6.2.3. Understanding Version Dependencies

When you are configuring a component, you can also view information about version dependencies.

1. Right-click your component and select Configure to display the Configure dialog for your component.
2. Click the Properties tab.
3. Click the information icon to view any version dependency information.

**Configure Processor**

SETTINGS SCHEDULING **PROPERTIES** COMMENTS


Required field +

Property	Value
My Property	No value set
My Service	No value set


Example Controller Service Property  
Supports expression language: false  
Requires Controller Service: MyService 1.0 from org.apache.nifi - nifi-example-service-api-nar

CANCEL APPLY

In the following example, MyProcessor version 1.0 is configured properly with the controller service StandardMyService version 1.0:



If the version of MyProcessor is changed to an incompatible version (MyProcessor 2.0), validation errors will be displayed on the processor:



and an error message will be displayed in the processor's controller service configuration since the service is no longer valid:

**Configure Processor**

SETTINGS SCHEDULING **PROPERTIES** COMMENTS

Required field +

Property	Value
My Property	Property1
My Service	Incompatible Controller Service Configured

CANCEL APPLY

### 1.1.6.3. Configuring a Processor

To configure a processor, right-click on the Processor and select the `Configure` option from the context menu. Alternatively, just double-click on the Processor. The configuration dialog is opened with four different tabs, each of which is discussed below. Once you have finished configuring the Processor, you can apply the changes by clicking the `Apply` button or cancel all changes by clicking the `Cancel` button.

Note that after a Processor has been started, the context menu shown for the Processor no longer has a `Configure` option but rather has a `View Configuration` option. Processor configuration cannot be changed while the Processor is running. You must first stop the Processor and wait for all of its active tasks to complete before configuring the Processor again.

Note that entering certain control characters are not supported and will be automatically filtered out when entered. The following characters and any unpaired Unicode surrogate codepoints will not be retained in any configuration:

```
[#x0], [#x1], [#x2], [#x3], [#x4], [#x5], [#x6], [#x7], [#x8], [#xB], [#xC],
[#xE], [#xF], [#x10], [#x11], [#x12], [#x13], [#x14], [#x15], [#x16], [#x17],
[#x18], [#x19], [#x1A], [#x1B], [#x1C], [#x1D], [#x1E], [#x1F], [#xFFFE],
[#xFFFF]
```

#### 1.1.6.3.1. Settings Tab

The first tab in the Processor Configuration dialog is the Settings tab:

**Configure Processor**

SETTINGS | SCHEDULING | PROPERTIES | COMMENTS

Name: RouteOnAttribute  Enabled

Automatically Terminate Relationships  unmatched  
FlowFiles that do not match any user-define expression will be routed here

Id: 313ab384-015c-1000-46ec-0ead80a5eb1e

Type: RouteOnAttribute 1.2.0

Bundle: org.apache.nifi - nifi-standard-nar

Penalty Duration: 30 sec | Yield Duration: 1 sec

Bulletin Level: WARN

CANCEL | APPLY

This tab contains several different configuration items. First, it allows the DFM to change the name of the Processor. The name of a Processor by default is the same as the Processor type. Next to the Processor Name is a checkbox, indicating whether the Processor is Enabled. When a Processor is added to the canvas, it is enabled. If the Processor is disabled, it cannot be started. The disabled state is used to indicate that when a group of Processors is started, such as when a DFM starts an entire Process Group, this (disabled) Processor should be excluded.

Below the Name configuration, the Processor's unique identifier is displayed along with the Processor's type and NAR bundle. These values cannot be modified.

Next are two dialogues for configuring 'Penalty duration' and 'Yield duration'. During the normal course of processing a piece of data (a FlowFile), an event may occur that indicates that the data cannot be processed at this time but the data may be processable at a later time. When this occurs, the Processor may choose to Penalize the FlowFile. This will prevent the FlowFile from being Processed for some period of time. For example, if the Processor is to push the data to a remote service, but the remote service already has a file with the same name as the filename that the Processor is specifying, the Processor may penalize the FlowFile. The 'Penalty duration' allows the DFM to specify how long the FlowFile should be penalized. The default value is 30 seconds.

Similarly, the Processor may determine that some situation exists such that the Processor can no longer make any progress, regardless of the data that it is processing. For example, if a Processor is to push data to a remote service and that service is not responding, the Processor cannot make any progress. As a result, the Processor should 'yield,' which will

prevent the Processor from being scheduled to run for some period of time. That period of time is specified by setting the 'Yield duration.' The default value is 1 second.

The last configurable option on the left-hand side of the Settings tab is the Bulletin level. Whenever the Processor writes to its log, the Processor also will generate a Bulletin. This setting indicates the lowest level of Bulletin that should be shown in the User Interface. By default, the Bulletin level is set to WARN, which means it will display all warning and error-level bulletins.

The right-hand side of the Settings tab contains an 'Auto-terminate relationships' section. Each of the Relationships that is defined by the Processor is listed here, along with its description. In order for a Processor to be considered valid and able to run, each Relationship defined by the Processor must be either connected to a downstream component or auto-terminated. If a Relationship is auto-terminated, any FlowFile that is routed to that Relationship will be removed from the flow and its processing considered complete. Any Relationship that is already connected to a downstream component cannot be auto-terminated. The Relationship must first be removed from any Connection that uses it. Additionally, for any Relationship that is selected to be auto-terminated, the auto-termination status will be cleared (turned off) if the Relationship is added to a Connection.

### 1.1.6.3.2. Scheduling Tab

The second tab in the Processor Configuration dialog is the Scheduling Tab:

The screenshot shows the 'Configure Processor' dialog with the 'SCHEDULING' tab selected. The 'Scheduling Strategy' is set to 'Timer driven'. 'Concurrent Tasks' is set to 1. 'Run Duration' is set to 0ms, with a slider indicating a range from 'Lower latency' to 'Higher throughput'. 'Run Schedule' is set to 0 sec. The 'CANCEL' and 'APPLY' buttons are visible at the bottom right.

The first configuration option is the Scheduling Strategy. There are three possible options for scheduling components:



**Timer driven:** This is the default mode. The Processor will be scheduled to run on a regular interval. The interval at which the Processor is run is defined by the `Run schedule` option (see below).

**Event driven:** When this mode is selected, the Processor will be triggered to run by an event, and that event occurs when FlowFiles enter Connections feeding this Processor. This mode is currently considered experimental and is not supported by all Processors. When this mode is selected, the `Run schedule` option is not configurable, as the Processor is not triggered to run periodically but as the result of an event. Additionally, this is the only mode for which the `Concurrent tasks` option can be set to 0. In this case, the number of threads is limited only by the size of the Event-Driven Thread Pool that the administrator has configured.

**CRON driven:** When using the CRON driven scheduling mode, the Processor is scheduled to run periodically, similar to the Timer driven scheduling mode. However, the CRON driven mode provides significantly more flexibility at the expense of increasing the complexity of the configuration. The CRON driven scheduling value is a string of six required fields and one optional field, each separated by a space. These fields are:

Field	Valid values
Seconds	0-59
Minutes	0-59
Hours	0-23
Day of Month	1-31
Month	1-12 or JAN-DEC
Day of Week	1-7 or SUN-SAT
Year (optional)	empty, 1970-2099

You typically specify values one of the following ways:

- **Number:** Specify one or more valid value. You can enter more than one value using a comma-separated list.
- **Range:** Specify a range using the <number>-<number> syntax.
- **Increment:** Specify an increment using <start value>/<increment> syntax. For example, in the Minutes field, 0/15 indicates the minutes 0, 15, 30, and 45.

You should also be aware of several valid special characters:

- \* - Indicates that all values are valid for that field.
- ? - Indicates that no specific value is specified. This special character is valid in the Days of Month and Days of Week field.
- L - You can append L to one of the Day of Week values, to specify the last occurrence of this day in the month. For example, 1L indicates the last Sunday of the month.

For example:

- The string 0 0 13 \* \* ? indicates that you want to schedule the processor to run at 1:00 PM every day.

- The string `0 20 14 ? * MON-FRI` indicates that you want to schedule the processor to run at 2:20 PM every Monday through Friday.
- The string `0 15 10 ? * 6L 2011-2017` indicates that you want to schedule the processor to run at 10:15 AM, on the last Friday of every month, between 2011 and 2017.

For additional information and examples, see the [Cron Trigger Tutorial](#) in the Quartz documentation.

Next, the Scheduling Tab provides a configuration option named `Concurrent tasks`. This controls how many threads the Processor will use. Said a different way, this controls how many FlowFiles should be processed by this Processor at the same time. Increasing this value will typically allow the Processor to handle more data in the same amount of time. However, it does this by using system resources that then are not usable by other Processors. This essentially provides a relative weighting of Processors - it controls how much of the system's resources should be allocated to this Processor instead of other Processors. This field is available for most Processors. There are, however, some types of Processors that can only be scheduled with a single Concurrent task.

The "Run schedule" dictates how often the Processor should be scheduled to run. The valid values for this field depend on the selected Scheduling Strategy (see above). If using the Event driven Scheduling Strategy, this field is not available. When using the Timer driven Scheduling Strategy, this value is a time duration specified by a number followed by a time unit. For example, `1 second` or `5 mins`. The default value of `0 sec` means that the Processor should run as often as possible as long as it has data to process. This is true for any time duration of 0, regardless of the time unit (i.e., `0 sec`, `0 mins`, `0 days`). For an explanation of values that are applicable for the CRON driven Scheduling Strategy, see the description of the CRON driven Scheduling Strategy itself.

When configured for clustering, an Execution setting will be available. This setting is used to determine which node(s) the Processor will be scheduled to execute. Selecting 'All Nodes' will result in this Processor being scheduled on every node in the cluster. Selecting 'Primary Node' will result in this Processor being scheduled on the Primary Node only.

The right-hand side of the tab contains a slider for choosing the 'Run duration.' This controls how long the Processor should be scheduled to run each time that it is triggered. On the left-hand side of the slider, it is marked 'Lower latency' while the right-hand side is marked 'Higher throughput.' When a Processor finishes running, it must update the repository in order to transfer the FlowFiles to the next Connection. Updating the repository is expensive, so the more work that can be done at once before updating the repository, the more work the Processor can handle (Higher throughput). However, this means that the next Processor cannot start processing those FlowFiles until the previous Process updates this repository. As a result, the latency will be longer (the time required to process the FlowFile from beginning to end will be longer). As a result, the slider provides a spectrum from which the DFM can choose to favor Lower Latency or Higher Throughput.

### 1.1.6.3.3. Properties Tab

The Properties Tab provides a mechanism to configure Processor-specific behavior. There are no default properties. Each type of Processor must define which Properties make sense for its use case. Below, we see the Properties Tab for a RouteOnAttribute Processor:


Property	Value
Routing Strategy	Route to Property name

This Processor, by default, has only a single property: 'Routing Strategy.' The default value is 'Route to Property name.' Next to the name of this property is a small question-mark symbol (




). This help symbol is seen in other places throughout the User Interface, and it indicates that more information is available. Hovering over this symbol with the mouse will provide additional details about the property and the default value, as well as historical values that have been set for the Property.

Clicking on the value for the property will allow a DFM to change the value. Depending on the values that are allowed for the property, the user is either provided a drop-down from which to choose a value or is given a text area to type a value:



In the top-right corner of the tab is a button for adding a New Property. Clicking this button will provide the DFM with a dialog to enter the name and value of a new property. Not all Processors allow User-Defined properties. In processors that do not allow them, the Processor becomes invalid when User-Defined properties are applied. RouteOnAttribute, however, does allow User-Defined properties. In fact, this Processor will not be valid until the user has added a property.




Note that after a User-Defined property has been added, an icon will appear on the right-hand side of that row (



). Clicking it will remove the User-Defined property from the Processor.


Some processors also have an Advanced User Interface (UI) built into them. For example, the UpdateAttribute processor has an Advanced UI. To access the Advanced UI, click the *Advanced* button that appears at the bottom of the Configure Processor window. Only processors that have an Advanced UI will have this button.

Some processors have properties that refer to other components, such as Controller Services, which also need to be configured. For example, the GetHTTP processor has an SSLContextService property, which refers to the StandardSSLContextService controller service. When DFMs want to configure this property but have not yet created and configured the controller service, they have the option to create the service on the spot, as depicted in the image below. For more information about configuring Controller Services, see the [Controller Services](#) section.



#### 1.1.6.3.4. Comments Tab

The last tab in the Processor configuration dialog is the Comments tab. This tab simply provides an area for users to include whatever comments are appropriate for this component. Use of the Comments tab is optional:



#### 1.1.6.4. Additional Help

You can access additional documentation about each Processor's usage by right-clicking on the Processor and selecting 'Usage' from the context menu. Alternatively, select Help from the Global Menu in the top-right corner of the UI to display a Help page with all of the documentation, including usage documentation for all the Processors that are available. Click on the desired Processor to view usage documentation.

#### 1.1.6.5. Using Custom Properties with Expression Language

You can use NiFi Expression Language to reference FlowFile attributes, compare them to other values, and manipulate their values when you are creating and configuring dataflows. For more information on Expression Language, see the [Expression Language Guide](#).

In addition to using FlowFile attributes, system properties, and environment properties within Express Language, you can also define custom properties for Expression Language use. Defining custom properties gives you more flexibility in handling and processing dataflows. You can also create custom properties for connection, server, and service properties, for easier dataflow configuration.

NiFi properties have resolution precedence of which you should be aware when creating custom properties:

- Processor-specific attributes

- FlowFile properties
- FlowFile attributes
- From variable registry:
  - User defined properties (custom properties)
  - System properties
  - Operating System environment variables

When you are creating custom properties, ensure that each custom property contains a distinct property value, so that it is not overridden by existing environment properties, system properties, or FlowFile attributes.


There are two ways to use and manage custom properties:

- In the NiFi UI via the Variables window
- Referencing custom properties via 'nifi.properties'

### 1.1.6.5.1. Variables Window


Variables can be created and configured within the NiFi UI. The variables can be used in any field that supports Expression Language. NiFi automatically picks up new or modified variables created in the UI.

To access the Variables window, right-click on the canvas with nothing selected:




Select "Variables" from the Context Menu:






"Variables" is also available in the right-click Context Menu when a process group is selected:




### 1.1.6.5.1.1. Creating a Variable

In the Variables window, click the "+" button to create a new variable. Add a name:



and a value:



Select "Apply":

### Variables

Process Group NiFi Flow		Variables putfile_dir
Steps To Update Variables		Referencing Processors ⓘ
Identifying components affected	✓	■ PutFile - Root
Stopping affected Processors	✓	
Disabling affected Controller Services	✓	Referencing Controller Services ⓘ
Applying Updates	✓	None
Re-Enabling affected Controller Services	✓	
Restarting affected Processors	✓	Unauthorized Referencing Components ⓘ
		None

CLOSE

Steps to update the variable are performed (Identifying components affected, Stopping affected Processors, etc.). For example, the Referencing Processors section now lists the "PutFile-Root" processor. Selecting the name of the processor in the list will navigate to that processor on the canvas. Looking at the properties of the processor, `${putfile_dir}` is referenced by the Directory property:

**Configure Processor**

SETTINGS
SCHEDULING
PROPERTIES
COMMENTS

Required field +

Property	Value
Directory	\$(putfile_dir)
Conflict Resolution Strategy	fail
Create Missing Directories	true
Maximum File Count	No value set
Last Modified Time	No value set
Permissions	No value set
Owner	No value set
Group	No value set

CANCEL
APPLY

### 1.1.6.5.1.2. Variable Scope

Variables are scoped by the Process Group they are defined in and are available to any Processor defined at that level and below (i.e. any descendant Processors).

Variables in a descendant group override the value in a parent group. More specifically, if a variable `x` is declared at the root group and also declared inside a process group, components inside the process group will use the value of `x` defined in the process group.

For example, in addition to the `putfile_dir` variable that exists at the root process group, assume another `putfile_dir` variable was created within Process Group A. If one of the components within Process Group A references `putfile_dir`, both variables will be listed, but the `putfile_dir` from the root group will have a strikethrough indicating that is being overridden:

**Variables**

Process Group  
Process Group A

Scope	Name	Value
Process Group A	putfile_dir	/usr/local/pgA_directory
NiFi Flow	putfile_dir	/usr/local/root_directory

Variables  
putfile\_dir

Referencing Processors  
PutFile - PG-A

Referencing Controller Services  
None

Unauthorized Referencing Components  
None

CANCEL APPLY

A variable can only be modified for the process group it was created in, which is listed at the top of the Variables window. To modify a variable defined in a different process group, select the "arrow" icon in that variable's row:

**Variables**

Process Group  
Process Group A

Scope	Name	Value
Process Group A	putfile_dir	/usr/local/pgA_directory
NiFi Flow	putfile_dir	/usr/local/root_directory

Variables  
putfile\_dir

Referencing Processors  
PutFile - Root

Referencing Controller Services  
None

Unauthorized Referencing Components  
None

CANCEL APPLY

Current Process Group

Root Process Group

Go to Variable Window for Root Process Group

which will navigate to the Variables window for that process group:

Process Group  
NiFi Flow

Scope	Name	Value
NiFi Flow	drivers_dir	file:///drivers/jdbc/mysql-...
NiFi Flow	putfile_dir	/usr/local/root_directory

Variables  
putfile\_dir

Referencing Processors  
PutFile - Root

Referencing Controller Services  
None


Unauthorized Referencing Components  
None

CANCEL APPLY

### 1.1.6.5.1.3. Variable Permissions

Variable permissions are based solely on the privileges configured on the corresponding Process Group.

For example, if a user does not have access to View a process group, the Variables window can not be viewed for that process group:




If a user has access to View a process group but does not have access to Modify the process group, the variables can be viewed but not modified.


For information on how to manage privileges on components, see the [Access Policies](#) section in the System Administrator's Guide.

#### 1.1.6.5.1.4. Referencing Controller Services

In addition to Referencing Processors, the Variables window also displays Referencing Controller Services:



Selecting the name of the controller service will navigate to that controller service in the Configuration window:



### 1.1.6.5.1.5. Unauthorized Referencing Components

When View or Modify privileges are not given to a component that references a variable, the UUID of the component will be displayed in the Variables window:



**Variables**

Process Group  
NiFi Flow

Scope	Name	Value
NiFi Flow	drivers_dir	file:///drivers/jdbc/mysql-connector-java-5.1...
NiFi Flow	property1	./private
NiFi Flow	putfile_dir	/usr/local/root_directory

Variables  
property1

Referencing Processors ?  
None

Referencing Controller Services ?  
None

Unauthorized Referencing Components ?  
424d4e96-ae1c-310a-48cc-c7f45b8b74e6

CANCEL APPLY

In the above example, the variable `property1` is referenced by a processor that "user1" is not able to view:

### 1.1.6.5.2. Referencing Custom Properties via `nifi.properties`

Identify one or more sets of key/value pairs, and give them to your system administrator.

Once the new custom properties have been added, ensure that the `nifi.variable.registry.properties` field in the 'nifi.properties' file is updated with the custom properties location.

NiFi must be restarted for these updates to be picked up.

For more information, see the [Custom Properties](#) section in the System Administrator's Guide.

### 1.1.6.6. Controller Services


Controller Services are shared services that can be used by reporting tasks, processors, and other services to utilize for configuration or task execution.

Controller Services defined on the controller level are limited to reporting tasks and other services defined there. Controller Services for use by processors in your dataflow must be defined in the configuration of the root process group or sub-process group(s) where they will be used.

If your NiFi instance is secured, your ability to view and add Controller Services is dependent on the privileges assigned to you. If you do not have access to one or more Controller Services, you are not able to see or access it in the UI. Access privileges can be assigned on a global or Controller Service-specific basis (see [Accessing the UI with Multi-Tenant Authorization](#) for more information).

#### 1.1.6.6.1. Adding Controller Services for Reporting Tasks

To add a Controller Service for a reporting task, select Controller Settings from the Global Menu.



This displays the NiFi Settings window. The window has four tabs: General, Reporting Task Controller Services, Reporting Tasks and Registry Clients. The General tab provides settings for the overall maximum thread counts of the instance.

## NiFi Settings

GENERAL

REPORTING TASK CONTROLLER SERVICES

REPORTING TASKS

REGISTRY CLIENTS

Maximum Timer Driven Thread Count ?


10

Maximum Event Driven Thread Count ?

5

APPLY

To the right of the General tab is the Reporting Task Controller Services tab. From this tab, the DFM may click the "+" button in the upper-right corner to create a new Controller Service.



The Add Controller Service window opens. This window is similar to the Add Processor window. It provides a list of the available Controller Services on the right and a tag cloud, showing the most common category tags used for Controller Services, on the left. The DFM may click any tag in the tag cloud in order to narrow down the list of Controller Services to those that fit the categories desired. The DFM may also use the Filter field at the top-right of the window to search for the desired Controller Service or use the Source drop-down at the top-left to filter the list by the group who created them. Upon selecting a Controller

Service from the list, the DFM can see a description of the service below. Select the desired controller service and click Add, or simply double-click the name of the service to add it.

### Add Controller Service

Source

all groups ▼

- avro
- cache
- cluster
- comma
- connection
- csv
- database
- dbcp
- delimited
- distributed
- jdbc
- json
- parse
- pooling
- provider
- reader
- record
- recordset
- result
- row
- separated
- server
- set
- store
- writer

Displaying 10 of 28

Type	Version	Tags
AWSCredentialsProviderControllerService	1.2.0	credentials, provider, aws
CouchbaseClusterService	1.2.0	database, couchbase, connection, ...
DistributedMapCacheClientService	1.2.0	cluster, cache, distributed, state, m...
DistributedMapCacheServer	1.2.0	cluster, server, cache, key/value, dis...
DistributedSetCacheClientService	1.2.0	cluster, cache, set, distributed, state
DistributedSetCacheServer	1.2.0	server, cache, set, distributed, disti...
GPCredentialsControllerService	1.2.0	gcp, credentials, provider
HBase_1_1_2_ClientService	1.2.0	client, hbase
StandardSSLContextService	1.2.0	p12, jks, certificate, keystore, trusts...
JettyWebSocketServer	1.2.0	server, Jetty, WebSocket

**StandardSSLContextService 1.2.0** org.apache.nifi - nifi-ssl-context-service-nar

Standard implementation of the SSLContextService. Provides the ability to configure keystore and/or truststore properties once and reuse that configuration throughout the application

CANCEL
ADD

Once you have added a Controller Service, you can configure it by clicking the Configure button in the far-right column. Other buttons in this column include Enable, Remove and Access Policies.

The diagram shows four icons in a row: a gear (Configure), a lightning bolt (Enable), a trash can (Remove), and a magnifying glass (Access Policies). Blue arrows point from the text labels 'Configure', 'Enable', 'Remove', and 'Access Policies' to their respective icons.

You can obtain information about Controller Services by clicking the Usage and Alerts buttons in the left-hand column.

45



When the DFM clicks the Configure button, a Configure Controller Service window opens. It has three tabs: Settings, Properties, and Comments. This window is similar to the Configure Processor window. The Settings tab provides a place for the DFM to give the Controller Service a unique name (if desired). It also lists the UUID, Type, Bundle and Support information for the service and provides a list of other components (reporting tasks or other controller services) that reference the service.

### Configure Controller Service

SETTINGS

PROPERTIES

COMMENTS

**Name**  
StandardSSLContextService

**Id**  
172438f9-015c-1000-ecd6-ea699f013e59

**Type**  
StandardSSLContextService 1.2.0

**Bundle**  
org.apache.nifi - nifi-ssl-context-service-nar

**Supports Controller Service**

- SSLContextService 1.2.0 from org.apache.nifi - nifi-standard-services-api-nar

**Referencing Components** ⓘ

▼ **Reporting Tasks** (1)

- ⚠ SiteToSiteProvenanceReportingTask

CANCEL

APPLY

The Properties tab lists the various properties that apply to the particular controller service. As with configuring processors, the DFM may hover over the question mark icons to see more information about each property.

**Configure Controller Service**

SETTINGS

PROPERTIES

COMMENTS

**Required field** +

Property	Value
Keystore Filename	No value set
Keystore Password	Sensitive value set
Key Password	Sensitive value set
Keystore Type	No value set
Truststore Filename	No value set
Truststore Password	Sensitive value set
Truststore Type	No value set
SSL Protocol	TLS

The algorithm to use for this SSL context  
 Default value: TLS  
 Supports expression language: false


CANCEL

APPLY


The Comments tab is just an open-text field, where the DFM may include comments about the service. After configuring a Controller Service, click the Apply button to apply the configuration and close the window, or click the Cancel button to cancel the changes and close the window.

### 1.1.6.6.2. Adding Controller Services for Dataflows

To add a Controller Service for a dataflow, you can either right click a Process Group and select Configure, or click Configure from the Operate Palette.




When you click Configure from the Operate Palette with nothing selected on your canvas, you add a Controller Service for your Root Process Group. That Controller Service is then available to all nested Process Groups in your dataflow. When you select a Process Group on the canvas and then click Configure from either the Operate Palette or the Process Group context menu, the service will be available to all Processors and Controller Services defined in that Process Group and below.



Use the following steps to add a Controller Service:

1. Click Configure, either from the Operate Palette, or from the Process Group context menu. This displays the process group Configuration window. The window has two tabs: General and Controller Services. The General tab is for settings that pertain to general information about the process group. For example, if configuring the root process group, the DFM can provide a unique name for the overall dataflow, as well as comments that describe the flow (Note: this information is visible to any other NiFi instance that connects remotely to this instance (using Remote Process Groups, a.k.a., Site-to-Site)).



2. From the Process Group Configuration page, select the Controller Services tab.
3. Click the "+" button to display the Add Controller Service dialog.
4. Select the Controller Service desired, and click Add.
5. Perform any necessary Controller Service configuration tasks by clicking the Configure icon



( in the right-hand column. )

### 1.1.6.6.3. Enabling/Disabling Controller Services

After a Controller Service has been configured, it must be enabled in order to run. Do this using the Enable button



( in the far-right column of the Controller Services tab. In order to modify an )



existing/running controller service, the DFM needs to stop/disable it (as well as all referencing reporting tasks and controller services). Do this using the Disable button



( Rather than having to hunt down each component that is referenced by that controller service, the DFM has the ability to stop/disable them when disabling the controller service in question. When enabling a controller service, the DFM has the option to either start/enable the controller service and all referencing components or start/enable only the controller service itself.

**Enable Controller Service**

**Service**  
StandardSSLContextService

**Scope**

Service only ▼

Service only ?

Service and referencing components ?

**Referencing Components** ?


▼ **Reporting Tasks** (1)

▲ [SiteToSiteProvenanceReportingTask](#)


CANCEL
ENABLE

### 1.1.6.7. Reporting Tasks

Reporting Tasks run in the background to provide statistical reports about what is happening in the NiFi instance. The DFM adds and configures Reporting Tasks similar to the process for Controller Services. To add a Reporting Task, select Controller Settings from the Global Menu.



This displays the NiFi Settings window. Select the Reporting Tasks tab and click the "+" button in the upper-right corner to create a new Reporting Task.



The Add Reporting Task window opens. This window is similar to the Add Processor window. It provides a list of the available Reporting Tasks on the right and a tag cloud, showing the most common category tags used for Reporting Tasks, on the left. The DFM may click any tag in the tag cloud in order to narrow down the list of Reporting Tasks to those that fit the categories desired. The DFM may also use the Filter field at the top-right of the window to search for the desired Reporting Task or use the Source drop-down at the top-left to filter the list by the group who created them. Upon selecting a Reporting Task

from the list, the DFM can see a description of the task below. Select the desired reporting task and click Add, or simply double-click the name of the service to add it.

### Add Reporting Task

Source

all groups ▼

- ambari execute
- garbage collection gc groovy
- heap js jvm jython log lua
- luaj memory **metrics**
- monitor monitoring python
- reporting**
- restricted script **site**
- site to site** stats
- storage warning

Displaying 7 of 10

Type ▲	Version	Tags
AmbariReportingTask	1.2.0	ambari, metrics, reporting
ControllerStatusReportingTask	1.2.0	stats, log
DataDogReportingTask	1.2.0	datadog, metrics, reporting
ScriptedReportingTask	1.2.0	luaj, python, groovy, jython, js, lua, execute, rep...
SiteToSiteBulletinReportingTask	1.2.0	site, restricted, bulletin, site to site
SiteToSiteProvenanceReportingTask	1.2.0	lineage, site, provenance, restricted, tracking, ...
SiteToSiteStatusReportingTask	1.2.0	site, metrics, history, status, site to site

**SiteToSiteStatusReportingTask 1.2.0** org.apache.nifi - nifi-site-to-site-reporting-nar


Publishes Status events using the Site To Site protocol. The component type and name filter regexes form a union: only components matching both regexes will be reported. However, all process groups are recursively searched for matching components, regardless of whether the process group matches the component filters.

CANCEL
ADD

Once a Reporting Task has been added, the DFM may configure it by clicking the Edit button in the far-right column. Other buttons in this column include Start, Remove, State and Access Policies.



You can obtain information about Reporting Tasks by clicking the View Details, Usage, and Alerts buttons in the left-hand column.




When the DFM clicks the Edit button, a Configure Reporting Task window opens. It has three tabs: Settings, Properties, and Comments. This window is similar to the Configure Processor window. The Settings tab provides a place for the DFM to give the Reporting Task a unique name (if desired). It also lists the UUID, Type, and Bundle information for the task and provides settings for the task's Scheduling Strategy and Run Schedule (similar to the same settings in a processor). The DFM may hover the mouse over the question mark icons to see more information about each setting.


### Configure Reporting Task

SETTINGS   PROPERTIES   COMMENTS

Name  
SiteToSiteStatusReportingTask  Enabled

Scheduling Strategy   
Timer driven The strategy used to schedule this reporting

Id  
1d1f5ecd-015c-1000-bff7-40b54c50db99

Run Schedule   
5 mins

Type  
SiteToSiteStatusReportingTask 1.2.0

Bundle  
org.apache.nifi - nifi-site-to-site-reporting-nar

CANCEL   APPLY

The Properties tab lists the various properties that may be configured for the task. The DFM may hover the mouse over the question mark icons to see more information about each property.

**Configure Reporting Task**

SETTINGS

PROPERTIES

COMMENTS

Required field +

Property	Value
Destination URL	No value set
Input Port Name	No value set
SSL Context Service	No value set
Instance URL	http://\${hostname(true)}:8080/nifi
Compress Events	true
Communications Timeout	30 secs
Batch Size	1000
Platform	nifi
Component Type Filter Regex	(Processor ProcessGroup RemoteProcessGrou..
Component Name Filter Regex	.*

A regex specifying which component names to report. Any component name matching this regex will be included.

Default value: .\*

Supports expression language: true

CANCEL

APPLY

The Comments tab is just an open-text field, where the DFM may include comments about the task. After configuring the Reporting Task, click the Apply button to apply the configuration and close the window, or click the Cancel button to cancel the changes and close the window.

When you want to run the Reporting Task, click the Start button



).

### 1.1.6.8. Connecting Components

Once processors and other components have been added to the canvas and configured, the next step is to connect them to one another so that NiFi knows what to do with each FlowFile after it has been processed. This is accomplished by creating a Connection between each component. When the user hovers the mouse over the center of a component, a new Connection icon (



) appears:

GenerateFlowFile			
GenerateFlowFile 1.2.0 org.apache.nifi - nifi-standard-nar			
In	0 (0 bytes)		5 min
Read/Write	0 bytes / 0 bytes		5 min
Out	0 (0 bytes)		5 min
Tasks/Time	0 / 00:00:00.000		5 min

The user drags the Connection bubble from one component to another until the second component is highlighted. When the user releases the mouse, a 'Create Connection' dialog appears. This dialog consists of two tabs: 'Details' and 'Settings'. They are discussed in detail below. Note that it is possible to draw a connection so that it loops back on the same processor. This can be useful if the DFM wants the processor to try to re-process FlowFiles if they go down a failure Relationship. To create this type of looping connection, simply drag the connection bubble away and then back to the same processor until it is highlighted. Then release the mouse and the same 'Create Connection' dialog appears.

### 1.1.6.8.1. Details Tab

The Details Tab of the 'Create Connection' dialog provides information about the source and destination components, including the component name, the component type, and the Process Group in which the component lives:

**Create Connection**

DETAILS

SETTINGS

**From Processor**  
GenerateFlowFile  
GenerateFlowFile

**Within Group**  
NiFi Flow

**For Relationships**  
 success

**To Processor**  
LogAttribute  
LogAttribute

**Within Group**  
NiFi Flow

CANCEL

ADD

Additionally, this tab provides the ability to choose which Relationships should be included in this Connection. At least one Relationship must be selected. If only one Relationship is available, it is automatically selected.

If multiple Connections are added with the same Relationship, any FlowFile that is routed to that Relationship will automatically be `cloned`, and a copy will be sent to each of those Connections.

### 1.1.6.8.2. Settings


The Settings Tab provides the ability to configure the Connection's name, FlowFile expiration, Back Pressure thresholds, and Prioritization:

The screenshot shows the 'Create Connection' dialog box with the 'SETTINGS' tab selected. The 'Name' field is empty. The 'Id' field shows 'No value set'. The 'FlowFile Expiration' field is set to '0 sec'. The 'Back Pressure Object Threshold' field is set to '10000'. The 'Back Pressure Data Size Threshold' field is set to '1 GB'. The 'Available Prioritizers' list includes: FirstInFirstOutPrioritizer, NewestFlowFileFirstPrioritizer, OldestFlowFileFirstPrioritizer, and PriorityAttributePrioritizer. The 'Selected Prioritizers' field is empty. The 'CANCEL' and 'ADD' buttons are at the bottom right.

The Connection name is optional. If not specified, the name shown for the Connection will be names of the Relationships that are active for the Connection.

#### 1.1.6.8.2.1. FlowFile Expiration

FlowFile expiration is a concept by which data that cannot be processed in a timely fashion can be automatically removed from the flow. This is useful, for example, when the volume of data is expected to exceed the volume that can be sent to a remote site. In this case, the expiration can be used in conjunction with Prioritizers to ensure that the highest priority data is processed first and then anything that cannot be processed within a certain time period (one hour, for example) can be dropped. The expiration period is based on the time that the data entered the NiFi instance. In other words, if the file expiration on a given connection is set to '1 hour', and a file that has been in the NiFi instance for one hour reaches that connection, it will expire. The default value of 0 sec indicates that the data will never expire. When a file expiration other than '0 sec' is set, a small clock icon appears on the connection label, so the DFM can see it at-a-glance when looking at a flow on the canvas.




### 1.1.6.8.2.2. Back Pressure

NiFi provides two configuration elements for Back Pressure. These thresholds indicate how much data should be allowed to exist in the queue before the component that is the source of the Connection is no longer scheduled to run. This allows the system to avoid being overrun with data. The first option provided is the "Back pressure object threshold." This is the number of FlowFiles that can be in the queue before back pressure is applied. The second configuration option is the "Back pressure data size threshold." This specifies the maximum amount of data (in size) that should be queued up before applying back pressure. This value is configured by entering a number followed by a data size (B for bytes, KB for kilobytes, MB for megabytes, GB for gigabytes, or TB for terabytes).


By default each new connection added will have a default Back Pressure Object Threshold of 10,000 objects and Back Pressure Data Size Threshold of 1 GB.

When back pressure is enabled, small progress bars appear on the connection label, so the DFM can see it at-a-glance when looking at a flow on the canvas. The progress bars change color based on the queue percentage: Green (0-60%), Yellow (61-85%) and Red (86-100%).



Hovering your mouse over a bar displays the exact percentage.





When the queue is completely full, the Connection is highlighted in red.



### 1.1.6.8.2.3. Prioritization


The right-hand side of the tab provides the ability to prioritize the data in the queue so that higher priority data is processed first. Prioritizers can be dragged from the top ('Available prioritizers') to the bottom ('Selected prioritizers'). Multiple prioritizers can be selected. The prioritizer that is at the top of the 'Selected prioritizers' list is the highest priority. If two FlowFiles have the same value according to this prioritizer, the second prioritizer will determine which FlowFile to process first, and so on. If a prioritizer is no longer desired, it can then be dragged from the 'Selected prioritizers' list to the 'Available prioritizers' list.

The following prioritizers are available:


- **FirstInFirstOutPrioritizer:** Given two FlowFiles, the one that reached the connection first will be processed first.
- **NewestFlowFileFirstPrioritizer:** Given two FlowFiles, the one that is newest in the dataflow will be processed first.
- **OldestFlowFileFirstPrioritizer:** Given two FlowFiles, the one that is oldest in the dataflow will be processed first. 'This is the default scheme that is used if no prioritizers are selected.'
- **PriorityAttributePrioritizer:** Given two FlowFiles that both have a "priority" attribute, the one that has the highest priority value will be processed first. Note that an UpdateAttribute processor should be used to add the "priority" attribute to the FlowFiles before they reach a connection that has this prioritizer set. Values for the "priority" attribute may be alphanumeric, where "a" is a higher priority than "z", and "1" is a higher priority than "9", for example.

#### 1.1.6.8.2.4. Changing Configuration and Context Menu Options

After a connection has been drawn between two components, the connection's configuration may be changed, and the connection may be moved to a new destination; however, the processors on either side of the connection must be stopped before a configuration or destination change may be made.



To change a connection's configuration or interact with the connection in other ways, right-click on the connection to open the connection context menu.




The following options are available:

- **Configure:** This option allows the user to change the configuration of the connection.
- **View status history:** This option opens a graphical representation of the connection's statistical information over time.
- **List queue:** This option lists the queue of FlowFiles that may be waiting to be processed.
- **Go to source:** This option can be useful if there is a long distance between the connection's source and destination components on the canvas. By clicking this option, the view of the canvas will jump to the source of the connection.
- **Go to destination:** Similar to the "Go to source" option, this option changes the view to the destination component on the canvas and can be useful if there is a long distance between two connected components.
- **Bring to front:** This option brings the connection to the front of the canvas if something else (such as another connection) is overlapping it.
- **Empty queue:** This option allows the DFM to clear the queue of FlowFiles that may be waiting to be processed. This option can be especially useful during testing, when the DFM is not concerned about deleting data from the queue. When this option is selected, users must confirm that they want to delete the data in the queue.
- **Delete:** This option allows the DFM to delete a connection between two components. Note that the components on both sides of the connection must be stopped and the connection must be empty before it can be deleted.


### 1.1.6.8.3. Bending Connections

To add a bend point (or elbow) to an existing connection, simply double-click on the connection in the spot where you want the bend point to be. Then, you can use the mouse to grab the bend point and drag it so that the connection is bent in the desired way. You can add as many bend points as you want. You can also use the mouse to drag and move the label on the connection to any existing bend point. To remove a bend point, simply double-click it again.




### 1.1.6.9. Processor Validation

Before trying to start a Processor, it's important to make sure that the Processor's configuration is valid. A status indicator is shown in the top-left of the Processor. If the Processor is invalid, the indicator will show a yellow Warning indicator with an exclamation mark indicating that there is a problem:



In this case, hovering over the indicator icon with the mouse will provide a tooltip showing all of the validation errors for the Processor. Once all of the validation errors have been addressed, the status indicator will change to a Stop icon, indicating that the Processor is valid and ready to be started but currently is not running:



### 1.1.6.10. Site-to-Site

When sending data from one instance of NiFi to another, there are many different protocols that can be used. The preferred protocol, though, is the NiFi Site-to-Site Protocol. Site-to-Site makes it easy to securely and efficiently transfer data to/from nodes in one NiFi instance or data producing application to nodes in another NiFi instance or other consuming application.

Using Site-to-Site provides the following benefits:

- Easy to configure
  - After entering the URL of the remote NiFi instance, the available ports (endpoints) are automatically discovered and provided in a drop-down list
- Secure
  - Site-to-Site optionally makes use of Certificates in order to encrypt data and provide authentication and authorization. Each port can be configured to allow only specific users, and only those users will be able to see that the port even exists. For information on configuring the Certificates, see the [Security Configuration](#) section of the System Administrator's Guide.
- Scalable
  - As nodes in the remote cluster change, those changes are automatically detected and data is scaled out across all nodes in the cluster.
- Efficient
  - Site-to-Site allows batches of FlowFiles to be sent at once in order to avoid the overhead of establishing connections and making multiple round-trip requests between peers.
- Reliable
  - Checksums are automatically produced by both the sender and receiver and compared after the data has been transmitted, in order to ensure that no corruption has occurred. If the checksums don't match, the transaction will simply be canceled and tried again.
- Automatically load balanced
  - As nodes come online or drop out of the remote cluster, or a node's load becomes heavier or lighter, the amount of data that is directed to that node will automatically be adjusted.
- FlowFiles maintain attributes
  - When a FlowFile is transferred over this protocol, all of the FlowFile's attributes are automatically transferred with it. This can be very advantageous in many situations, as all of the context and enrichment that has been determined by one instance of NiFi travels with the data, making for easy routing of the data and allowing users to easily inspect the data.
- Adaptable
  - As new technologies and ideas emerge, the protocol for handling Site-to-Site communications are able to change with them. When a connection is made to a remote NiFi instance, a handshake is performed in order to negotiate which protocol and which version of the protocol will be used. This allows new capabilities to be added while still maintaining backward compatibility with all older instances.

Additionally, if a vulnerability or deficiency is ever discovered in a protocol, it allows a newer version of NiFi to forbid communication over the compromised versions of the protocol.

Site-to-Site is a protocol transferring data between two NiFi instances. Both end can be a standalone NiFi or a NiFi cluster. In this section, the NiFi instance initiates the communications is called *Site-to-Site client NiFi instance* and the other end as *Site-to-Site server NiFi instance* to clarify what configuration needed on each NiFi instances.

A NiFi instance can be both client and server for Site-to-Site protocol, however, it can only be a client or server within a specific Site-to-Site communication. For example, if there are three NiFi instances A, B and C. A pushes data to B, and B pulls data from C. *A - push # B # pull - C*. Then B is not only a *server* in the communication between A and B, but also a *client* in B and C.

It is important to understand which NiFi instance will be the client or server in order to design your data flow, and configure each instance accordingly. Here is a summary of what components run on which side based on data flow direction:

- Push: a client *sends* data to a Remote Process Group, the server *receives* it with an Input Port
- Pull: a client *receives* data from a Remote Process Group, the server *sends* data through an Output Port

#### 1.1.6.10.1. Configure Site-to-Site client NiFi instance

**Remote Process Group:** In order to communicate with a remote NiFi instance via Site-to-Site, simply drag a [Remote Process Group](#) onto the canvas and enter the URL of the remote NiFi instance (for more information on the components of a Remote Process Group, see [Remote Process Group Transmission](#) section of this guide.) The URL is the same URL you would use to go to that instance's User Interface. At that point, you can drag a connection to or from the Remote Process Group in the same way you would drag a connection to or from a Processor or a local Process Group. When you drag the connection, you will have a chance to choose which Port to connect to. Note that it may take up to one minute for the Remote Process Group to determine which ports are available.

If the connection is dragged starting from the Remote Process Group, the ports shown will be the Output Ports of the remote group, as this indicates that you will be pulling data from the remote instance. If the connection instead ends on the Remote Process Group, the ports shown will be the Input Ports of the remote group, as this implies that you will be pushing data to the remote instance.

If the remote instance is configured to use secure data transmission, you will see only ports that you are authorized to communicate with. For information on configuring NiFi to run securely, see the [System Administrator's Guide](#).

**Transport Protocol:** On a Remote Process Group creation or configuration dialog, you can choose Transport Protocol to use for Site-to-Site communication as shown in the following image:

**Configure Remote Process Group**

Name  
http://localhost:8080/nifi/

Id  
a43a9b4e-015a-1000-6997-39a4e265a8b8

URLs  
http://localhost:8080/nifi/

Transport Protocol <span style="font-size: small;">?</span>	Local Network Interface <span style="font-size: small;">?</span>
RAW <span style="float: right;">▼</span>	<input type="text"/>
HTTP Proxy Server Hostname <span style="font-size: small;">?</span>	HTTP Proxy Server Port <span style="font-size: small;">?</span>
<input type="text"/>	<input type="text"/>
HTTP Proxy User <span style="font-size: small;">?</span>	HTTP Proxy Password <span style="font-size: small;">?</span>
<input type="text"/>	<input type="text"/>
Communications Timeout <span style="font-size: small;">?</span>	Yield Duration <span style="font-size: small;">?</span>
30 sec	10 sec

CANCEL
APPLY

By default, it is set to *RAW* which uses raw socket communication using a dedicated port. *HTTP* transport protocol is especially useful if the remote NiFi instance is in a restricted network that only allow access through HTTP(S) protocol or only accessible from a specific HTTP Proxy server. For accessing through a HTTP Proxy Server, BASIC and DIGEST authentication are supported.

**Local Network Interface:** In some cases, it may be desirable to prefer one network interface over another. For example, if a wired interface and a wireless interface both exist, the wired interface may be preferred. This can be configured by specifying the name of the network interface to use in this box. If the value entered is not valid, the Remote Process Group will not be valid and will not communicate with other NiFi instances until this is resolved.

### 1.1.6.10.2. Configure Site-to-Site server NiFi instance

**Retrieve Site-to-Site Details:** If your NiFi is running securely, in order for another NiFi instance to retrieve information from your instance, it needs to be added to the Global Access "retrieve site-to-site details" policy. This will allow the other instance to query your instance for details such as name, description, available peers (nodes when clustered), statistics, OS port information and available Input and Output ports. Utilizing Input and Output ports in a secured instance requires additional policy configuration as described below.

**Input Port:** In order to allow another NiFi instance to push data to your local instance, you can simply drag an [Input Port](#) onto the Root Process Group of your canvas. After entering a

name for the port, it will be added to your flow. You can now right-click on the Input Port and choose Configure in order to adjust the name and the number of concurrent tasks that are used for the port.

If Site-to-Site is configured to run securely, you will need to manage the port's "receive data via site-to-site" component access policy. Only those users who have been added to the policy will be able to communicate with the port.

**Output Port:** Similar to an Input Port, a DataFlow Manager may choose to add an [Output Port](#) to the Root Process Group. The Output Port allows an authorized NiFi instance to remotely connect to your instance and pull data from the Output Port. Configuring the Output Port and managing the port's access policies will again allow the DFM to control how many concurrent tasks are allowed, as well as which users are authorized to pull data from the instance being configured.

In addition to other instances of NiFi, some other applications may use a Site-to-Site client in order to push data to or receive data from a NiFi instance. For example, NiFi provides an Apache Storm spout and an Apache Spark Receiver that are able to pull data from NiFi's Root Group Output Ports.

For information on how to enable and configure Site-to-Site on a NiFi instance, see the [Site-to-Site Properties](#) section of the System Administrator's Guide.

For information on how to configure access policies, see the [Access Policies](#) section of the System Administrator's Guide.

### 1.1.6.11. Example Dataflow

This section has described the steps required to build a dataflow. Now, to put it all together. The following example dataflow consists of just two processors: GenerateFlowFile and LogAttribute. These processors are normally used for testing, but they can also be used to build a quick flow for demonstration purposes and see NiFi in action.


After you drag the GenerateFlowFile and LogAttribute processors to the canvas and connect them (using the guidelines provided above), configure them as follows:

- Generate FlowFile
  - On the Scheduling tab, set Run schedule to: 5 sec. Note that the GenerateFlowFile processor can create many FlowFiles very quickly; that's why setting the Run schedule is important so that this flow does not overwhelm the system NiFi is running on.
  - On the Properties tab, set File Size to: 10 kb
- Log Attribute
  - On the Settings tab, under Auto-terminate relationships, select the checkbox next to Success. This will terminate FlowFiles after this processor has successfully processed them.
  - Also on the Settings tab, set the Bulletin level to Info. This way, when the dataflow is running, this processor will display the bulletin icon (see [Anatomy of a Processor](#)), and



the user may hover over it with the mouse to see the attributes that the processor is logging.

The dataflow should look like the following:



Now see the following section on how to start and stop the dataflow. When the dataflow is running, be sure to note the statistical information that is displayed on the face of each processor (see [Anatomy of a Processor](#)).

## 1.1.7. Command and Control of the DataFlow

When a component is added to the NiFi canvas, it is in the Stopped state. In order to cause the component to be triggered, the component must be started. Once started, the component can be stopped at any time. From a Stopped state, the component can be configured, started, or disabled.

### 1.1.7.1. Starting a Component

In order to start a component, the following conditions must be met:

- The component's configuration must be valid.
- All defined Relationships for the component must be connected to another component or auto-terminated.
- The component must be stopped.
- The component must be enabled.
- The component must have no active tasks. For more information about active tasks, see the "Anatomy of ..." sections under [Monitoring of DataFlow](#) ([Anatomy of a Processor](#), [Anatomy of a Process Group](#), [Anatomy of a Remote Process Group](#)).

Components can be started by selecting all of the components to start and then clicking the Start button (



) in the Operate Palette or by right-clicking a single component and choosing Start from the context menu.

If starting a Process Group, all components within that Process Group (including child Process Groups) will be started, with the exception of those components that are invalid or disabled.

Once started, the status indicator of a Processor will change to a Play symbol (



).

### 1.1.7.2. Stopping a Component

A component can be stopped any time that it is running. A component is stopped by right-clicking on the component and clicking Stop from the context menu, or by selecting the component and clicking the Stop button (



) in the Operate Palette.

If a Process Group is stopped, all of the components within the Process Group (including child Process Groups) will be stopped.

Once stopped, the status indicator of a component will change to the Stop symbol (



).

Stopping a component does not interrupt its currently running tasks. Rather, it stops scheduling new tasks to be performed. The number of active tasks is shown in the top-right corner of the Processor (See [Anatomy of a Processor](#) for more information).

### 1.1.7.3. Enabling/Disabling a Component

When a component is enabled, it is able to be started. Users may choose to disable components when they are part of a dataflow that is still being assembled, for example. Typically, if a component is not intended to be run, the component is disabled, rather than being left in the Stopped state. This helps to distinguish between components that are intentionally not running and those that may have been stopped temporarily (for instance, to change the component's configuration) and inadvertently were never restarted.

When it is desirable to re-enable a component, it can be enabled by selecting the component and clicking the Enable button (



) in the Operate Palette. This is available only when the selected component or components are disabled. Alternatively, a component can be enabled by checking the checkbox next to the "Enabled" option in the Settings tab of the Processor configuration dialog or the configuration dialog for a Port.

Once enabled, the component's status indicator will change to either Invalid (



) or Stopped (



), depending on whether or not the component is valid.

A component is then disabled by selecting the component and clicking the Disable button (



) in the Operate Palette, or by clearing the checkbox next to the "Enabled" option in the Settings tab of the Processor configuration dialog or the configuration dialog for a Port.

Only Ports and Processors can be enabled and disabled.

### 1.1.7.4. Remote Process Group Transmission

Remote Process Groups provide a mechanism for sending data to or retrieving data from a remote instance of NiFi. When a Remote Process Group (RPG) is added to the canvas, it is added with the Transmission Disabled, as indicated by the icon (



) in the top-left corner. When Transmission is Disabled, it can be enabled by right-clicking on the RPG and clicking the "Enable Transmission" menu item. This will cause all ports for which there is a Connection to begin transmitting data. This will cause the status indicator to then change to the Transmission Enabled icon (



).

If there are problems communicating with the Remote Process Group, a Warning indicator (



) may instead be present in the top-left corner. Hovering over this Warning indicator with the mouse will provide more information about the problem.

#### 1.1.7.4.1. Individual Port Transmission

There are times when the DFM may want to either enable or disable transmission for only a specific Port within the Remote Process Group. This can be accomplished by right-clicking on the Remote Process Group and choosing the "Remote ports" menu item. This provides a configuration dialog from which each Port can be configured:

**Remote Process Group Ports**

<p><b>Name</b> NiFi Flow</p>	<p><b>URL</b> http://nifi-01:8080/nifi</p>
<div style="border: 1px solid #ccc; padding: 5px;"> <p><b>Input ports</b></p> <div style="margin-bottom: 10px;"> <p><input checked="" type="checkbox"/> <b>Tweets</b> No description specified.</p> <p>Concurrent tasks ⓘ 1      Compressed No</p> </div> <div> <p><input type="checkbox"/> <b>Provenance Data</b> No description specified.</p> <p>Concurrent tasks ⓘ 1      Compressed No</p> </div> </div>	<div style="border: 1px solid #ccc; padding: 5px; height: 30px;"> <p><b>Output ports</b></p> </div>

CLOSE

The left-hand side lists all of the Input Ports that the remote instance of NiFi allows data to be sent to. The right-hand side lists all of the Output Ports from which this instance is able to pull data. If the remote instance is using secure communications (the URL of the NiFi instance begins with `https://`, rather than `http://`), any Ports that the remote instance has not made available to this instance will not be shown.

If a Port that is expected to be shown is not shown in this dialog, ensure that the instance has proper permissions and that the Remote Process Group's flow is current. This can be checked by closing the Port Configuration Dialog and looking at the bottom-right corner of the Remote Process Group. The date at which the flow was last refreshed is shown. If the flow appears to be outdated, it can be updated by right-clicking on the Remote Process Group and selecting "Refresh flow." (See [Anatomy of a Remote Process Group](#) for more information).

Each Port is shown with the Port name, followed by its description, currently configured number of Concurrent tasks, and whether or not data sent to this port will be compressed. To the left of this information is a switch to turn the Port on or off. Those Ports that have no Connections attached to them are grayed out:

**Remote Process Group Ports**

Name: NiFi Flow **Currently Transmitting**

URL: `http://nifi-01:8080/nifi`

Input ports		Output ports	
<input checked="" type="checkbox"/>	<b>Tweets</b> No description specified.	Concurrent tasks 1	Compressed No
<input type="checkbox"/>	<b>Provenance Data</b> No description specified.	Concurrent tasks 1	Compressed No

**Not Connected**

CLOSE

The on/off switch provides a mechanism to enable and disable transmission for each Port in the Remote Process Group independently. Those Ports that are connected but are not currently transmitting can be configured by clicking the pencil icon (



) below the on/off switch. Clicking this icon will allow the DFM to change the number of

Concurrent tasks and whether or not compression should be used when transmitting data to or from this Port.


## 1.1.8. Navigating within a DataFlow

NiFi provides various mechanisms for getting around a dataflow. The [NiFi User Interface](#) section describes various ways to navigate around the NiFi canvas; however, once a flow exists on the canvas, there are additional ways to get from one component to another. When multiple Process Groups exist in a flow, breadcrumbs appear at the bottom of the screen, providing a way to navigate between them. In addition, to enter a Process Group that is currently visible on the canvas, simply double-click it, thereby "drilling down" into it. Connections also provide a way to jump from one location to another within the flow. Right-click on a connection and select "Go to source" or "Go to destination" in order to jump to one end of the connection or another. This can be very useful in large, complex dataflows, where the connection lines may be long and span large areas of the canvas. Finally, all components provide the ability to jump forward or backward within the flow. Right-click any component (e.g., a processor, process group, port, etc.) and select either "Upstream connections" or "Downstream connections". A dialog window will open, showing the available upstream or downstream connections that the user may jump to. This can be especially useful when trying to follow a dataflow in a backward direction. It is typically easy to follow the path of a dataflow from start to finish, drilling down into nested process groups; however, it can be more difficult to follow the dataflow in the other direction.

### 1.1.8.1. Component Linking

A hyperlink can be used to navigate directly to a component on the NiFi canvas. This is especially useful when [Multi-Tenant Authorization](#) is configured. For example, a URL can be given to a user to direct them to the specific process group to which they have privileges.

The default URL for a NiFi instance is `http://<hostname>:8080/nifi`, which points to the root process group. When a component is selected on the canvas, the URL is updated with the component's process group id and component id in the form `http://<hostname>:8080/nifi/?processGroupId=<UUID>&componentIds=<UUIDs>;`. In the following screenshot, the GenerateFlowFile processor in the process group PG1 is the selected component:




Linking to multiple components on the canvas is supported, with the restriction that the length of the URL cannot exceed a 2000 character limit.

### 1.1.8.2. Component Alignment


Components on the NiFi canvas can be aligned to more precisely arrange your dataflow. To do this, first select all the components you want to align. Then right-click to see the context menu and select "Align vertically" or "Align horizontally" depending on your desired result.

#### 1.1.8.2.1. Align Vertically

Here is an example of aligning components vertically on your canvas. With all components selected/highlighted, right-click:




and select "Align vertically" to achieve these results:




### 1.1.8.2.2. Align Horizontally

Here is an example of aligning components horizontally on your canvas. With all components selected/highlighted, right-click:





and select "Align horizontally" to achieve these results:




## 1.1.9. Monitoring of DataFlow




NiFi provides a great deal of information about the DataFlow in order to monitor its health and status. The Status bar provides information about the overall system health (see [NiFi User Interface](#)). Processors, Process Groups, and Remote Process Groups provide fine-grained details about their operations. Connections and Process Groups provide information about the amount of data in their queues. The Summary Page provides information about all of the components on the canvas in a tabular format and also provides System Diagnostics that include disk usage, CPU utilization, and Java Heap and Garbage Collection information. In a clustered environment, this information is available per-node or as aggregates across the entire cluster. We will explore each of these monitoring artifacts below.

### 1.1.9.1. Anatomy of a Processor

NiFi provides a significant amount of information about each Processor on the canvas. The following diagram shows the anatomy of a Processor:



The image outlines the following elements:

- Processor Type:** NiFi provides several different types of Processors in order to allow for a wide range of tasks to be performed. Each type of Processor is designed to perform one specific task. The Processor type (PutFile, in this example) describes the task that this Processor performs. In this case, the Processor writes a FlowFile to disk - or "Puts" a FlowFile to a File.
- Bulletin Indicator:** When a Processor logs that some event has occurred, it generates a Bulletin to notify those who are monitoring NiFi via the User Interface. The DFM is able to configure which bulletins should be displayed in the User Interface by updating the "Bulletin level" field in the "Settings" tab of the Processor configuration dialog. The default value is `WARN`, which means that only warnings and errors will be displayed in the UI. This icon is not present unless a Bulletin exists for this Processor. When it is present, hovering over the icon with the mouse will provide a tooltip explaining the message provided by the Processor as well as the Bulletin level. If the instance of NiFi is clustered, it will also show the Node that emitted the Bulletin. Bulletins automatically expire after five minutes.
- Status Indicator:** Shows the current Status of the Processor. The following indicators are possible:
  -  **Running:**  
The Processor is currently running.
  -  **Stopped:**  
The Processor is valid and enabled but is not running.
  -  **Invalid:**  
The Processor is enabled but is not currently valid and cannot be started. Hovering over this icon will provide a tooltip indicating why the Processor is not valid.

**Disabled:**

The Processor is not running and cannot be started until it has been enabled. This status does not indicate whether or not the Processor is valid.

- **Processor Name:** This is the user-defined name of the Processor. By default, the name of the Processor is the same as the Processor Type. In the example, this value is "Copy to / review".
- **Active Tasks:** The number of tasks that this Processor is currently executing. This number is constrained by the "Concurrent tasks" setting in the "Scheduling" tab of the Processor configuration dialog. Here, we can see that the Processor is currently performing one task. If the NiFi instance is clustered, this value represents the number of tasks that are currently executing across all nodes in the cluster.
- **5-Minute Statistics:** The Processor shows several different statistics in tabular form. Each of these statistics represents the amount of work that has been performed in the past five minutes. If the NiFi instance is clustered, these values indicate how much work has been done by all of the Nodes combined in the past five minutes. These metrics are:
  - **In:** The amount of data that the Processor has pulled from the queues of its incoming Connections. This value is represented as <count> (<size>) where <count> is the number of FlowFiles that have been pulled from the queues and <size> is the total size of those FlowFiles' content. In this example, the Processor has pulled 29 FlowFiles from the input queues, for a total of 14.16 megabytes (MB).
  - **Read/Write:** The total size of the FlowFile content that the Processor has read from disk and written to disk. This provides valuable information about the I/O performance that this Processor requires. Some Processors may only read the data without writing anything while some will not read the data but will only write data. Others will neither read nor write data, and some Processors will both read and write data. In this example, we see that in the past five minutes, this Processor has read 4.88 MB of the FlowFile content and has written 4.88 MB as well. This is what we would expect, since this Processor simply copies the contents of a FlowFile to disk. Note, however, that this is not the same as the amount of data that it pulled from its input queues. This is because some of the files that it pulled from the input queues already exist in the output directory, and the Processor is configured to route FlowFiles to failure when this occurs. Therefore, for those files which already existed in the output directory, data was neither read nor written to disk.
  - **Out:** The amount of data that the Processor has transferred to its outbound Connections. This does not include FlowFiles that the Processor removes itself, or FlowFiles that are routed to connections that are auto-terminated. Like the "In" metric above, this value is represented as <count> (<size>) where <count> is the number of FlowFiles that have been transferred to outbound Connections and <size> is the total size of those FlowFiles' content. In this example, all of the Relationships are configured to be auto-terminated, so no FlowFiles are reported as having been transferred Out.
  - **Tasks/Time:** The number of times that this Processor has been triggered to run in the past 5 minutes, and the amount of time taken to perform those tasks. The format of the time is <hour>:<minute>:<second>. Note that the amount of time taken can exceed five minutes, because many tasks can be executed in parallel. For instance, if

the Processor is scheduled to run with 60 Concurrent tasks, and each of those tasks takes one second to complete, it is possible that all 60 tasks will be completed in a single second. However, in this case we will see the Time metric showing that it took 60 seconds, instead of 1 second. This time can be thought of as "System Time," or said another way, this value is 60 seconds because that's the amount of time it would have taken to perform the action if only a single concurrent task were used.

### 1.1.9.2. Anatomy of a Process Group





The Process Group provides a mechanism for grouping components together into a logical construct in order to organize the DataFlow in a way that makes it more understandable from a higher level. The following image highlights the different elements that make up the anatomy of a Process Group:





The Process Group consists of the following elements:

- **Name:** This is the user-defined name of the Process Group. This name is set when the Process Group is added to the canvas. The name can later be changed by right-clicking on the Process Group and clicking the "Configure" menu option. In this example, the name of the Process Group is "Process Group ABC."
- **Bulletin Indicator:** When a child component of a Process Group emits a bulletin, that bulletin is propagated to the component's parent Process Group, as well. When any component has an active Bulletin, this indicator will appear, allowing the user to hover over the icon with the mouse to see the Bulletin.
- **Active Tasks:** The number of tasks that are currently executing by the components within this Process Group. Here, we can see that the Process Group is currently performing two tasks. If the NiFi instance is clustered, this value represents the number of tasks that are currently executing across all nodes in the cluster.
- **Statistics:** Process Groups provide statistics about the amount of data that has been processed by the Process Group in the past 5 minutes as well as the amount of data

currently enqueued within the Process Group. The following elements comprise the "Statistics" portion of a Process Group:

- **Queued:** The number of FlowFiles currently enqueued within the Process Group. This field is represented as <count> (<size>) where <count> is the number of FlowFiles that are currently enqueued in the Process Group and <size> is the total size of those FlowFiles' content. In this example, the Process Group currently has 26 FlowFiles enqueued with a total size of 12.7 megabytes (MB).
- **In:** The number of FlowFiles that have been transferred into the Process Group through all of its Input Ports over the past 5 minutes. This field is represented as <count> / <size> # <ports> where <count> is the number of FlowFiles that have entered the Process Group in the past 5 minutes, <size> is the total size of those FlowFiles' content and <ports> is the number of Input Ports. In this example, 8 FlowFiles have entered the Process Group with a total size of 800 KB and two Input Ports exist.
- **Read/Write:** The total size of the FlowFile content that the components within the Process Group have read from disk and written to disk. This provides valuable information about the I/O performance that this Process Group requires. In this example, we see that in the past five minutes, components within this Process Group have read 14.72 MB of the FlowFile content and have written 14.8 MB.
- **Out:** The number of FlowFiles that have been transferred out of the Process Group through its Output Ports over the past 5 minutes. This field is represented as <ports> # <count> (<size>) where <ports> is the number of Output Ports, <count> is the number of FlowFiles that have exited the Process Group in the past 5 minutes and <size> is the total size of those FlowFiles' content. In this example, there are three Output Ports, 16 FlowFiles have exited the Process Group and their total size is 78.57 KB.
- **Component Counts:** The Component Counts element provides information about how many components of each type exist within the Process Group. The following provides information about each of these icons and their meanings:
  -  **Transmitting Ports:** The number of Remote Process Group Ports that currently are configured to transmit data to remote instances of NiFi or pull data from remote instances of NiFi. **Transmitting**
  -  **Non-Transmitting Ports:** The number of Remote Process Group Ports that are currently connected to components within this Process Group but currently have their transmission disabled. **Non-**
  -  **Components:** The number of Processors, Input Ports, and Output Ports that are currently running within this Process Group. **Running**
  -  **Components:** The number of Processors, Input Ports, and Output Ports that are currently not running but are valid and enabled. These components are ready to be started. **Stopped**


- 
**Invalid**

**Components:** The number of Processors, Input Ports, and Output Ports that are enabled but are currently not in a valid state. This may be due to misconfigured properties or missing Relationships.
- 
**Disabled**

**Components:** The number of Processors, Input Ports, and Output Ports that are currently disabled. These components may or may not be valid. If the Process Group is started, these components will not cause any errors but will not be started.
- Version State Counts:** The Version State Counts element provides information about how many versioned process groups are within the Process Group. See [Version States](#) for more information.
- Comments:** When the Process Group is added to the canvas, the user is given the option of specifying Comments in order to provide information about the Process Group. The comments can later be changed by right-clicking on the Process Group and clicking the "Configure" menu option.

### 1.1.9.3. Anatomy of a Remote Process Group

When creating a DataFlow, it is often necessary to transfer data from one instance of NiFi to another. In this case, the remote instance of NiFi can be thought of as a Process Group. For this reason, NiFi provides the concept of a Remote Process Group. From the User Interface, the Remote Process Group looks similar to the Process Group. However, rather than showing information about the inner workings and state of a Remote Process Group, such as queue sizes, the information rendered about a Remote Process Group is related to the interaction that occurs between this instance of NiFi and the remote instance.



The image above shows the different elements that make up a Remote Process Group. Here, we provide an explanation of the icons and details about the information provided.

- Transmission Status:** The Transmission Status indicates whether or not data Transmission between this instance of NiFi and the remote instance is



currently enabled. The icon shown will be the Transmission Enabled icon (



) if any of the Input Ports or Output Ports is currently configured to transmit or the Transmission Disabled icon (



) if all of the Input Ports and Output Ports that are currently connected are stopped.

- **Remote Instance Name:** This is the name of the NiFi instance that was reported by the remote instance. When the Remote Process Group is first created, before this information has been obtained, the URL of the remote instance will be shown here instead.
- **Remote Instance URL:** This is the URL of the remote instance that the Remote Process Group points to. This URL is entered when the Remote Process Group is added to the canvas and it cannot be changed.
- **Secure Indicator:** This icon indicates whether or not communications with the remote NiFi instance are secure. If communications with the remote instance are secure, this will be indicated by the "Locked" icon (
 
 ). If the communications are not secure, this will be indicated by the "Unlocked" icon (
 
 ). If the communications are secure, this instance of NiFi will not be able to communicate with the remote instance until an administrator for the remote instance grants access. Whenever the Remote Process Group is added to the canvas, this will automatically initiate a request to have a user for this instance of NiFi created on the remote instance. This instance will be unable to communicate with the remote instance until an administrator on the remote instance adds the user to the system and adds the "NiFi" role to the user. In the event that communications are not secure, the Remote Process Group is able to receive data from anyone, and the data is not encrypted while it is transferred between instances of NiFi.
- **5-Minute Statistics:** Two statistics are shown for Remote Process Groups: **Sent** and **Received**. Both of these are in the format <count> (<size>) where <count> is the number of FlowFiles that have been sent or received in the previous five minutes and <size> is the total size of those FlowFiles' content.
- **Comments:** The Comments that are provided for a Remote Process Group are not comments added by the users of this NiFi but rather the Comments added by the administrators of the remote instance. These comments indicate the purpose of the NiFi instance as a whole.
- **Last Refreshed Time:** The information that is pulled from a remote instance and rendered on the Remote Process Group in the User Interface is periodically refreshed in the background. This element indicates the time at which that refresh last happened, or if the information has not been refreshed for a significant amount of time, the value will change to indicate *Remote flow not current*. NiFi can be triggered to initiate a refresh of this information by right-clicking on the Remote Process Group and choosing the "Refresh flow" menu item.



### 1.1.9.4. Queue Interaction

The FlowFiles enqueued in a Connection can be viewed when necessary. The Queue listing is opened via `List queue` in a Connection's context menu. The listing will return the top 100 FlowFiles in the active queue according to the configured priority. The listing can be performed even if the source and destination are actively running.

Additionally, details for a Flowfile in the listing can be viewed by clicking on the Details icon (



) in the left most column. From here, the FlowFile details and attributes are available as well buttons for downloading or viewing the content. Viewing the content is only available if the `nifi.content.viewer.url` has been configured. If the source or destination of the Connection are actively running, there is a chance that the desired FlowFile will no longer be in the active queue.

The FlowFiles enqueued in a Connection can also be deleted when necessary. The removal of the FlowFiles is initiated via `Empty queue` in the Connection's context menu. This action can also be performed if the source and destination are actively running.

### 1.1.9.5. Summary Page

While the NiFi canvas is useful for understanding how the configured DataFlow is laid out, this view is not always optimal when trying to discern the status of the system. In order to help the user understand how the DataFlow is functioning at a higher level, NiFi provides a Summary page. This page is available in the Global Menu in the top-right corner of the User Interface. See the [NiFi User Interface](#) section for more information about the location of this toolbar.

The Summary Page is opened by selecting Summary from the Global Menu. This opens the Summary table dialog:

**NiFi Summary**

PROCESSORS    INPUT PORTS    OUTPUT PORTS    REMOTE PROCESS GROUPS    CONNECTIONS    PROCESS GROUPS

Displaying 60 of 60

Filter: by name View: Single node Cluster

Name	Type	Run Status	In / Size 5 min	Read / Write 5 min	Out / Size 5 min	Tasks / Time 5 min	
Base64EncodeCo...	Base64EncodeCo...	Invalid	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
Capture Network ...	ExecuteProcess	Running (5)	0 (0 bytes)	0 bytes / 245.97 MB	2,883 (245.97 MB)	2,911 / 00:24:59.988	
Check if Dataset ...	IdentifyMimeType	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
Decompress Data...	CompressContent	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
Detect Interesting...	RouteOnAttribute	Running (2)	11,741,700 (13 GB)	0 bytes / 0 bytes	0 (0 bytes)	11,741,700 / 00:09:...	
Empty Contents	ReplaceText	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
EvaluateJsonPath	EvaluateJsonPath	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
Evaluate.JsonPath	Evaluate.JsonPath	Running (4)	11,742,510 (13 GB)	13 GB / 0 bytes	11,742,510 (13 GB)	11,742,856 / 00:20:...	
Extract File ID	UpdateAttribute	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
Extract File ID	UpdateAttribute	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000	
ExtractText	ExtractText	Running	1,498,914 (244.45 ...)	244.45 MB / 0 bytes	1,496,995 (244.25 ...)	1,500,692 / 00:02:4...	

Last updated: 17:45:24 UTC system diagnostics



This dialog provides a great deal of information about each of the components on the canvas. Below, we have annotated the different elements within the dialog in order to make the discussion of the dialog easier.

**NiFi Summary**

Component Tabs: PROCESSORS | INPUT PORTS | OUTPUT PORTS | REMOTE PROCESS GROUPS | CONNECTIONS | PROCESS GROUPS

Displaying 60 of 260

Filter: by name

View: Single node Cluster

Name	Type	Run Status	In / Size 5 min	Read / Write 5 min	Out / Size 5 min	Tasks / Time 5 min
Base64EncodeCo...	Base64EncodeCo...	Invalid	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Capture Network ...	ExecuteProcess	Running (5)	0 (0 bytes)	0 bytes / 245.97 MB	2,883 (2)	24,357,500 / 00:00:00.000
Check if Dataset ...	IdentifyMimeType	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Decorate	Content	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Detect	Attribute	Running (2)	11,741,700 (13 GB)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Empty contents	replaceAllText	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Evaluate.JsonPath	Evaluate.JsonPath	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Evaluate.JsonPath	Evaluate.JsonPath	Running (4)	11,742,510 (13 GB)	13 GB / 0 bytes	11,742,510	0 / 00:00:00.000
Extract File ID	UpdateAttribute	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
Extract File ID	UpdateAttribute	Running	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 / 00:00:00.000
ExtractText	ExtractText	Running	1,498,914 (244.45 ...)	244.45 MB / 0 bytes	1,496,995 (244.25 ...)	1,500,692 / 00:02:4...

Last updated: 17:45:24 UTC

system diagnostics

The Summary page is primarily comprised of a table that provides information about each of the components on the canvas. Above this table is a set of five tabs that can be used to view the different types of components. The information provided in the table is the same information that is provided for each component on the canvas. Each of the columns in the table may be sorted by clicking on the heading of the column. For more on the types of information displayed, see the sections [Anatomy of a Processor](#), [Anatomy of a Process Group](#), and [Anatomy of a Remote Process Group](#) above.

The Summary page also includes the following elements:


- **Bulletin Indicator:** As in other places throughout the User Interface, when this icon is present, hovering over the icon will provide information about the Bulletin that was generated, including the message, the severity level, the time at which the Bulletin was generated, and (in a clustered environment) the node that generated the Bulletin. Like all the columns in the Summary table, this column where bulletins are shown may be sorted by clicking on the heading so that all the currently existing bulletins are shown at the top of the list.
- **Details:** Clicking the Details icon will provide the user with the details of the component. This dialog is the same as the dialog provided when the user right-clicks on the component and chooses the "View Configuration" menu item.
- **Go To:** Clicking this button will close the Summary page and take the user directly to the component on the NiFi canvas. This may change the Process Group that the user is currently in. This icon is not available if the Summary page has been opened in a new browser tab or window (by clicking the "Pop Out" button, as described below).
- **Status History:** Clicking the Status History icon will open a new dialog that shows a historical view of the statistics that are rendered for this component. See the section [Historical Statistics of a Component](#) for more information.

- **Refresh:** The Refresh button allows the user to refresh the information displayed without closing the dialog and opening it again. The time at which the information was last refreshed is shown just to the right of the Refresh button. The information on the page is not automatically refreshed.
- **Filter:** The Filter element allows users to filter the contents of the Summary table by typing in all or part of some criteria, such as a Processor Type or Processor Name. The types of filters available differ according to the selected tab. For instance, if viewing the Processor tab, the user is able to filter by name or by type. When viewing the Connections tab, the user is able to filter by source, by name, or by destination name. The filter is automatically applied when the contents of the text box are changed. Below the text box is an indicator of how many entries in the table match the filter and how many entries exist in the table.
- **Pop-Out:** When monitoring a flow, it is helpful to be able to open the Summary table in a separate browser tab or window. The Pop-Out button, next to the Close button, will cause the entire Summary dialog to be opened in a new browser tab or window (depending on the configuration of the browser). Once the page is "popped out", the dialog is closed in the original browser tab/window. In the new tab/window, the Pop-Out button and the Go-To button will no longer be available.
- **System Diagnostics:** The System Diagnostics window provides information about how the system is performing with respect to system resource utilization. While this is intended mostly for administrators, it is provided in this view because it does provide a summary of the system. This dialog shows information such as CPU utilization, how full the disks are, and Java-specific metrics, such as memory size and utilization, as well as Garbage Collection information.

### 1.1.9.6. Historical Statistics of a Component

While the Summary table and the canvas show numeric statistics pertaining to the performance of a component over the past five minutes, it is often useful to have a view of historical statistics as well. This information is available by right-clicking on a component and choosing the "Status History" menu option or by clicking on the Status History in the Summary page (see [Summary Page](#) for more information).

The amount of historical information that is stored is configurable in the NiFi properties but defaults to 24 hours. For specific configuration information reference the Component Status Repository of the [System Administrator's Guide](#). When the Status History dialog is opened, it provides a graph of historical statistics:



The left-hand side of the dialog provides information about the component that the stats are for, as well as a textual representation of the statistics being graphed. The following information is provided on the left-hand side:

- **Id:** The ID of the component for which the stats are being shown.
- **Group Id:** The ID of the Process Group in which the component resides.
- **Name:** The Name of the Component for which the stats are being shown.
- **Component-Specific Entries:** Information is shown for each different type of component. For example, for a Processor, the type of Processor is displayed. For a Connection, the source and destination names and IDs are shown.
- **Start:** The earliest time shown on the graph.
- **End:** The latest time shown on the graph.
- **Min/Max/Mean:** The minimum, maximum, and mean (arithmetic mean, or average) values are shown. These values are based only on the range of time selected, if any time range is selected. If this instance of NiFi is clustered, these values are shown for the cluster as a whole, as well as each individual node. In a clustered environment, each node is shown in a different color. This also serves as the graph's legend, showing the color of each node that is shown in the graph. Hovering the mouse over the Cluster or one of the nodes in the legend will also make the corresponding node bold in the graph.

The right-hand side of the dialog provides a drop-down list of the different types of metrics to render in the graphs below. The top graph is larger so as to provide an easier-to-read

rendering of the information. In the bottom-right corner of this graph is a small handle (



) that can be dragged to resize the graph. The blank areas of the dialog can also be dragged around to move the entire dialog.


The bottom graph is much shorter and provides the ability to select a time range. Selecting a time range here will cause the top graph to show only the time range selected, but in a more detailed manner. Additionally, this will cause the Min/Max/Mean values on the left-hand side to be recalculated. Once a selection has been created by dragging a rectangle over the graph, double-clicking on the selected portion will cause the selection to fully expand in the vertical direction (i.e., it will select all values in this time range). Clicking on the bottom graph without dragging will remove the selection.

## 1.1.10. Versioning a DataFlow


When NiFi is connected to a NiFi Registry, dataflows can be version controlled on the process group level. For more information about NiFi Registry usage and configuration, see the documentation at <https://nifi.apache.org/docs/nifi-registry-docs/index.html>.

### 1.1.10.1. Connecting to a NiFi Registry

To connect NiFi to a Registry, select Controller Settings from the Global Menu.



This displays the NiFi Settings window. Select the Registry Clients tab and click the "+" button in the upper-right corner to register a new Registry client.




In the Add Registry Client window, provide a name and URL.

The 'Add Registry Client' dialog box contains the following fields and values:

- Name:** Local Registry
- URL:** http://localhost:18080
- Description:** (Empty text area)

Buttons at the bottom: CANCEL, ADD





Click "Add" to complete the registration.



Versioned flows are stored and organized in registry buckets. Bucket Policies and Special Privileges configured by the registry administrator determine which buckets a user can import versioned flows from and which buckets a user can save versioned flows to. Information on Bucket Policies and Special Privileges can be found in the NiFi Registry User Guide (<https://nifi.apache.org/docs/nifi-registry-docs/html/user-guide.html>).

### 1.1.10.2. Version States

Versioned process groups exist in the following states:

- 
**to date:** The flow version is the latest. **Up**
- 
**modified:** Local changes have been made. **Locally**
- 
**Stale:** A newer version of the flow is available.
- 
**modified and stale:** Local changes have been made and a newer version of the flow is available. **Locally**




Sync

**failure:** Unable to synchronize the flow with the registry.

Version state information is displayed:

1. Next to the process group name, for the versioned process group itself. Hovering over the state icon displays additional information about the versioned flow.
2. At the bottom of a process group, for the versioned flows contained in the process group.
3. In the Status Bar at the top of the UI, for the versioned flows contained in the root process group.



Version state information is also shown in the "Process Groups" tab of the Summary Page.

**NiFi Summary**

PROCESSORS INPUT PORTS OUTPUT PORTS REMOTE PROCESS GROUPS CONNECTIONS PROCESS GROUPS

Displaying 7 of 7

Filter by name

Name	Version State	Transferr...	In / Size 5...	Read / Write 5 mi...	Out / Size ...	Sent / Size...	Received / ...
NiFi Flow		0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)
Process Group DEF		0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)
Flow 3	* Locally modified	0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)
test	⚠ Locally modified and stale	0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)
MySQL CDC	⚠ Stale	0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)
PG 13	? Sync failure	0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)
Process Group ABC	✓ Up to date	0 (0 bytes)	0 (0 bytes)	0 bytes / 0 bytes	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)

Last updated: 15:15:50 EST system diagnostics

NiFi Flow

To see the most recent version states, it may be necessary to right-click on the NiFi canvas and select 'Refresh' from the context menu.

### 1.1.10.3. Import a Versioned Flow

When a NiFi instance is connected to a registry, an "Import" link will appear in the Add Process Group dialog.

**Add Process Group**

Process Group Name

[Import...](#)

Import a flow from a registry

CANCEL ADD

Selecting the link will open the Import Version dialog.



### Import Version

Registry  
Local Registry


Bucket  
Bucket 1

Name  
MySQL CDC

Version	Created	Comments
3	01/02/2018 17:18:44.686	Changed Run Schedule of CDC processor to 300 ms.
2	01/02/2018 17:17:38.128	Corrected LogAttribute Processor by auto-terminating.
1	01/02/2018 17:12:17.339	Start from template

CANCEL IMPORT

Connected registries will appear as options in the Registry drop-down menu. For the chosen Registry, buckets the user has access to will appear as options in the Bucket drop-down menu. The names of the flows in the chosen bucket will appear as options in the Name drop-down menu. Select the desired version of the flow to import and select "Import" for the dataflow to be placed on the canvas.



Since the version imported in this example is the latest version (MySQL CDC, Version 3), the state of the versioned process group is "Up to


date" (  ).

If the version imported had been an older version, the state would be


"Stale" (  ).

### 1.1.10.4. Start Version Control


To place a process group under version control, right-click on the process group and in the context menu, select "Version#Start version control".




In the Save Flow Version window, select a Registry and Bucket and enter a Name for the Flow. If desired, add content for the Description and Comment fields.



Select Save and Version 1 of the flow is saved.



As the first and latest version of the flow, the state of the versioned process group is "Up to date" (  ).


The root process group can not be placed under version control.

### 1.1.10.5. Managing Local Changes


When changes are made to a versioned process group, the state of the component updates to "Locally

modified" (  ).

The DFM can show, revert or commit the local changes. These options are available for selection in the context menu when right-clicking on the process group:



or when right-clicking on the canvas inside the process group:



The following actions are not considered local changes:

- disabling/enabling processors and controller services

- stopping/starting processors
- modifying sensitive property values
- modifying remote process group URLs
- updating a processor that was referencing a non-existent controller service to reference an externally available controller service
- modifying variables

Variables do not support sensitive values and will be included when versioning a Process Group.

### 1.1.10.5.1. Show Local Changes

The local changes made to a versioned process group can be viewed in the Show Local Changes dialog by selecting "Version#Show local changes" from the context menu.

**Show Local Changes**

The following changes have been made to ABC (Version 1).

Displaying 4 of 4

Filter

Component Name ▲	Change Type	Difference	
Get Movie Data	Run Schedule Changed	From '10 mins' to '5 mins'	→
LogAttribute	Component Added	Processor was added	→
Publish to "Movies" Topic	Property Value Changed	From 'Compression Type=none' to 'Compression Type=gzip'	→
RouteOnAttribute	Bulletin Level Changed	From 'WARN' to 'ERROR'	→

CLOSE

You can navigate to a component by selecting the "Go To" icon

(  )  
in its row.

As described in the [Managing Local Changes](#) section, there are exceptions to which actions are reviewable local changes. Additionally, multiple changes to the same property will only appear as one change in the list as the

changes are determined by diffing the current state of the process group and the saved version of the process group noted in the Show Local Changes dialog.

### 1.1.10.5.2. Revert Local Changes

Revert the local changes made to a versioned process group by selecting "Version#Revert local changes" from the context menu. The Revert Local Changes dialog displays a list of the local changes for the DFM to review and consider prior to initiating the revert. Select "Revert" to remove all changes.

The following changes have been made to ABC (Version 1). Revert will remove all changes.


Displaying 4 of 4

Filter

Component Name ^	Change Type	Difference	
Get Movie Data	Run Schedule Changed	From '10 mins' to '5 mins'	→
LogAttribute	Component Added	Processor was added	→
Publish to "Movies" Topic	Property Value Changed	From 'Compression Type=none' to 'Compression Type=gzip'	→
RouteOnAttribute	Bulletin Level Changed	From 'WARN' to 'ERROR'	→

CANCEL REVERT


You can navigate to a component by selecting the "Go To" icon

(  )  
in its row.

As described in the [Managing Local Changes](#) section, there are exceptions to which actions are revertible local changes. Additionally, multiple changes to the same property will only appear as one change in the list as the changes are determined by diffing the current state of the process group and the saved version of the process group noted in the Revert Local Changes dialog.

### 1.1.10.5.3. Commit Local Changes

To commit and save a flow version, select "Version#Commit local changes" from the context menu. In the Save Flow Version dialog, add comments if desired and select "Save".



**Save Flow Version**

Registry  
Local Registry

Bucket  
Bucket 2


Name  
ABC

Description  
Get movie CSV data, convert to JSON and publish to Kafka topic "Movies"

Comments

- Lowered Run Schedule on GetHttp
- Added Gzip compression
- Increased bulletin level from Warn to Error
- Added new LogAttribute processor


CANCEL SAVE

Local changes can not be committed if the version that has been modified is not the latest version. In this scenario, the version state is "Locally modified and stale" (  ).


### 1.1.10.6. Change Version

To change the version of a flow, right-click on the versioned process group and select "Version#Change version".






In the Change Version dialog, select the desired version and select "Change":



The version of the flow is changed:




In the example shown, the versioned flow is upgraded from an older to the newer latest version. However, a versioned flow can also be rolled back to an older version.


For "Change version" to be an available selection, local changes to the process group need to be reverted.

### 1.1.10.7. Stop Version Control



To stop version control on a flow, right-click on the versioned process group and select "Version#Stop version control":



In the Stop Version Control dialog, select "Disconnect".



The removal of the process group from version control is confirmed.



### 1.1.10.8. Nested Versioned Flows

A versioned process group can contain other versioned process groups. However, local changes to a parent process group cannot be reverted or saved if it contains a child process group that also has local changes. The child process group must first be reverted or have its changes committed for those actions to be performed on the parent process group.

### 1.1.11. Templates

DFMs have the ability to build very large and complex DataFlows using NiFi. This is achieved by using the basic components: Processor, Funnel, Input/Output Port, Process Group,

and Remote Process Group. These can be thought of as the most basic building blocks for constructing a DataFlow. At times, though, using these small building blocks can become tedious if the same logic needs to be repeated several times.

To solve this issue, NiFi provides the concept of a Template. A Template is a way of combining these basic building blocks into larger building blocks. Once a DataFlow has been created, parts of it can be formed into a Template. This Template can then be dragged onto the canvas, or can be exported as an XML file and shared with others. Templates received from others can then be imported into an instance of NiFi and dragged onto the canvas.

### 1.1.11.1. Creating a Template

To create a Template, select the components that are to be a part of the template, and then click the "Create Template" (



) button in the Operate Palette (See [NiFi User Interface](#) for more information on the Operate Palette).

Clicking this button without selecting anything will create a Template that contains all of the contents of the current Process Group. This means that creating a Template with nothing selected while on the Root Process Group will create a single Template that contains the entire flow.

After clicking this button, the user is prompted to provide a name and an optional description for the template. Each template must have a unique name. After entering the name and optional description, clicking the Create button will generate the template and notify the user that the template was successfully created, or provide an appropriate error message if unable to create the template for some reason.

It is important to note that if any Processor that is Templated has a sensitive property (such as a password), the value of that sensitive property is not included in the Template. As a result, when dragging the Template onto the canvas, newly created Processors may not be valid if they are missing values for their sensitive properties. Additionally, any Connection that was selected when making the Template is not included in the Template if either the source or the destination of the Connection is not also included in the Template.

### 1.1.11.2. Importing a Template

After receiving a Template that has been exported from another NiFi, the first step needed to use the template is to import the template into this instance of NiFi. You may import templates into any Process Group where you have the appropriate authorization.

From the Operate Palette, click the "Upload Template" (



) button (see [NiFi User Interface](#) for more information on the Operate Palette). This will display the Upload Template dialog. Click the find icon and use the File Selection dialog to choose which template file to upload. Select the file and click Open. Clicking the "Upload"

button will attempt to import the Template into this instance of NiFi. The Upload Template dialog will update to show "Success" or an error message if there was a problem importing the template.

### 1.1.11.3. Instantiating a Template

Once a Template has been created (see [Creating a Template](#)) or imported (see [Importing a Template](#)), it is ready to be instantiated, or added to the canvas. This is accomplished by dragging the Template icon (



) from the Components Toolbar (see [NiFi User Interface](#)) onto the canvas.

This will present a dialog to choose which Template to add to the canvas. After choosing the Template to add, simply click the "Add" button. The Template will be added to the canvas with the upper-left-hand side of the Template being placed wherever the user dropped the Template icon.

This leaves the contents of the newly instantiated Template selected. If there was a mistake, and this Template is no longer wanted, it may be deleted.

### 1.1.11.4. Managing Templates

One of the most powerful features of NiFi Templates is the ability to easily export a Template to an XML file and to import a Template that has already been exported. This provides a very simple mechanism for sharing parts of a DataFlow with others. You can select Templates from the Global Menu (see [NiFi User Interface](#)) to open a dialog that displays all of the Templates that are currently available, filter the templates to see only those of interest, export, and delete Templates.

#### 1.1.11.4.1. Exporting a Template

Once a Template has been created, it can be shared with others in the Template Management page (see [Managing Templates](#)). To export a Template, locate the Template in the table. The Filter in the top-right corner can be used to help find the appropriate Template if several are available. Then click the Export or Download button (



). This will download the template as an XML file to your computer. This XML file can then be sent to others and imported into other instances of NiFi (see [Importing a Template](#)).

#### 1.1.11.4.2. Removing a Template

Once it is decided that a Template is no longer needed, it can be easily removed from the Template Management page (see [Managing Templates](#)). To delete a Template, locate it in the table (the Filter in the top-right corner may be used to find the appropriate Template if several are available) and click the Delete button (



). This will prompt for confirmation. After confirming the deletion, the Template will be removed from this table and will no longer be available to add to the canvas.

## 1.1.12. Data Provenance

While monitoring a dataflow, users often need a way to determine what happened to a particular data object (FlowFile). NiFi's Data Provenance page provides that information. Because NiFi records and indexes data provenance details as objects flow through the system, users may perform searches, conduct troubleshooting and evaluate things like dataflow compliance and optimization in real time. By default, NiFi updates this information every five minutes, but that is configurable.

To access the Data Provenance page, select Data Provenance from the Global Menu. Clicking this button opens a dialog window that allows the user to see the most recent Data Provenance information available, search the information for specific items, and filter the search results. It is also possible to open additional dialog windows to see event details, replay data at any point within the dataflow, and see a graphical representation of the data's lineage, or path through the flow. (These features are described in depth below.)

The screenshot shows the NiFi Data Provenance page with a table of events. Annotations highlight key features: 'Event Type' points to the 'Type' column; 'Provenance Event Details' points to an information icon in the first column; 'FlowFile Lineage Graph' points to a link icon in the 'Node' column; and 'Go To Arrow' points to a blue arrow icon in the 'Node' column.

Date/Time	Type	FlowFile Uuid	Size	Component Name	Component Type	Node
07/29/2016 00:14:...	ATTRIBUTES_MODL...	91ae19fa-5797-45...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	bcc29546-bbd0-43...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	9f4c3b69-6cef-40a...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	38bb2021-1f07-4e...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	f31d3aa0-40b7-46...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	7d12c959-6952-41...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	93f31b5c-be89-49e...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	a1e5a6a4-b44e-4e...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	cf2095c8-052a-47...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	c0db8381-6c13-42...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	9da3e06d-9715-46...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...
07/29/2016 00:14:...	ATTRIBUTES_MODL...	18247e64-41b3-4f...	1.11 KB	EvaluateJsonPath	EvaluateJsonPath	nifi-05.eng.hortonw...

Additional interface elements include: 'NiFi Data Provenance' title, 'Displaying 1,000 of 1,000' status, 'Oldest event available: 07/14/2016 20:56:52 UTC', 'Showing the most recent 1,000 of 1,000+ events, please refine the search.', a search bar, a filter dropdown set to 'by component name', and a refresh button at the bottom left.

### 1.1.12.1. Provenance Events

Each point in a dataflow where a FlowFile is processed in some way is considered a 'provenance event'. Various types of provenance events occur, depending on the dataflow design. For example, when data is brought into the flow, a RECEIVE event occurs, and when data is sent out of the flow, a SEND event occurs. Other types of processing events may occur, such as if the data is cloned (CLONE event), routed (ROUTE event), modified (CONTENT\_MODIFIED or ATTRIBUTES\_MODIFIED event), split (FORK event), combined with other data objects (JOIN event), and ultimately removed from the flow (DROP event).

The provenance event types are:

Provenance Event	Description
ADDINFO	Indicates a provenance event when additional information such as a new linkage to a new URI or UUID is added

Provenance Event	Description
ATTRIBUTES_MODIFIED	Indicates that a FlowFile's attributes were modified in some way
CLONE	Indicates that a FlowFile is an exact duplicate of its parent FlowFile
CONTENT_MODIFIED	Indicates that a FlowFile's content was modified in some way
CREATE	Indicates that a FlowFile was generated from data that was not received from a remote system or external process
DOWNLOAD	Indicates that the contents of a FlowFile were downloaded by a user or external entity
DROP	Indicates a provenance event for the conclusion of an object's life for some reason other than object expiration
EXPIRE	Indicates a provenance event for the conclusion of an object's life due to the object not being processed in a timely manner
FETCH	Indicates that the contents of a FlowFile were overwritten using the contents of some external resource
FORK	Indicates that one or more FlowFiles were derived from a parent FlowFile
JOIN	Indicates that a single FlowFile is derived from joining together multiple parent FlowFiles
RECEIVE	Indicates a provenance event for receiving data from an external process
REPLAY	Indicates a provenance event for replaying a FlowFile
ROUTE	Indicates that a FlowFile was routed to a specified relationship and provides information about why the FlowFile was routed to this relationship
SEND	Indicates a provenance event for sending data to an external process
UNKNOWN	Indicates that the type of provenance event is unknown because the user who is attempting to access the event is not authorized to know the type

### 1.1.12.2. Searching for Events


One of the most common tasks performed in the Data Provenance page is a search for a given FlowFile to determine what happened to it. To do this, click the `Search` button in the upper-right corner of the Data Provenance page. This opens a dialog window with parameters that the user can define for the search. The parameters include the processing event of interest, distinguishing characteristics about the FlowFile or the component that produced the event, the timeframe within which to search, and the size of the FlowFile.





### Search Events


Fields


Event Type	<input type="text"/>
FlowFile UUID	<input type="text"/>
Filename	<input type="text"/>
Component ID	<input type="text"/>
Relationship	<input type="text"/>
twitter.msg	<input type="text"/>
language	<input type="text"/>


Start date 


Start time (UTC) 

End date 

End time (UTC) 

Minimum file size 

Maximum file size 

Search location  
 

For example, to determine if a particular FlowFile was received, search for an Event Type of "RECEIVE" and include an identifier for the FlowFile, such as its uuid or filename. The asterisk (\*) may be used as a wildcard for any number of characters. So, to determine whether a FlowFile with "ABC" anywhere in its filename was received at any time on Jan. 6, 2015, the search shown in the following image could be performed:

**Search Events**

Fields		
Event Type	RECEIVE	
FlowFile UUID		
Filename	*ABC* <input style="width: 50px;" type="text"/>	
Component ID		
Relationship		
twitter.msg		
language		
Start date	Start time (UTC)	
<input type="text" value="07/28/2016"/>	<input type="text" value="00:00:00"/>	
End date	End time (UTC)	
<input type="text" value="07/28/2016"/>	<input type="text" value="23:59:59"/>	
Minimum file size	Maximum file size	
<input type="text"/>	<input type="text"/>	
Search location	<input style="width: 100%;" type="text" value="cluster"/>	
	<input type="button" value="CANCEL"/> <input style="background-color: #4a7c8c; color: white;" type="button" value="SEARCH"/>	

### 1.1.12.3. Details of an Event

In the far-left column of the Data Provenance page, there is a View Details icon for each event

( ).  
 Clicking this button opens a dialog window with three tabs: Details, Attributes, and Content.

**Provenance Event**

DETAILS	ATTRIBUTES	CONTENT
<b>Time</b> 07/29/2016 00:58:44.829 UTC		<b>Parent FlowFiles (0)</b> No parents
<b>Event Duration</b> No value set		<b>Child FlowFiles (0)</b> No children
<b>Lineage Duration</b> 00:00:00.203		
<b>Type</b> ATTRIBUTES_MODIFIED		
<b>FlowFile Uuid</b> 62d2161f-0b2a-4b2a-a552-ab617bef3811		
<b>File Size</b> 1.1 KB		
<b>Component Id</b> 7bba4f68-2861-3a12-aac6-60f12e11e215		
<b>Component Name</b> EvaluateJsonPath		
<b>Component Type</b> ...		

OK

The Details tab shows various details about the event, such as when it occurred, what type of event it was, and the component that produced the event. The information that is displayed will vary according to the event type. This tab also shows information about the FlowFile that was processed. In addition to the FlowFile's UUID, which is displayed on the left side of the Details tab, the UUIDs of any parent or children FlowFiles that are related to that FlowFile are displayed on the right side of the Details tab.

The Attributes tab shows the attributes that exist on the FlowFile as of that point in the flow. In order to see only the attributes that were modified as a result of the processing event, the user may select the checkbox next to "Only show modified" in the upper-right corner of the Attributes tab.

### Provenance Event

DETAILS ATTRIBUTES CONTENT

**Attribute Values**  Show modified attributes only

eventType  
ATTRIBUTES\_MODIFIED  
No value previously set

filename  
6320498487869637

newSize  
1119  
No value previously set

oldSize  
1119  
No value previously set

path  
./

reporting.task.transaction.id  
fc9fad99-89f0-4978-a3aa-571bb8b8851b

uuid  
62d2161f-0b2a-4b2a-a552-ab617bef3811

OK

#### 1.1.12.4. Replaying a FlowFile

A DFM may need to inspect a FlowFile's content at some point in the dataflow to ensure that it is being processed as expected. And if it is not being processed properly, the DFM may need to make adjustments to the dataflow and replay the FlowFile again. The Content tab of the View Details dialog window is where the DFM can do these things. The Content tab shows information about the FlowFile's content, such as its location in the Content Repository and its size. In addition, it is here that the user may click the `Download` button to download a copy of the FlowFile's content as it existed at this point in the flow. The user may also click the `Submit` button to replay the FlowFile at this point in the flow. Upon clicking `Submit`, the FlowFile is sent to the connection feeding the component that produced this processing event.

**Provenance Event**

DETAILS
ATTRIBUTES
CONTENT

**Input Claim**



Container  
default

Section  
918

Identifier  
1469753924663-275350

Offset  
108834

Size  
1.1 KB

 DOWNLOAD
 VIEW

**Output Claim**



Container  
default

Section  
918

Identifier  
1469753924663-275350

Offset  
108834

Size  
1.1 KB

 DOWNLOAD
 VIEW

**Replay**

Connection Id  
88970033-a406-33a2-b679-711d04de4a35

OK

### 1.1.12.5. Viewing FlowFile Lineage


It is often useful to see a graphical representation of the lineage or path a FlowFile took within the dataflow. To see a FlowFile's lineage, click on the "Show Lineage" icon (



) in the far-right column of the Data Provenance table. This opens a graph displaying the FlowFile (




) and the various processing events that have occurred. The selected event will be highlighted in red. It is possible to right-click or double-click on any event to see that event's details (see [Details of an Event](#)). To see how the lineage evolved over time, click the slider at the bottom-left of the window and move it to the left to see the state of the lineage at earlier stages in the dataflow.




### 1.1.12.5.1. Find Parents

Sometimes, a user may need to track down the original FlowFile that another FlowFile was spawned from. For example, when a FORK or CLONE event occurs, NiFi keeps track of the parent FlowFile that produced other FlowFiles, and it is possible to find that parent FlowFile in the Lineage. Right-click on the event in the lineage graph and select "Find parents" from the context menu.




Once "Find parents" is selected, the graph is re-drawn to show the parent FlowFile and its lineage as well as the child and its lineage.




### 1.1.12.5.2. Expanding an Event

In the same way that it is useful to find a parent FlowFile, the user may also want to determine what children were spawned from a given FlowFile. To do this, right-click on the event in the lineage graph and select "Expand" from the context menu.



Once "Expand" is selected, the graph is re-drawn to show the children and their lineage.



### 1.1.12.6. Write Ahead Provenance Repository

By default, the Provenance Repository is implemented in a Persistent Provenance configuration. In Apache NiFi 1.2.0, the Write Ahead configuration was introduced to provide the same capabilities as Persistent Provenance, but with far better performance. Migrating to the Write Ahead configuration is easy to accomplish. Simply change the setting for the `nifi.provenance.repository.implementation` system property in the `nifi.properties` file from the default value of `org.apache.nifi.provenance.PersistentProvenanceRepository` to `org.apache.nifi.provenance.WriteAheadProvenanceRepository` and restart NiFi.

However, to increase the chances of a successful migration consider the following factors and recommended actions.

#### 1.1.12.6.1. Backwards Compatibility

The `WriteAheadProvenanceRepository` can use the Provenance data stored by the `PersistentProvenanceRepository`. However, the `PersistentProvenanceRepository` may not be able to read the data written by the `WriteAheadProvenanceRepository`. Therefore, once the Provenance Repository is changed to use the `WriteAheadProvenanceRepository`, it cannot be changed back to the `PersistentProvenanceRepository` without first deleting the data in the Provenance Repository. It is therefore recommended that before changing the implementation to Write Ahead, ensure your version of NiFi is stable, in case an issue arises that requires the need to roll back to a previous version of NiFi that did not support the `WriteAheadProvenanceRepository`.

#### 1.1.12.6.2. Older Existing NiFi Version

If you are upgrading from an older version of NiFi to 1.2.0 or later, it is recommended that you do not change the provenance configuration to Write Ahead until you confirm your flows and environment are stable in 1.2.0 first. This reduces the number of variables in your upgrade and can simplify the debugging process if any issues arise.

#### 1.1.12.6.3. Bootstrap.conf

While better performance is achieved with the G1 garbage collector, Java 8 bugs may surface more frequently in the Write Ahead configuration. It is recommended that the following line is commented out in the `bootstrap.conf` file in the `conf` directory:

```
java.arg.13=-XX:+UseG1GC
```



#### 1.1.12.6.4. System Properties

Many of the same system properties are supported by both the Persistent and Write Ahead configurations, however the default values have been chosen for a Persistent Provenance configuration. The following exceptions and recommendations should be noted when changing to a Write Ahead configuration:

- `nifi.provenance.repository.journal.count` is not relevant to a Write Ahead configuration
- `nifi.provenance.repository.concurrent.merge.threads` and `nifi.provenance.repository.warm.cache.frequency` are new properties. The default values of 2 for threads and blank for frequency (i.e. disabled) should remain for most installations.
- Change the settings for `nifi.provenance.repository.max.storage.time` (default value of 24 hours) and `nifi.provenance.repository.max.storage.size` (default value of 1 GB) to values more suitable for your production environment
- Change `nifi.provenance.repository.index.shard.size` from the default value of 500 MB to 4 GB
- Change `nifi.provenance.repository.index.threads` from the default value of 2 to either 4 or 8 as the Write Ahead repository enables this to scale better
- If processing a high volume of events, change `nifi.provenance.repository.rollover.time` from a default of 30 secs to 1 min and `nifi.provenance.repository.rollover.size` from the default of 100 MB to 1 GB

Once these property changes have been made, restart NiFi.

**Note:** Detailed descriptions for each of these properties can be found in [System Properties](#).

#### 1.1.12.6.5. Encrypted Provenance Considerations

The above migration recommendations for `WriteAheadProvenanceRepository` also apply to the encrypted version of the configuration, `EncryptedWriteAheadProvenanceRepository`.

The next section has more information about implementing an Encrypted Provenance Repository.

#### 1.1.12.7. Encrypted Provenance Repository

While OS-level access control can offer some security over the provenance data written to the disk in a repository, there are scenarios where the data may be sensitive, compliance and regulatory requirements exist, or NiFi is running on hardware not under the direct control of the organization (cloud, etc.). In this case, the provenance repository allows for all data to be encrypted before being persisted to the disk.

**Performance** The current implementation of the encrypted provenance repository intercepts the record writer and reader of `WriteAheadProvenanceRepository`, which offers significant performance improvements over the legacy



```
key3=SFellxuz7J89Y/IQ7YbJPOL0/YKZRFL/VUxJgEHxxlXpd/
8ELA7wwN59KlKTr3BURCcFP5YGmwrSKfr4OE4Vlg==
key4=kZprfcTSTH69UuOU3jMkZfrtiVR/eqWmmbdku3BqcUJ/
+UToecNB5lzOVEMBChyEXppyXXC35Wa6GEXFK6PMk==
key5=c6FzfnKm7UR7xqi2NFpZ+fEKbfsU7+1NvRw
+XWQ9U39MONWqk5gvoyOCdFR1kUgeg46jrn5dGXk13sRqE0GETQ==
```


Each line defines a key ID and then the Base64-encoded cipher text of a 16 byte IV and wrapped AES-128, AES-192, or AES-256 key depending on the JCE policies available. The individual keys are wrapped by AES/GCM encryption using the **master key** defined by `nifi.bootstrap.sensitive.key` in `conf/bootstrap.conf`.

### 1.1.12.7.2.3. Key Rotation

Simply update `nifi.properties` to reference a new key ID in `nifi.provenance.repository.encryption.key.id`. Previously-encrypted events can still be decrypted as long as that key is still available in the key definition file or `nifi.provenance.repository.encryption.key.id.<OldKeyID>` as the key ID is serialized alongside the encrypted record.

### 1.1.12.7.3. Writing and Reading Event Records

Once the repository is initialized, all provenance event record write operations are serialized according to the configured schema writer (`EventIdFirstSchemaRecordWriter` by default for `WriteAheadProvenanceRepository`) to a `byte[]`. Those bytes are then encrypted using an implementation of `ProvenanceEventEncryptor` (the only current implementation is `AES/GCM/NoPadding`) and the encryption metadata (`keyId`, `algorithm`, `version`, `IV`) is serialized and prepended. The complete `byte[]` is then written to the repository on disk as normal.



On record read, the process is reversed. The encryption metadata is parsed and used to decrypt the serialized bytes, which are then deserialized into a `ProvenanceEventRecord` object. The delegation to the normal schema record writer/reader allows for "random-access" (i.e. immediate seek without decryption of unnecessary records).

Within the NiFi UI/API, there is no detectable difference between an encrypted and unencrypted provenance repository. The Provenance Query operations work as expected with no change to the process.

#### 1.1.12.7.4. Potential Issues

```
Switching Implementations When switching
between implementation "families" (i.e.
VolatileProvenanceRepository or
PersistentProvenanceRepository to
EncryptedWriteAheadProvenanceRepository),
the existing repository must be cleared from the file
system before starting NiFi. A terminal command
like localhost:$NIFI_HOME $ rm -rf
provenance_repository/ is sufficient.
```

- Switching between unencrypted and encrypted repositories
  - If a user has an existing repository (`WriteAheadProvenanceRepository` only - **not** `PersistentProvenanceRepository`) that is not encrypted and switches their configuration to use an encrypted repository, the application writes an error to the log but starts up. However, previous events are not accessible through the provenance query interface and new events will overwrite the existing events. The same behavior occurs if a user switches from an encrypted repository to an unencrypted repository. Automatic roll-over is a future effort ([NIFI-3722](#)) but NiFi is not intended for long-term storage of provenance events so the impact should be minimal. There are two scenarios for roll-over:
    - Encrypted # unencrypted - if the previous repository implementation was encrypted, these events should be handled seamlessly as long as the key provider available still has the keys used to encrypt the events (see **Key Rotation**)
    - Unencrypted # encrypted - if the previous repository implementation was unencrypted, these events should be handled seamlessly as the previously recorded events simply need to be read with a plaintext schema record reader and then written back with the encrypted record writer
  - There is also a future effort to provide a standalone tool in NiFi Toolkit to encrypt/decrypt an existing provenance repository to make the transition easier. The translation process could take a long time depending on the size of the existing repository, and being able to perform this task outside of application startup would be valuable ([NIFI-3723](#)).
- Multiple repositories - No additional effort or testing has been applied to multiple repositories at this time. It is possible/likely issues will occur with repositories on different physical devices. There is no option to provide a heterogenous environment (i.e. one encrypted, one plaintext repository).
- Corruption - when a disk is filled or corrupted, there have been reported issues with the repository becoming corrupted and recovery steps are necessary. This is likely to continue

to be an issue with the encrypted repository, although still limited in scope to individual records (i.e. an entire repository file won't be irrecoverable due to the encryption).

### 1.1.13. Other Management Features

In addition to the Summary Page, Data Provenance Page, Template Management Page, and Bulletin Board Page, there are other tools in the Global Menu (see [NiFi User Interface](#)) that are useful to the DFM. Select Flow Configuration History to view all the changes that have been made to the dataflow. The history can aid in troubleshooting, such as if a recent change to the dataflow has caused a problem and needs to be fixed. The DFM can see what changes have been made and adjust the flow as needed to fix the problem. While NiFi does not have an "undo" feature, the DFM can make new changes to the dataflow that will fix the problem.

Two other tools in the Global Menu are Controller Settings and Users. The Controller Settings page provides the ability to change the name of the NiFi instance, add comments describing the NiFi instance, and set the maximum number of threads that are available to the application. It also provides tabs where DFMs may add and configure [Controller Services](#) and [Reporting Tasks](#). The Users page is used to manage user access, which is described in the [System Administrator's Guide](#).