

Hortonworks Data Platform

Hadoop Security Guide

(May 9, 2016)

Hortonworks Data Platform: Hadoop Security Guide

Copyright © 2012-2016 Hortonworks, Inc. Some rights reserved.

The Hortonworks Data Platform, powered by Apache Hadoop, is a massively scalable and 100% open source platform for storing, processing and analyzing large volumes of data. It is designed to deal with data from many sources and formats in a very quick, easy and cost-effective manner. The Hortonworks Data Platform consists of the essential set of Apache Hadoop projects including MapReduce, Hadoop Distributed File System (HDFS), HCatalog, Pig, Hive, HBase, ZooKeeper and Ambari. Hortonworks is the major contributor of code and patches to many of these projects. These projects have been integrated and tested as part of the Hortonworks Data Platform release process and installation and configuration tools have also been included.

Unlike other providers of platforms built using Apache Hadoop, Hortonworks contributes 100% of our code back to the Apache Software Foundation. The Hortonworks Data Platform is Apache-licensed and completely open source. We sell only expert technical support, [training](#) and partner-enablement services. All of our technology is, and will remain free and open source.

Please visit the [Hortonworks Data Platform](#) page for more information on Hortonworks technology. For more information on Hortonworks services, please visit either the [Support](#) or [Training](#) page. Feel free to [Contact Us](#) directly to discuss your specific needs.



Except where otherwise noted, this document is licensed under
Creative Commons Attribution ShareAlike 4.0 License.
<http://creativecommons.org/licenses/by-sa/4.0/legalcode>

Table of Contents

1. HDP Security Overview	1
1.1. Understanding Data Lake Security	1
1.2. HDP Security Features	3
1.2.1. Administration	4
1.2.2. Authentication and Perimeter Security	4
1.2.3. Authorization	5
1.2.4. Audit	7
1.2.5. Data Protection	7
2. Authentication	8
2.1. Enabling Kerberos Authentication Using Ambari	8
2.1.1. Kerberos Overview	8
2.1.2. Hadoop and Kerberos Principals	9
2.1.3. Installing and Configuring the KDC	10
2.1.4. Enabling Kerberos Security	15
2.1.5. Kerberos Client Packages	19
2.1.6. Disabling Kerberos Security	19
2.1.7. Customizing the Attribute Template	20
2.1.8. Managing Admin Credentials	20
2.2. Configuring Ambari Authentication with LDAP or AD	21
2.2.1. Configuring Ambari for LDAP or Active Directory Authentication	21
2.2.2. Configuring Ranger Authentication with UNIX, LDAP, or AD	26
2.2.3. Encrypting Database and LDAP Passwords in Ambari	35
2.3. Configuring LDAP Authentication in Hue	37
2.3.1. Enabling the LDAP Backend	37
2.3.2. Enabling User Authentication with Search Bind	37
2.3.3. Setting the Search Base to Find Users and Groups	38
2.3.4. Specifying the URL of the LDAP Server	39
2.3.5. Specifying LDAPS and StartTLS Support	39
2.3.6. Specifying Bind Credentials for LDAP Searches	39
2.3.7. Synchronizing Users and Groups	39
2.3.8. Setting Search Bind Authentication and Importing Users and Groups	40
2.3.9. Setting LDAP Users' Filter	40
2.3.10. Setting an LDAP Groups Filter	41
2.3.11. Setting Multiple LDAP Servers	41
2.4. Advanced Security Options for Ambari	42
2.4.1. Configuring Ambari for Non-Root	42
2.4.2. Optional: Ambari Web Inactivity Timeout	45
2.4.3. Set Up Kerberos for Ambari Server	46
2.4.4. Optional: Set Up Two-Way SSL Between Ambari Server and Ambari Agents	47
2.4.5. Optional: Configure Ciphers and Protocols for Ambari Server	47
2.4.6. Optional: HTTP Cookie Persistence	47
2.5. Enabling SPNEGO Authentication for Hadoop	48
2.5.1. Configure Ambari Server for Authenticated HTTP	48
2.5.2. Configuring HTTP Authentication for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon and Storm	48
2.6. Setting Up Kerberos Authentication for Non-Ambari Clusters	49

2.6.1. Preparing Kerberos	49
2.6.2. Configuring HDP for Kerberos	55
2.6.3. Setting up One-Way Trust with Active Directory	82
2.6.4. Configuring Proxy Users	84
2.7. Perimeter Security with Apache Knox	84
2.7.1. Apache Knox Gateway Overview	84
2.7.2. Configuring the Knox Gateway	86
2.7.3. Defining Cluster Topologies	90
2.7.4. Configuring a Hadoop Server for Knox	92
2.7.5. Mapping the Internal Nodes to External URLs	96
2.7.6. Configuring Authentication	100
2.7.7. Configuring Identity Assertion	110
2.7.8. Configuring Service Level Authorization	115
2.7.9. Audit Gateway Activity	118
2.7.10. Gateway Security	120
2.7.11. Setting Up Knox for WebHDFS HA	123
2.7.12. Knox CLI Testing Tools	125
3. Configuring Authorization in Hadoop	127
3.1. Installing Ranger Using Ambari	127
3.1.1. Overview	127
3.1.2. Installation Prerequisites	127
3.1.3. Ranger Installation	133
3.1.4. Enabling Ranger Plugins	170
3.1.5. Ranger Plugins - Kerberos Overview	195
3.2. Using Ranger to Provide Authorization in Hadoop	199
3.2.1. Opening and Closing the Ranger Console	199
3.2.2. Console Operations Summary	200
3.2.3. Configuring Services	201
3.2.4. Policy Management	218
3.2.5. Users/Groups and Permissions Administration	236
3.2.6. Reports Administration	246
3.2.7. Special Requirements for High Availability Environments	249
3.2.8. Adding a New Component to Apache Ranger	250
3.2.9. Developing a Custom Authorization Module	253
3.2.10. Apache Ranger Public REST API	253
4. Data Protection: Wire Encryption	288
4.1. Enabling RPC Encryption	288
4.2. Enabling Data Transfer Protocol	289
4.3. Enabling SSL: Understanding the Hadoop SSL Keystore Factory	289
4.4. Creating and Managing SSL Certificates	291
4.4.1. Obtain a Certificate from a Trusted Third-Party Certification Authority (CA)	291
4.4.2. Create and Set Up an Internal CA (OpenSSL)	292
4.4.3. Installing Certificates in the Hadoop SSL Keystore Factory (HDFS, MapReduce, and YARN)	296
4.4.4. Using a CA-Signed Certificate	297
4.5. Enabling SSL for HDP Components	298
4.6. Enable SSL for WebHDFS, MapReduce Shuffle, and YARN	298
4.7. Enable SSL for HttpFS	301
4.8. Enable SSL on Oozie	302
4.8.1. Configure Oozie HCatalogJob Properties	303

4.9. Enable SSL on the HBase REST Server	303
4.10. Enable SSL on the HBase Web UI	305
4.11. Enable SSL on HiveServer2	306
4.12. Enable SSL for Kafka Clients	307
4.12.1. Configuring the Kafka Broker	307
4.12.2. Configuring Kafka Producer and Kafka Consumer	309
4.13. Enable SSL for Accumulo	310
4.13.1. Generate a Certificate Authority	310
4.13.2. Generate a Certificate/Keystore Per Host	311
4.13.3. Configure Accumulo Servers	312
4.13.4. Configure Accumulo Clients	313
4.14. SPNEGO setup for WebHCat	313
4.15. Configure SSL for Hue	314
4.15.1. Enabling SSL on Hue by Using a Private Key	314
4.15.2. Enabling SSL on Hue Without Using a Private Key	314
4.16. Configure SSL for Knox	315
4.16.1. Self-Signed Certificate with Specific Hostname for Evaluations	315
4.16.2. CA-Signed Certificates for Production	315
4.16.3. Setting Up Trust for the Knox Gateway Clients	316
4.17. Securing Phoenix	316
4.18. Set Up SSL for Ambari	316
4.18.1. Set Up Truststore for Ambari Server	317
4.19. Configure Ambari Ranger SSL	318
4.19.1. Configuring Ambari Ranger SSL Using Public CA Certificates	318
4.19.2. Configuring Ambari Ranger SSL Using a Self-Signed Certificate	331
4.20. Configure Non-Ambari Ranger SSL	346
4.20.1. Configuring Non-Ambari Ranger SSL Using Public CA Certificates	346
4.20.2. Configuring Non-Ambari Ranger SSL Using a Self Signed Certificate	349
4.21. Connecting to SSL-Enabled Components	353
4.21.1. Connect to SSL Enabled HiveServer2 using JDBC	354
4.21.2. Connect to SSL Enabled Oozie Server	354
5. Auditing in Hadoop	356
5.1. Using Apache Solr for Ranger Audits	356
5.1.1. Prerequisites	356
5.1.2. Installing Solr	357
5.1.3. Configuring Solr Standalone	357
5.1.4. Configuring SolrCloud	358
5.2. Manually Enabling Audit Settings in Ambari Clusters	360
5.2.1. Manually Updating Ambari Solr Audit Settings	360
5.2.2. Manually Updating Ambari HDFS Audit Settings	361
5.3. Enabling Audit Logging in Non-Ambari Clusters	362
5.4. Manging Auditing in Ranger	363
5.4.1. View Operation Details	364
5.4.2. Access	365
5.4.3. Admin	366
5.4.4. Login Sessions	367
5.4.5. Plugins	368
6. Data Protection: HDFS Encryption	369
6.1. Ranger KMS Administration Guide	369
6.1.1. Installing the Ranger Key Management Service	369

6.1.2. Enable Ranger KMS Audit	377
6.1.3. Enabling SSL for Ranger KMS	380
6.1.4. Install Multiple Ranger KMS	385
6.1.5. Using the Ranger Key Management Service	386
6.1.6. Ranger KMS Properties	391
6.1.7. Troubleshooting Ranger KMS	395
6.2. HDFS "Data at Rest" Encryption	395
6.2.1. HDFS Encryption Overview	395
6.2.2. Configuring and Starting the Ranger Key Management Service (Ranger KMS)	397
6.2.3. Configuring and Using HDFS Data at Rest Encryption	398
6.2.4. Configuring HDP Services for HDFS Encryption	406
6.2.5. Appendix: Creating an HDFS Admin User	413

List of Figures

3.1. Installing Ranger - Main Dashboard View	134
3.2. Installing Ranger - Add Service	135
3.3. Installing Ranger - Choose Service	136
3.4. Installing Ranger - Ranger Requirements	137
3.5. Installing Ranger Assign Masters	138
3.6. Knox Service Manager	198
3.7. Knox Service Edit	198
6.1. HDFS Encryption Components	397

List of Tables

2.1. UNIX Authentication Settings	27
2.2. Active Directory Authentication Settings	28
2.3. Active Directory Custom ranger-admin-site Settings	30
2.4. LDAP Authentication Settings	32
2.5. LDAP Custom ranger-admin-site Settings	34
2.6. Active Directory Authentication Settings	35
2.7. Service Principals	53
2.8. Service Keytab File Names	54
2.9. General core-site.xml, Knox, and Hue	58
2.10. core-site.xml Master Node Settings – Knox Gateway	59
2.11. core-site.xml Master Node Settings – Hue	59
2.12. hdfs-site.xml File Property Settings	60
2.13. yarn-site.xml Property Settings	64
2.14. mapred-site.xml Property Settings	66
2.15. hbase-site.xml Property Settings for HBase Server	67
2.16. hive-site.xml Property Settings	70
2.17. oozie-site.xml Property Settings	71
2.18. webhcat-site.xml Property Settings	72
2.19. Supported Hadoop Services	85
2.20. Apache Service Gateway Directores	86
2.21. Cluster Topology Provider and Service Roles	91
2.22. gateway-site.xml Configuration Elements	110
2.23. LDAP Authentication and Authorization Arguments	126
3.1. Ranger DB Host	139
3.2. Driver Class Name	140
3.3. Ranger DB Username Settings	140
3.4. JDBC Connect String	140
3.5. DBA Credential Settings	141
3.6. UNIX User Sync Properties	150
3.7. LDAP/AD Common Configs	152
3.8. LDAP/AD User Configs	153
3.9. LDAP/AD Group Configs	155
3.10. UNIX Authentication Settings	157
3.11. LDAP Authentication Settings	158
3.12. AD Settings	162
3.13. LDAP Advanced ranger-ugsync-site Settings	167
3.14. AD Advanced ranger-ugsync-site Settings	167
3.15. Advanced ranger-ugsync-site Settings for LDAP and AD	167
3.16. HDFS Plugin Properties	196
3.17. Hive Plugin Properties	196
3.18. HBase Plugin Properties	197
3.19. Knox Plugin Properties	197
3.20. Knox Configuration Properties	198
3.21. Service Details	203
3.22. Config Properties	204
3.23. Service Details	205
3.24. Config Properties	206
3.25. Service Details	207

3.26. Config Properties	208
3.27. Service Details	209
3.28. Config Properties	209
3.29. Service Details	211
3.30. Config Properties	211
3.31. Service Details	213
3.32. Config Properties	213
3.33. Service Details	215
3.34. Config Properties	215
3.35. Service Details	217
3.36. Config Properties	217
3.37. Policy Details	220
3.38. User and Group Permissions	220
3.39. Policy Details	223
3.40. User and Group Permissions	223
3.41. Policy Details	225
3.42. User and Group Permissions	225
3.43. Policy Details	228
3.44. User and Group Permissions	228
3.45. Policy Details	229
3.46. User and Group Permissions	230
3.47. Policy Details	231
3.48. User and Group Permissions	231
3.49. Policy Details	233
3.50. User and Group Permissions	233
3.51. Knox User and Group Permissions	234
3.52. Policy Details	235
3.53. User and Group Permissions	236
4.1. Components that Support SSL	289
4.2. Configure SSL Data Protection for HDP Components	298
4.3. Configuration Properties in ssl-server.xml	300
5.1. Solr install.properties Values	357
5.2. Solr install.properties Values	359
5.3. Search Criteria	365
5.4. Search Criteria	366
5.5. Search Criteria	367
5.6. Agents Search Criteria	368
6.1. Properties in Advanced dbks-site Menu (dbks-site.xml)	391
6.2. Properties in Advanced kms-env	391
6.3. Properties in Advanced kms-properties (install.properties)	391
6.4. Properties in Advanced kms-site (kms-site.xml)	392
6.5. Properties in Advanced ranger-kms-audit (ranger-kms-audit.xml)	393
6.6. Properties in Advanced ranger-kms-policymgr-ssl	394
6.7. Properties in Advanced ranger-kms-security	394
6.8. Troubleshooting Suggestions	395

1. HDP Security Overview

Security is essential for organizations that store and process sensitive data in the Hadoop ecosystem. Many organizations must adhere to strict corporate security policies.

Hadoop is a distributed framework used for data storage and large-scale processing on clusters using commodity servers. Adding security to Hadoop is challenging because all the interactions do not follow the classic client-server pattern. In Hadoop the file system is partitioned and distributed, requiring authorization checks at multiple points; a submitted job is executed at a later time on nodes different than the node on which the client authenticated and submitted the job; secondary services such as a workflow system access Hadoop on behalf of users; and the system scales to thousands of servers and tens of thousands of concurrent tasks.

A Hadoop-powered "Data Lake" can provide a robust foundation for a new generation of Big Data analytics and insight, but can also increase the number of access points to an organization's data. As diverse types of enterprise data are pulled together into a central repository, the inherent security risks must be understood and addressed.

Hortonworks understands the importance of security and governance for every business. To ensure effective protection for our customers, we use a holistic approach based on five core security features:

- Administration
- Authentication and perimeter security
- Authorization
- Audit
- Data protection

This chapter provides an overview of the security features implemented in the Hortonworks Data Platform (HDP). Subsequent chapters in this guide provide more details on each of these security features.

1.1. Understanding Data Lake Security


The general consensus in nearly every industry is that data is an essential new driver of competitive advantage. Hadoop plays a critical role in the modern data architecture by providing low-cost, large-scale data storage and processing. The successful Hadoop journey typically starts with data architecture optimization or new advanced analytic applications, which leads to the formation of a Data Lake. As new and existing types of data from sources such as machine sensors, server logs, clickstream data, and other sources flow into the Data Lake, it serves as a central repository based on shared Hadoop services that power deep organizational insights across a broad and diverse set of data.

The need to protect the Data Lake with comprehensive security is clear. As large and growing volumes of diverse data are channeled into the Data Lake, it will store vital and often highly sensitive business data. However, the external ecosystem of data and operational systems feeding the Data Lake is highly dynamic and can introduce new

security threats on a regular basis. Users across multiple business units can access the Data Lake freely and refine, explore, and enrich its data at will, using methods of their own choosing, further increasing the risk of a breach. Any breach of this enterprise-wide data can be catastrophic: privacy violations, regulatory infractions, or the compromise of vital corporate intelligence. To prevent damage to the company's business, customers, finances, and reputation, IT leaders must ensure that their Data Lake meets the same high standards of security as any legacy data environment.

Only as Secure as the Weakest Link

Piecemeal protections are no more effective for a Data Lake than they would be in a traditional repository. Hortonworks firmly believes that effective Hadoop security depends on a holistic approach. Our framework for comprehensive security revolves around five pillars of security: administration, authentication/ perimeter security, authorization, audit, and data protection.




Requirements for Enterprise-Grade Security

Security administrators must address questions and provide enterprise-grade coverage across each of these areas as they design the infrastructure to secure data in Hadoop. If any of these pillars is vulnerable, it will become a risk vector built into the very fabric of the company's Big Data environment. In this light, your Hadoop security strategy must address all five pillars, with a consistent implementation approach to ensure their effectiveness.

Needless to say, you can't achieve comprehensive protection across the Hadoop stack by using a hodgepodge of point solutions. Security must be an integral part of the platform on which your Data Lake is built. This bottom-up approach makes it possible to enforce and manage security across the stack through a central point of administration, thereby preventing gaps and inconsistencies. This approach is especially important for Hadoop implementations where new applications or data engines are always on the horizon in the form of new Open Source projects – a dynamic scenario that can quickly exacerbate any vulnerability.

Hortonworks helps customers maintain the high levels of protection for enterprise data by building centralized security administration and management into the infrastructure of the Hortonworks Data Platform. HDP provides an enterprise-ready data platform with


rich capabilities spanning security, governance, and operations. HDP includes powerful data security functionality that works across component technologies and integrates with preexisting EDW, RDBMS and MPP systems. By implementing security at the platform level, Hortonworks ensures that security is consistently administered to all of the applications across the stack, and simplifies the process of adding or removing Hadoop applications.



The Hortonworks Data Platform

1.2. HDP Security Features

HDP uses Apache Ranger to provide centralized security administration and management. The Ranger Administration Portal is the central interface for security administration. Users can create and update policies, which are then stored in a policy database. Ranger plugins (light-weight Java programs) are embedded within the processes of each cluster component. For example, the Ranger plugin for Apache Hive is embedded within HiveServer2.




Apache Ranger Architecture

These plugins pull policies from a central server and store them locally in a file. When a user request comes through the component, these plugins intercept the request and evaluate it against the security policy. Plugins also collect data from the user request and follow a separate thread to send this data back to the audit server.

1.2.1. Administration

In order to deliver consistent security administration and management, Hadoop administrators require a centralized user interface that can be used to define, administer and manage security policies consistently across all of the Hadoop stack components.



Ranger Centralized Security Administration

The Apache Ranger administration console provides a central point of administration for the other four pillars of Hadoop security.



Ranger Admin Console

1.2.2. Authentication and Perimeter Security

Establishing user identity with strong authentication is the basis for secure access in Hadoop. Users need to reliably identify themselves and then have that identity propagated throughout the Hadoop cluster to access cluster resources. Hortonworks uses Kerberos for authentication. Kerberos is an industry standard used to authenticate users and resources within a Hadoop cluster. HDP also includes Ambari, which simplifies Kerberos setup, configuration, and maintenance.

Apache Knox Gateway is used to ensure perimeter security for Hortonworks customers. With Knox, enterprises can confidently extend the Hadoop REST API to new users without

Kerberos complexities, while also maintaining compliance with enterprise security policies. Knox provides a central gateway for Hadoop REST APIs that have varying degrees of authorization, authentication, SSL, and SSO capabilities to enable a single access point for Hadoop.

Single, simple point of access for a cluster	Central controls ensure consistency across one or more clusters	Integrated with existing systems to simplify identity maintenance
<ul style="list-style-type: none">• Kerberos Encapsulation• Single Hadoop access point• REST API hierarchy• Consolidated API calls• Multi-cluster support	<ul style="list-style-type: none">• Eliminates SSH "edge node"• Central API management• Central audit control• Service level Authorization	<ul style="list-style-type: none">• SSO Integration – Siteminder and OAM*• LDAP & AD integration

Apache Knox Features

1.2.3. Authorization

Ranger manages fine-grained access control through a rich user interface that ensures consistent policy administration across Hadoop data access components. Security administrators have the flexibility to define security policies for a database, table and column, or a file, and can administer permissions for specific LDAP-based groups or individual users. Rules based on dynamic conditions such as time or geolocation, can also be added to an existing policy rule. The Ranger authorization model is highly pluggable and can be easily extended to any data source using a service-based definition.

Administrators can use Ranger to define a centralized security policy for the following Hadoop components:

- HDFS
- YARN
- Hive
- HBase
- Storm
- Knox
- Solr
- Kafka

Ranger works with standard authorization APIs in each Hadoop component, and is able to enforce centrally administered policies for any method used to access the data lake.

Policy Details :

Policy Name *	<input type="text" value="Customer_Details_Table"/>	<input checked="" type="radio"/> enabled
Hive Database *	<input type="text" value="xademo"/>	<input checked="" type="radio"/> include
table *	<input type="text" value="customer_details"/>	<input checked="" type="radio"/> include
Hive Column *	<input type="text" value="phone_number plan date"/>	<input checked="" type="radio"/> include
Description	<input type="text"/>	
Audit Logging	<input checked="" type="radio"/> YES	

add/edit permissions

- select
- update
- Create
- Drop
- Alter
- Index
- Lock
- All
- Select/Deselect All

User and Group Permissions :

Permissions	Select Group	Select User	Delegate Admin
	<input type="text" value="Marketing"/>	<input type="text" value="Mal Inara"/>	<input type="checkbox"/>
+			x
		Add Permissions	+
			x

Ranger Security Policy Definitions

Ranger provides administrators with deep visibility into the security administration process that is required for auditing purposes. The combination of Ranger's rich user interface with deep audit visibility makes it highly intuitive to use, enhancing productivity for security administrators.

The screenshot shows the Ranger Access Manager interface with the following details:

- Header:** Ranger, Access Manager, Audit, Settings, admin
- Breadcrumbs:** Service Manager > sandbox_hive Policies
- Title:** List of Policies : sandbox_hive
- Search Bar:** Search for your policy...
- Action Bar:** Add New Policy
- Table:** A grid of policy definitions with columns: Policy ID, Policy Name, Status, Audit Logging, Groups, Users, and Action.
- Data:** The table contains the following rows:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users	Action
3	sandbox_hive-1-20150529142947	Enabled	Enabled	--	exployee	Edit Delete
4	Hive Global Tables Allow	Disabled	Enabled	public	--	Edit Delete
5	Hive Global UDF Allow	Disabled	Enabled	public	--	Edit Delete
18	Call_Details_Table	Enabled	Enabled	developer	--	Edit Delete
19	Customer_Details_Table	Disabled	Enabled	Marketing	--	Edit Delete
20	Hive Demo Table Loader	Enabled	Enabled	--	hive	Edit Delete
21	Hive Demo UDF Loader	Enabled	Enabled	--	hive	Edit Delete
29	admin policy	Enabled	Enabled	--	admin	Edit Delete

Ranger Security Policy Overview

1.2.4. Audit

As customers deploy Hadoop into corporate data and processing environments, metadata and data governance must be vital parts of any enterprise-ready data lake. For these reasons, Hortonworks [established the Data Governance Initiative \(DGI\) with Aetna, Merck, Target, and SAS](#) to introduce a common approach to Hadoop data governance into the open source community. This initiative has since evolved into a new open source project called Apache Atlas. Apache Atlas is a set of core foundational governance services that enables enterprises to effectively and efficiently meet their compliance requirements within Hadoop, and also allows integration with the complete enterprise data ecosystem. These services include:

- Search and Lineage for datasets
- Metadata-driven data access control
- Indexed and searchable centralized auditing operational events
- Data lifecycle management – ingestion to disposition
- Metadata interchange with other tools

Ranger also provides a centralized framework for collecting access audit history and easily reporting this data, including the ability to filter data based on various parameters. HDP enhances audit information that is captured within various components within Hadoop, and provides insights through this centralized reporting capability.

1.2.5. Data Protection

Data protection adds a robust layer of security by making data unreadable in transit over the network or at rest on a disk. HDP fully satisfies enterprise requirements for security and compliance by using transparent data encryption ([TDE](#)) to encrypt data for HDFS files, along with a Ranger-embedded open source Hadoop key management store (KMS). Ranger provides security administrators with the ability to manage keys and authorization policies for KMS. Hortonworks is also working extensively with its encryption partners to integrate HDFS encryption with enterprise-grade key management frameworks. With Hortonworks, our customers have the flexibility to leverage an open source key management store (KMS), or use enterprise-wide KMS solutions provided by the partner ecosystem.

Encryption in HDFS, combined with KMS access policies maintained by Ranger, prevents rogue Linux or Hadoop administrators from accessing data, and supports segregation of duties for both data access and encryption.

2. Authentication

2.1. Enabling Kerberos Authentication Using Ambari

This chapter describes how to configure Kerberos for strong authentication for Hadoop users and hosts in an Ambari-managed cluster.

- [Kerberos Overview \[8\]](#)
- [Hadoop and Kerberos Principals \[9\]](#)
- [Installing and Configuring the KDC \[10\]](#)
- [Enabling Kerberos Security \[15\]](#)

2.1.1. Kerberos Overview

Strongly authenticating and establishing a user's identity is the basis for secure access in Hadoop. Users need to be able to reliably "identify" themselves and then have that identity propagated throughout the Hadoop cluster. Once this is done, those users can access resources (such as files or directories) or interact with the cluster (like running MapReduce jobs). Besides users, Hadoop cluster resources themselves (such as Hosts and Services) need to authenticate with each other to avoid potential malicious systems or daemon's "posing as" trusted components of the cluster to gain access to data.

Hadoop uses Kerberos as the basis for strong authentication and identity propagation for both user and services. Kerberos is a third party authentication mechanism, in which users and services rely on a third party - the Kerberos server - to authenticate each to the other. The Kerberos server itself is known as the **Key Distribution Center**, or **KDC**. At a high level, it has three parts:

- A database of the users and services (known as **principals**) that it knows about and their respective Kerberos passwords
- An **Authentication Server (AS)** which performs the initial authentication and issues a **Ticket Granting Ticket (TGT)**
- A **Ticket Granting Server (TGS)** that issues subsequent service tickets based on the initial TGT

A **user principal** requests authentication from the AS. The AS returns a TGT that is encrypted using the user principal's Kerberos password, which is known only to the user principal and the AS. The user principal decrypts the TGT locally using its Kerberos password, and from that point forward, until the ticket expires, the user principal can use the TGT to get service tickets from the TGS. Service tickets are what allow a principal to access various services.


Because cluster resources (hosts or services) cannot provide a password each time to decrypt the TGT, they use a special file, called a **keytab**, which contains the resource principal's authentication credentials. The set of hosts, users, and services over which the Kerberos server has control is called a **realm**.

Terminology

Term	Description
Key Distribution Center, or KDC	The trusted source for authentication in a Kerberos-enabled environment.
Kerberos KDC Server	The machine, or server, that serves as the Key Distribution Center (KDC).
Kerberos Client	Any machine in the cluster that authenticates against the KDC.
Principal	The unique name of a user or service that authenticates against the KDC.
Keytab	A file that includes one or more principals and their keys.
Realm	The Kerberos network that includes a KDC and a number of Clients.
KDC Admin Account	An administrative account used by Ambari to create principals and generate keytabs in the KDC.

2.1.2. Hadoop and Kerberos Principals

Each service and sub-service in Hadoop must have its own principal. A **principal** name in a given realm consists of a primary name and an instance name, in this case the instance name is the FQDN of the host that runs that service. As services do not log in with a password to acquire their tickets, their principal's authentication credentials are stored in a **keytab** file, which is extracted from the Kerberos database and stored locally in a secured directory with the service principal on the service component host.



Principals and Keytabs

Principal and Keytab Naming Conventions

Asset	Convention	Example
Principals	\$service_component_name/\$FQDN@EXAMPLE.COM	nn/c6401.ambari.apache.org@EXAMPLE.COM
Keytabs	\$service_component_abbreviation.service.keytab	/etc/security/keytabs/nn.service.keytab



Note

In addition to the Hadoop **Service Principals**, Ambari itself also requires a set of **Ambari Principals** to perform service "smoke" checks and alert health checks.

Keytab files for the Ambari, or headless, principals reside on each cluster host, just as keytab files for the service principals.

Notice in the preceding example the primary name for each service principal. These primary names, such as nn or hive for example, represent the NameNode or Hive service, respectively. Each primary name has appended to it the instance name, the FQDN of the host on which it runs. This convention provides a unique principal name for services that run on multiple hosts, like DataNodes and NodeManagers. Adding the host name serves to distinguish, for example, a request from DataNode A from a request from DataNode B. This is important for the following reasons:

- Compromised Kerberos credentials for one DataNode do not automatically lead to compromised Kerberos credentials for all DataNodes.
- If multiple DataNodes have exactly the same principal and are simultaneously connecting to the NameNode, and if the Kerberos authenticator being sent happens to have same timestamps, then the authentication is rejected as a replay request.

2.1.3. Installing and Configuring the KDC

Ambari is able to configure Kerberos in the cluster to work with an existing MIT KDC, or existing Active Directory installation. This section describes the steps necessary to prepare for this integration.



Note

If you do not have an existing KDC (MIT or Active Directory), [install a new MIT KDC](#). Please be aware that installing a KDC on a cluster host **after** installing the Kerberos client may overwrite the krb5.conf file generated by Ambari.

You can choose to have Ambari connect to the KDC and automatically create the necessary Service and Ambari principals, generate and distribute the keytabs ("Automated Kerberos Setup"). Ambari also provides an advanced option to manually configure Kerberos. If you choose this option, you must create the principals, generate and distribute the keytabs. Ambari will not do this automatically ("Manual Kerberos Setup").

Supported Key Distribution Center (KDC) Versions

- Microsoft Active Directory 2008 and above
- MIT Kerberos v5
- [Use an Existing MIT KDC \[10\]](#)
- [Use an Existing Active Directory \[11\]](#)
- [Use Manual Kerberos Setup \[11\]](#)

2.1.3.1. Use an Existing MIT KDC

To use an existing MIT Kerberos v5 KDC for the cluster, you must prepare the following:

- Ambari Server and cluster hosts have network access to both the KDC and KDC admin hosts.
- KDC administrative credentials are on-hand.

Proceed with [Enabling Kerberos Security in Ambari](#).

2.1.3.2. Use an Existing Active Directory

To use an existing Microsoft Active Directory 2008 and later domain for the cluster with Automated Kerberos Setup, you must prepare the following:

- Ambari Server and cluster hosts have network access to, and be able to resolve the DNS names of, the Domain Controllers.
- Active Directory secure LDAP (LDAPS) connectivity has been configured.
- Active Directory User container for principals has been created and is on-hand. For example, "OU=Hadoop,OU=People,dc=apache,dc=org"
- Active Directory administrative credentials with delegated control of "Create, delete, and manage user accounts" on the previously mentioned User container are on-hand.

Proceed with [Enabling Kerberos Security in Ambari](#).

2.1.3.3. Use Manual Kerberos Setup

To perform Manual Kerberos Setup, you must prepare the following:

- Cluster hosts have network access to the KDC.
- Kerberos client utilities (such as kinit) have been installed on every cluster host.
- The Java Cryptography Extensions (JCE) have been setup on the Ambari Server host and all hosts in the cluster.
- The Service and Ambari Principals will be manually created in the KDC before completing this wizard.
- The keytabs for the Service and Ambari Principals will be manually created and distributed to cluster hosts before completing this wizard.

Proceed with [Enabling Kerberos Security in Ambari](#).

2.1.3.4. (Optional) Install a new MIT KDC

The following gives a very high level description of the KDC installation process. To get more information see specific Operating Systems documentation, such as [RHEL documentation](#), [CentOS documentation](#), or [SLES documentation](#).



Note

Because Kerberos is a time-sensitive protocol, all hosts in the realm must be time-synchronized, for example, by using the Network Time Protocol (NTP).

If the local system time of a client differs from that of the KDC by as little as 5 minutes (the default), the client will not be able to authenticate.

Install the KDC Server

1. Install a new version of the KDC server:

RHEL/CentOS/Oracle Linux

```
yum install krb5-server krb5-libs krb5-workstation
```

SLES

```
zypper install krb5 krb5-server krb5-client
```

Ubuntu/Debian

```
apt-get install krb5-kdc krb5-admin-server
```

2. Using a text editor, open the KDC server configuration file, located by default here:

```
vi /etc/krb5.conf
```

3. Change the [realms] section of this file by replacing the default "kerberos.example.com" setting for the kdc and admin_server properties with the Fully Qualified Domain Name of the KDC server host. In the following example, "kerberos.example.com" has been replaced with "my.kdc.server".

```
[realms]
EXAMPLE.COM = {
    kdc = my.kdc.server
    admin_server = my.kdc.server
}
```



Note

For Ubuntu/Debian, the setup of the default realm for the KDC and KDC Admin hostnames is performed during the KDC server install. You can re-run setup using dpkg-reconfigure krb5-kdc. Therefore, Steps 2 and 3 above are not needed for Ubuntu/Debian.

Create the Kerberos Database

- Use the utility kdb5_util to create the Kerberos database.

RHEL/CentOS/Oracle Linux

```
kdb5_util create -s
```

SLES

```
kdb5_util create -s
```

Ubuntu/Debian

```
krb5_newrealm
```

Start the KDC

- Start the KDC server and the KDC admin server.

RHEL/CentOS/Oracle Linux 6

```
/etc/rc.d/init.d/krb5kdc start
```

```
/etc/rc.d/init.d/kadmin start
```

RHEL/CentOS/Oracle Linux 7

```
systemctl start krb5kdc
```

```
systemctl start kadmin
```

SLES 11

```
rckrb5kdc start
```

```
rckadmind start
```

Ubuntu/Debian

```
service krb5-kdc restart
```

```
service krb5-admin-server restart
```

Important



When installing and managing your own MIT KDC, it is **very important** to *set up the KDC server to auto-start on boot*. For example:

RHEL/CentOS/Oracle Linux 6

```
chkconfig krb5kdc on
```

```
chkconfig kadmin on
```

RHEL/CentOS/Oracle Linux 7

```
systemctl enable krb5kdc
```

```
systemctl enable kadmin
```

SLES 11

```
chkconfig rckrb5kdc on
```

```
chkconfig rckadmind on
```

Create a Kerberos Admin

Kerberos principals can be created either on the KDC machine itself or through the network, using an “admin” principal. The following instructions assume you are using the

KDC machine and using the `kadmin.local` command line administration utility. Using `kadmin.local` on the KDC machine allows you to create principals without needing to create a separate "admin" principal before you start.



Note

You will need to provide these admin account credentials to Ambari when enabling Kerberos. This allows Ambari to connect to the KDC, create the cluster principals and generate the keytabs.

1. Create a KDC admin by creating an admin principal.

```
kadmin.local -q "addprinc admin/admin"
```

2. Confirm that this admin principal has permissions in the KDC ACL. Using a text editor, open the KDC ACL file:

RHEL/CentOS/Oracle Linux

```
vi /var/kerberos/krb5kdc/kadm5.acl
```

SLES

```
vi /var/lib/kerberos/krb5kdc/kadm5.acl
```

Ubuntu/Debian

```
vi /etc/krb5kdc/kadm5.acl
```

3. Ensure that the KDC ACL file includes an entry so to allow the admin principal to administer the KDC for your specific realm. When using a realm that is different than EXAMPLE.COM, **be sure there is an entry for the realm you are using**. If not present, principal creation will fail. For example, for an `admin/admin@HADOOP.COM` principal, you should have an entry:

```
*/admin@HADOOP.COM *
```

4. After editing and saving the `kadm5.acl` file, you must restart the `kadmin` process.

RHEL/CentOS/Oracle Linux 6

```
/etc/rc.d/init.d/kadmin restart
```

RHEL/CentOS/Oracle Linux 7

```
systemctl restart kadmin
```

SLES 11

```
rckadmind restart
```

Ubuntu/Debian

```
service krb5-admin-server restart
```

2.1.4. Enabling Kerberos Security

Whether you choose automated or manual Kerberos setup, Ambari provides a wizard to help with enabling Kerberos in the cluster. This section provides information on preparing Ambari before running the wizard, and the steps to run the wizard.

- [Installing the JCE \[15\]](#)
- [Creating Mappings Between Principals and UNIX Usernames \[56\]](#)
- [Running the Kerberos Security Wizard \[16\]](#)

Important



Prerequisites for enabling Kerberos are having the JCE installed on all hosts on the cluster (including the Ambari Server) and having the Ambari Server host as part of the cluster. This means the Ambari Server host should be running an Ambari Agent.

You should also [create mappings between principals and UNIX user names](#). Creating mappings can help resolve access issues related to case mismatches between principal and local user names.

Note



Ambari Metrics will not be secured with Kerberos unless it is configured for distributed metrics storage. By default, it uses embedded metrics storage and will not be secured as part of the Kerberos Wizard. If you wish to have Ambari Metrics secured with Kerberos, please see [this topic](#) to enable distributed metrics storage prior to running the Kerberos Wizard.

2.1.4.1. Installing the JCE

Before enabling Kerberos in the cluster, you must deploy the Java Cryptography Extension (JCE) security policy files on the Ambari Server and on all hosts in the cluster.

Important



If you are using Oracle JDK, **you must distribute and install the JCE on all hosts** in the cluster, including the Ambari Server. **Be sure to restart Ambari Server after installing the JCE**. If you are using OpenJDK, some distributions of the OpenJDK come with unlimited strength JCE automatically and therefore, installation of JCE is not required.

2.1.4.1.1. Install the JCE

1. On the Ambari Server, obtain the JCE policy file appropriate for the JDK version in your cluster.
 - For Oracle JDK 1.8:

<http://www.oracle.com/technetwork/java/javase/downloads/jce8-download-2133166.html>

- For Oracle JDK 1.7:

<http://www.oracle.com/technetwork/java/javase/downloads/jce-7-download-432124.html>

2. Save the policy file archive in a temporary location.
3. On Ambari Server and on each host in the cluster, add the unlimited security policy JCE jars to \$JAVA_HOME/jre/lib/security/.

For example, run the following to extract the policy jars into the JDK installed on your host:

```
unzip -o -j -q jce_policy-8.zip -d /usr/jdk64/jdk1.8.0_40/jre/lib/security/
```

4. Restart Ambari Server: sudo ambari-server restart.
5. Proceed to [Running the Security Wizard](#).

2.1.4.2. Running the Kerberos Security Wizard

Ambari provides three options for enabling Kerberos:

- Existing MIT KDC
- Existing Active Directory
- Manage Kerberos principals and keytabs manually

When choosing **Existing MIT KDC** or **Existing Active Directory**, the Kerberos Wizard prompts for information related to the KDC, the KDC Admin Account and the Service and Ambari principals. Once provided, Ambari will automatically create principals, generate keytabs and distribute keytabs to the hosts in the cluster. The services will be configured for Kerberos and the service components are restarted to authenticate against the KDC. This is the **Automated Setup** option. See [Launching the Kerberos Wizard \(Automated Setup\)](#) for more details.

When choosing **Manage Kerberos principals and keytabs manually**, you must create the principals, generate and distribute the keytabs. Ambari will not do this automatically. This is the **Manual Setup** option. See [Launching the Kerberos Wizard \(Manual Setup\)](#) for more details.

2.1.4.2.1. Launching the Kerberos Wizard (Automated Setup)

1. Be sure you have [Installed and Configured your KDC](#) and have [prepared the JCE](#) on each host in the cluster.
2. Log in to Ambari Web and Browse to Admin > Kerberos.
3. Click “Enable Kerberos” to launch the wizard.
4. Select the type of KDC you are using and confirm you have met the prerequisites.

5. Provide information about the KDC and admin account.
 - a. (Optional) In the **Domains** field, provide a list of patterns to use to map hosts in the cluster to the appropriate realm. For example, if your hosts have a common domain in their FQDN such as host1.hortonworks.local and host2.hortonworks.local, you would set this to:

```
.hortonworks.local, hortonworks.local
```
 - b. (Optional) To manage your Kerberos client krb5.conf manually (and not have Ambari manage the krb5.conf), expand the **Advanced krb5-conf** section and uncheck the "Manage" option. **You must have the krb5.conf configured on each host.**
 - c. (Optional) to configure any additional KDC's to be used for this environment, add an entry for each additional KDC to the **realms** section of the **Advanced krb5-conf**'s krb5-conf template.

```
kdc = {{kdc_host}}
kdc = otherkdc.example.com
```
 - d. (Optional) To not have Ambari install the Kerberos client libraries on all hosts, expand the **Advanced kerberos-env** section and uncheck the "Install OS-specific Kerberos client package(s)" option. **You must have the Kerberos client utilities installed on each host.**
 - e. (Optional) If your Kerberos client libraries are in non-standard path locations, expand the **Advanced kerberos-env** section and adjust the "Executable Search Paths" option.
 - f. (Optional) If your KDC has a password policy, expand the **Advanced kerberos-env** section and adjust the Password options.
 - g. (Optional) Ambari will test your Kerberos settings by generating a test principal and authenticating with that principal. To customize the test principal name that Ambari will use, expand the **Advanced kerberos-env** section and adjust the **Test Principal Name** value. By default, the test principal name is a combination of cluster name and date **(\${cluster_name}-\${short_date})**. This test principal **will be deleted** after the test is complete.
 - h. (Optional) If you need to customize the attributes for the principals Ambari will create, when using Active Directory, see the [Customizing the Attribute Template](#) for more information. When using MIT KDC, you can pass **Principal Attribute** options in the **Advanced kerberos-env** section. For example, you can set options related to pre-auth or max. renew life by passing:

```
-requires_pcreauth -maxrenewlife "7 days"
```
6. Proceed with the install.
7. Ambari will install Kerberos clients on the hosts and test access to the KDC by testing that Ambari can create a principal, generate a keytab and distribute that keytab.
8. Customize the Kerberos identities used by Hadoop and proceed to kerberize the cluster.

Important



On the **Configure Identities** step, be sure to review the principal names, particularly the **Ambari Principals** on the **General** tab. These principal names, by default, append the name of the cluster to each of the Ambari principals. You can leave this as default or adjust these by removing the "-\${cluster-name}" from principal name string. For example, if your cluster is named HDP and your realm is EXAMPLE.COM, the hdfs principal will be created as hdfs-HDP@EXAMPLE.COM.

9. Confirm your configuration. You can optionally download a CSV file of the principals and keytabs that Ambari will automatically create.

10. Click **Next** to start the process.

11. After principals have been created and keytabs have been generated and distributed, Ambari updates the cluster configurations, then starts and tests the Services in the cluster.



Note

If your cluster includes Storm, after enabling Kerberos, you must also [set up Ambari for Kerberos](#) for Storm Service Summary information to be displayed in Ambari Web. Otherwise, you will see n/a for Storm information such as Slots, Tasks, Executors and Topologies.

12. Exit the wizard when complete.

2.1.4.2.2. Launching the Kerberos Wizard (Manual Setup)

1. Be sure you have [Installed and Configured your KDC](#) and have [prepared the JCE](#) on each host in the cluster.
2. Log in to Ambari Web and Browse to Admin > Kerberos.
3. Click "Enable Kerberos" to launch the wizard.
4. Select the **Manage Kerberos principals and keytabs manually** option and confirm you have met the prerequisites.
5. Provide information about the KDC and admin account.
 - a. If your Kerberos client libraries are in non-standard path locations, expand the **Advanced kerberos-env** section and adjust the "Executable Search Paths" option.
6. Customize the Kerberos identities used by Hadoop and proceed to kerberize the cluster.

Important



On the **Configure Identities** step, be sure to review the principal names, particularly the **Ambari Principals** on the **General** tab. These principal names,

by default, append the name of the cluster to each of the Ambari principals. You can leave this as default or adjust these by removing the "-\${cluster-name}" from principal name string. For example, if your cluster is named HDP and your realm is EXAMPLE.COM, the hdfs principal will be created as hdfs-HDP@EXAMPLE.COM.

7. Confirm your configuration. Since you have chosen the Manual Kerberos Setup option, obtain the CSV file for the list of principals and keytabs required for the cluster to work with Kerberos. **Do not proceed until you have manually created and distributed the principals and keytabs to the cluster hosts.**
8. Click **Next** to continue.
9. Ambari updates the cluster configurations, then starts and tests the Services in the cluster.
10. Exit the wizard when complete.

2.1.5. Kerberos Client Packages

If you chose to enable Kerberos using the Automated Kerberos Setup option, as part of the enabling Kerberos process, Ambari installs the Kerberos clients on the cluster hosts. Depending on your operating system, the following packages are installed:

Packages installed by Ambari for the Kerberos Client

Operating System	Packages
RHEL/CentOS/Oracle Linux 7	krb5-workstation
RHEL/CentOS/Oracle Linux 6	krb5-workstation
SLES 11	krb5-client
Ubuntu/Debian	krb5-user, krb5-config

2.1.6. Disabling Kerberos Security

After [Enabling Kerberos Security](#), you can disable Kerberos.

1. Log in to Ambari Web and Browse to Admin > Kerberos.
2. Click **Disable Kerberos** to launch the wizard.
3. Complete the wizard.



Note

If you have enabled Kerberos with an Automated Setup option, Ambari will attempt to contact the KDC and remove the principals created by Ambari. If the KDC is unavailable, the wizard will fail on the Unkerberize step. You can choose to ignore and continue the failure but removal of principals from the KDC will not be performed.

2.1.7. Customizing the Attribute Template

If you are using the Kerberos Automated setup with Active Directory, depending on your KDC policies, you can customize the attributes that Ambari sets when creating principals. On the Configure Kerberos step of the wizard, in the **Advanced kerberos-env** section, you have access to the Ambari Attribute Template. This template (which is based on the [Apache Velocity](#) templating syntax) can be modified to adjust which attributes are set on the principals and how those attribute values are derived.

The following table lists the set of computed attribute variables available if you choose to modify the template:

Attribute Variables	Example
\$normalized_principal	nn/c6401.ambari.apache.org@EXAMPLE.COM
\$principal_name	nn/c6401.ambari.apache.org
\$principal_primary	nn
\$principal_digest	[[MD5 hash of the \$normalized_principal]]
\$principal_instance	c6401.ambari.apache.org
\$realm	EXAMPLE.COM
\$password	[[password]]

2.1.8. Managing Admin Credentials

When you enable Kerberos, if you choose to use an **Existing MIT KDC or Existing Active Directory**, the Kerberos Wizard prompts for information related to the KDC, the KDC Admin Account credentials and the Service and Ambari principals. Once provided, Ambari will automatically create principals, generate keytabs and distribute keytabs to the hosts in the cluster. The services will be configured for Kerberos and the service components are restarted to authenticate against the KDC. This is the **Kerberos Automated Setup** option.

By default, Ambari will not retain the KDC Admin Account credentials you provide unless you have [encrypted the passwords stored in Ambari](#). If you have not configured Ambari for password encryption, you will be prompted to provide KDC Admin Account credentials whenever cluster changes are made that require KDC principal and/or keytab changes (such as adding services, components and hosts).

If you have configured Ambari for password encryption, you will have an option to Save Admin Credentials. Ambari will use the retained KDC Admin Account credentials to make the KDC changes automatically.



Save Admin Credentials 



Important

If you **do not** have password encryption enabled for Ambari, the Save Admin Credentials option **will not be** enabled.

Updating KDC Credentials

If you have chosen to Save Admin Credentials when enabling Kerberos, you can update or remove the credentials from Ambari using the following:

1. In Ambari Web, browse to **Admin > Kerberos** and click the **Manage KDC Credentials** button. The **Manage KDC Credentials** dialog is displayed.
2. If credentials have been previously saved, click **Remove** to remove the credentials currently stored in Ambari. Once removed, if cluster changes that require KDC principal and/or keytab changes (such as adding services, components and hosts), you will be prompted to enter the KDC Admin Account credentials.
3. Alternatively, to update the KDC Admin Account credentials, enter the Admin principal and password values and click **Save**.

2.2. Configuring Ambari Authentication with LDAP or AD

2.2.1. Configuring Ambari for LDAP or Active Directory Authentication

By default Ambari uses an internal database as the user store for authentication and authorization. If you want to configure LDAP or Active Directory (AD) external authentication, you need to [collect the following information](#) and [run a setup command](#).

Also, you must [synchronize your LDAP users and groups](#) into the Ambari DB to be able to manage authorization and permissions against those users and groups.



Note

When synchronizing LDAP users and groups, Ambari uses LDAP results paging controls to synchronize large numbers of LDAP objects. Most modern LDAP servers support these control, but for those that do not, such as Oracle Directory Server Enterprise Edition 11g, Ambari introduces a configuration parameter to disable pagination. The `authentication.ldap.pagination.enabled` property can be set to `false` in the `/etc/ambari-server/conf/ambari-properties` file to disable result paging controls. This will limit the maximum number of entities that can be imported at any given time to the maximum result limit of the LDAP server. To work around this, import sets of users or groups using the `-users` and `-groups` options covered in [section 3.1.4 - Specific Set of Users and Groups](#).

2.2.1.1. Setting Up LDAP User Authentication

The following table details the properties and values you need to know to set up LDAP authentication.



Note

If you are going to set `bindAnonymously` to false (the default), you need to make sure you have an LDAP Manager name and password set up. If you are going to use SSL, you need to make sure you have already set up your certificate and keys.

Ambari Server LDAP Properties

Property	Values	Description
<code>authentication.ldap.primaryUrl</code>	<code>server:port</code>	The hostname and port for the LDAP or AD server. Example: <code>my.ldap.server:389</code>
<code>authentication.ldap.secondaryUrl</code>	<code>server:port</code>	The hostname and port for the secondary LDAP or AD server. Example: <code>my.secondary.ldap.server:389</code> This is an optional value.
<code>authentication.ldap.useSSL</code>	true or false	If true, use SSL when connecting to the LDAP or AD server.
<code>authentication.ldap.usernameAttribute</code>	[LDAP attribute]	The attribute for username. Example: <code>uid</code>
<code>authentication.ldap.baseDn</code>	[Distinguished Name]	The root Distinguished Name to search in the directory for users. Example: <code>ou=people,dc=hadoop,dc=apache,dc=org</code>
<code>authentication.ldap.referral</code>	[Referral method]	Determines if LDAP referrals should be followed, or ignored.
<code>authentication.ldap.bindAnonymous</code>	true or false	If true, bind to the LDAP or AD server anonymously
<code>authentication.ldap.managerDn</code>	[Full Distinguished Name]	If Bind anonymous is set to false, the Distinguished Name ("DN") for the manager. Example: <code>uid=hdfs,ou=people,dc=hadoop,dc=apache,dc=org</code>
<code>authentication.ldap.managerPassword</code>	[password]	If Bind anonymous is set to false, the password for the manager
<code>authentication.ldap.userObjectClass</code>	[LDAP Object Class]	The object class that is used for users. Example: <code>organizationalPerson</code>
<code>authentication.ldap.groupObjectClass</code>	[LDAP Object Class]	The object class that is used for groups. Example: <code>groupOfUniqueNames</code>
<code>authentication.ldap.groupMembershipAttribute</code>	[LDAP attribute]	The attribute for group membership. Example: <code>uniqueMember</code>
<code>authentication.ldap.groupNameAttribute</code>	[LDAP attribute]	The attribute for group name.

2.2.1.2. Configure Ambari to use LDAP Server



Note

Only if you are using LDAPS, and the LDAPS server certificate is signed by a trusted Certificate Authority, there is no need to import the certificate into Ambari so this section does not apply to you. If the LDAPS server certificate is self-signed, or is signed by an unrecognized certificate authority such as an internal certificate authority, you must import the certificate and create a keystore file. The following example creates a keystore file at `/keys/ldaps-keystore.jks`, but you can create it anywhere in the file system:

Run the LDAP setup command on the Ambari server and answer the prompts, using the information you collected above:

1. `mkdir /etc/ambari-server/keys`

where the `keys` directory does not exist, but should be created.

2. \$JAVA_HOME/bin/keytool -import -trustcacerts -alias root -file \$PATH_TO_YOUR_LDAPS_CERT -keystore /etc/ambari-server/keys/ldaps-keystore.jks
3. Set a password when prompted. You will use this during ambari-server setup-ldap.
ambari-server setup-ldap
 1. At the Primary URL* prompt, enter the server URL and port you collected above. Prompts marked with an asterisk are required values.
 2. At the Secondary URL* prompt, enter the secondary server URL and port. This value is optional.
 3. At the Use SSL* prompt, enter your selection. **If using LDAPS**, enter true.
 4. At the User object class* prompt, enter the object class that is used for users.
 5. At the User name attribute* prompt, enter your selection. The default value is uid.
 6. At the Group object class* prompt, enter the object class that is used for groups.
 7. At the Group name attribute* prompt, enter the attribute for group name.
 8. At the Group member attribute* prompt, enter the attribute for group membership.
 9. At the Distinguished name attribute* prompt, enter the attribute that is used for the distinguished name.
10. At the Base DN* prompt, enter your selection.
11. At the Referral method* prompt, enter to follow or ignore LDAP referrals.
12. At the Bind anonymously* prompt, enter your selection.
13. At the Manager DN* prompt, enter your selection if you have set bind.Anonymously to false.
14. At the Enter the Manager Password* prompt, enter the password for your LDAP manager DN.
15. If you set Use SSL* = true in step 3, the following prompt appears: Do you want to provide custom TrustStore for Ambari?

Consider the following options and respond as appropriate.

- **More secure option:** If using a self-signed certificate that you do not want imported to the existing JDK keystore, enter y.

For example, you want this certificate used only by Ambari, not by any other applications run by JDK on the same host.

If you choose this option, additional prompts appear. Respond to the additional prompts as follows:

- At the TrustStore type prompt, enter jks.
- At the Path to TrustStore file prompt, enter /keys/ldaps-keystore.jks (or the actual path to your keystore file).
- At the Password for TrustStore prompt, enter the password that you defined for the keystore.
- **Less secure option:** If using a self-signed certificate that you want to import and store in the existing, default JDK keystore, enter n.

- Convert the SSL certificate to X.509 format, if necessary, by executing the following command:

```
openssl x509 -in slapd.pem -out <slapd.crt>
```

Where <slapd.crt> is the path to the X.509 certificate.

- Import the SSL certificate to the existing keystore, for example the default jre certificates storage, using the following instruction:

```
/usr/jdk64/jdk1.7.0_45/bin/keytool -import -trustcacerts -file slapd.crt -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

Where Ambari is set up to use JDK 1.7. Therefore, the certificate must be imported in the JDK 7 keystore.

16. Review your settings and if they are correct, select y.

17 Start or restart the Server

```
ambari-server restart
```

The users you have just imported are initially granted the Ambari User privilege. Ambari Users can read metrics, view service status and configuration, and browse job information. For these new users to be able to start or stop services, modify configurations, and run smoke tests, they need to be Admins. To make this change, as an Ambari Admin, use Manage Ambari > Users > Edit. For instructions, see Managing Users and Groups.

2.2.1.2.1. Example Active Directory Configuration

Directory Server implementations use specific object classes and attributes for storing identities. In this example, configurations specific to Active Directory are displayed as an example. Only those properties that are specific to Active Directory are displayed.

Run `ambari-server setup-ldap` and provide the following information about your Domain.

Prompt	Example AD Values
User object class* (posixAccount)	user
User name attribute* (uid)	sAMAccountName

Prompt	Example AD Values
Group object class* (posixGroup)	group
Group member attribute* (memberUid)	member
Distinguished name attribute* (dn)	distinguishedName

2.2.1.3. Synchronizing LDAP Users and Groups

Run the LDAP synchronize command and answer the prompts to initiate the sync:

```
ambari-server sync-ldap [option]
```



Note

To perform this operation, your Ambari Server must be running.

- When prompted, you must provide credentials for an Ambari Admin.
- When syncing ldap, Local user accounts with matching username will switch to LDAP type, which means their authentication will be against the external LDAP and not against the Local Ambari user store.
- LDAP sync only syncs up-to-1000 users. If your LDAP contains over 1000 users and you plan to import over 1000 users, you must use the –users option when syncing and specify a filtered list of users to perform import in batches.

The utility provides three options for synchronization:

- Specific set of users and groups, or
- Synchronize the existing users and groups in Ambari with LDAP, or
- All users and groups

Review log files for failed synchronization attempts, at `/var/log/ambari-server/ambari-server.log` on the Ambari Server host.



Note

When synchronizing LDAP users and groups, Ambari uses LDAP results paging controls to synchronize large numbers of LDAP objects. Most modern LDAP servers support these control, but for those that do not, such as Oracle Directory Server Enterprise Edition 11g, Ambari introduces a configuration parameter to disable pagination. The `authentication.ldap.pagination.enabled` property can be set to false in the `/etc/ambari-server/conf/ambari-properties` file to disable result paging controls. This will limit the maximum number of entities that can be imported at any given time to the maximum result limit of the LDAP server. To work around this, import sets of users or groups using the `-users` and `-groups` options covered in [section 3.1.4 - Specific Set of Users and Groups](#).

2.2.1.4. Specific Set of Users and Groups

```
ambari-server sync-ldap --users users.txt --groups groups.txt
```

Use this option to synchronize a specific set of users and groups from LDAP into Ambari. Provide the command a text file of comma-separated users and groups. The comma separated entries in each of these files should be based off of the values in LDAP of the attributes chosen during setup. The "User name attribute" should be used for the users.txt file, and the "Group name attribute" should be used for the groups.txt file. This command will find, import, and synchronize the matching LDAP entities with Ambari.



Note

Group membership is determined using the Group Membership Attribute (groupMembershipAttr) specified during setup-ldap. User name is determined by using the Username Attribute (usernameAttribute) specified during setup-ldap.

2.2.1.5. Existing Users and Groups

```
ambari-server sync-ldap --existing
```

After you have performed a synchronization of a [specific set of users and groups](#), you use this option to synchronize only those entities that are in Ambari with LDAP. Users will be removed from Ambari if they no longer exist in LDAP, and group membership in Ambari will be updated to match LDAP.



Note

Group membership is determined using the Group Membership Attribute specified during setup-ldap.

2.2.1.6. All Users and Groups



Important

Only use this option if you are sure you want to synchronize all users and groups from LDAP into Ambari. If you only want to synchronize a subset of users and groups, use a [specific set of users and groups](#) option.

```
ambari-server sync-ldap --all
```

This will import all entities with matching LDAP user and group object classes into Ambari.

2.2.2. Configuring Ranger Authentication with UNIX, LDAP, or AD

2.2.2.1. UNIX Authentication Settings

The following figure shows the UNIX authentication settings, and the table below describes each of these properties.




Table 2.1. UNIX Authentication Settings

Configuration Property
Allow remote Login
ranger.unixauth.service.hostname
ranger.unixauth.service.port

2.2.2.2. Active Directory Authentication Settings

This section describes how to configure settings for Active Directory authentication.



Note

In addition to these settings, you may also need to configure the Active Directory properties described in Configuring Usersync Settings.

2.2.2.2.1. AD Settings

The following figure shows the Active Directory (AD) authentication settings, and the table below describes each of these properties.




Table 2.2. Active Directory Authentication Settings

Configuration Property Name	Description	Default Value	Example Value	Required?
ranger.ldap.ad.domain	Server domain name (or IP address) where ranger-usersync module is running (along with the AD Authentication Service). The default value of "localhost" must be changed to the domain name.	localhost	example.com	Yes, if Active Directory authentication is selected.
ranger.ldap.ad.url	The URL and port number where ranger-usersync module is running the AD Authentication Service. The default value is a placeholder and must be changed to point to the AD server.	ldap://ad.xasecure.net:389	ldap://127.0.0.1:389	Yes, if Active Directory authentication is selected.

2.2.2.2.2. Custom ranger-admin-site Settings for Active Directory (Optional)

The following Custom ranger-admin-site settings for Active Directory authentication are optional.

To add a Custom ranger-admin-site property:

1. Select **Custom ranger-admin-site**, then click **Add Property**.

The screenshot shows a configuration interface for the Hortonworks Data Platform. The left side features a tree view of settings categories. At the top, under 'AD Settings', there are two properties: 'ranger.ldap.ad.domain' set to 'localhost' and 'ranger.ldap.ad.url' set to 'ldap://ad.xasecure.net:389'. Below this, several other sections are listed: 'LDAP Settings', 'Advanced ranger-admin-site' (which is expanded), 'Advanced ranger-env', 'Advanced ranger-ugsync-site', 'Custom admin-properties', 'Custom ranger-admin-site' (which is expanded), and 'Custom ranger-site', 'Custom ranger-ugsync-site', 'Custom usersync-properties'. The 'Add Property ...' button within the 'Custom ranger-admin-site' section is highlighted with a red box.

2. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.

The screenshot shows a modal dialog titled "Add Property". The "Type" field contains "ranger-site.xml". The "Key" field contains "ranger.ldap.ad.base_dn". The "Value" field contains "dc=example,dc=com". At the bottom right are "Cancel" and "Add" buttons.

The following figure shows the Custom ranger-admin-site settings required for Active Directory (AD) authentication, and the table below describes each of these properties.

The screenshot shows a configuration interface for "Custom ranger-site". It lists four properties with their values and edit icons:

- ranger.ldap.ad.base_dn: dc=example,dc=com
- ranger.ldap.ad.bind_dn: cn=adadmin,cn=Users,dc=example,dc=com
- ranger.ldap.ad.bind.password: secret123!
- ranger.ldap.ad.referral: follow

Each property row has a green plus sign and a red minus sign to its right.

Table 2.3. Active Directory Custom ranger-admin-site Settings

Custom Property Name	Sample Values for AD Authentication
ranger.ldap.ad.base_dn	dc=example,dc=com
ranger.ldap.ad.bind_dn	cn=adadmin,cn=Users,dc=example,dc=com
ranger.ldap.ad.bind.password	secret123!
ranger.ldap.ad.referral	follow ignore throw

There are three possible values for `ranger.ldap.ad.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the AD service provider processes all of the normal entries first, and then follows the continuation references.

- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search. In the case of AD, a `PartialResultException` is returned when referrals are encountered while search results are processed.

2.2.2.3. LDAP Authentications Settings

This section describes how to configure LDAP and Advanced ranger-ugsync-site settings for Active Directory authentication.



Note

In addition to these settings, you must also configure the LDAP properties described in Configuring Usersync Settings.

2.2.2.3.1. LDAP Settings

The following figure shows the LDAP authentication settings, and the table below describes each of these properties.




Table 2.4. LDAP Authentication Settings

Configuration Property Name	Description	Default Value	Example Value	Required?
ranger.ldap.url	The URL and port number where ranger-usersync module is running the LDAP Authentication Service.	ldap://71.127.43.33:389	ldap://127.0.0.1:389	Yes, if LDAP authentication is selected.
ranger.ldap.user.dnpattern	The domain name pattern.	uid={0},ou=users,dc=xasecure,dc=net	cn=ldapadmin,ou=Users,dc=example,dc=com	Yes, if LDAP authentication is selected.
ranger.ldap.group.roleattribute	The LDAP group role attribute.	cn	cn	Yes, if LDAP authentication is selected.

2.2.2.3.2. Custom ranger-admin-site Settings for LDAP (Optional)

The following Custom ranger-admin-site settings for LDAP are optional.

To add a Custom ranger-admin-site property:

1. Select **Custom ranger-admin-site**, then click **Add Property**.

The screenshot shows a configuration interface for ranger-admin-site settings. At the top, under 'AD Settings', there are two properties: 'ranger.ldap.ad.domain' set to 'localhost' and 'ranger.ldap.ad.url' set to 'ldap://ad.xassecure.net:389'. Below this, a tree view lists several sections: 'LDAP Settings', 'Advanced ranger-admin-site' (selected), 'Advanced ranger-env', 'Advanced ranger-ugsync-site', 'Custom admin-properties', 'Custom ranger-admin-site' (selected), and three other items: 'Custom ranger-site', 'Custom ranger-ugsync-site', and 'Custom usersync-properties'. The 'Add Property ...' button within the 'Custom ranger-admin-site' section is highlighted with a red box.

2. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.

The screenshot shows a 'Add Property' dialog box. The 'Type' field contains 'ranger-admin-site.xml'. The 'Key' field contains 'ranger.ldap.base_dn'. The 'Value' field contains 'dc=example,dc=com'. At the bottom right, there are 'Cancel' and 'Add' buttons, with 'Add' being highlighted by a red box.

The following figure shows the Custom ranger-admin-site settings required for LDAP authentication, and the table below describes each of these properties.

The screenshot shows the 'Custom ranger-site' configuration page. It lists four properties with their values: 'ranger.ldap.ad.base_dn' is 'dc=example,dc=com'; 'ranger.ldap.ad.bind_dn' is 'cn=adadmin,cn=Users,dc=example,dc=com'; 'ranger.ldap.ad.bind.password' is 'secret123!'; and 'ranger.ldap.referral' is 'follow'. There is also a link 'Add Property ...' at the bottom left.

Table 2.5. LDAP Custom ranger-admin-site Settings

Custom Property Name	Sample Values for AD or LDAP Authentication
ranger.ldap.base_dn	dc=example,dc=com
ranger.ldap.bind_dn	cn=adadmin,cn=Users,dc=example,dc=com
ranger.ldap.bind.password	secret123!
ranger.ldap.referral	follow ignore throw

There are three possible values for `ranger.ldap.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the LDAP service provider processes all of the normal entries first, and then follows the continuation references.
- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search.

2.2.2.3.3. Advanced ranger-admin-site Settings

The following Advanced ranger-admin-site properties apply only to LDAP authentication.

Table 2.6. Active Directory Authentication Settings

Property Name	Sample values for LDAP Authentication
<code>ranger.ldap.group.searchbase</code>	<code>dc=example,dc=com</code>
<code>ranger.ldap.group.searchfilter</code>	<code>(member=cn={0},ou=Users,dc=example,dc=com)</code>

2.2.3. Encrypting Database and LDAP Passwords in Ambari

By default the passwords to access the Ambari database and the LDAP server are stored in a plain text configuration file. To have those passwords encrypted, you need to run a special setup command.

Ambari Server should not be running when you do this: either make the edits before you start Ambari Server the first time or bring the server down to make the edits.

1. On the Ambari Server, run the special setup command and answer the prompts:

```
ambari-server setup-security
```

- a. Select Option 2: Choose one of the following options:

- [1] Enable HTTPS for Ambari server.
- [2] Encrypt passwords stored in `ambari.properties` file.
- [3] Setup Ambari kerberos JAAS configuration.

- b. Provide a master key for encrypting the passwords. You are prompted to enter the key twice for accuracy.

If your passwords are encrypted, you need access to the master key to start Ambari Server.

- c. You have three options for maintaining the master key:

- Persist it to a file on the server by pressing `y` at the prompt.
- Create an environment variable `AMBARI_SECURITY_MASTER_KEY` and set it to the key.

- Provide the key manually at the prompt on server start up.
- d. Start or restart the Server
- ```
ambari-server restart
```

### 2.2.3.1. Reset Encryption

There may be situations in which you want to:

- [Remove Encryption Entirely \[36\]](#)
- [Change the current master key](#), either because the key has been forgotten or because you want to change the current key as a part of a security routine.

Ambari Server should not be running when you do this.

### 2.2.3.2. Remove Encryption Entirely

To reset Ambari database and LDAP passwords to a completely unencrypted state:

1. On the Ambari host, open `/etc/ambari-server/conf/ambari.properties` with a text editor and set this property  

```
security.passwords.encryption.enabled=false
```
2. Delete `/var/lib/ambari-server/keys/credentials.jceks`
3. Delete `/var/lib/ambari-server/keys/master`
4. You must now reset the database password and, if necessary, the LDAP password. Run [ambari-server setup](#) and [ambari-server setup-ldap](#) again.

### 2.2.3.3. Change the Current Master Key

To change the master key:

- If you know the current master key or if the current master key has been persisted:

1. Re-run the encryption setup command and follow the prompts.

```
ambari-server setup-security
```

- a. Select Option 2: Choose one of the following options:

- [1] Enable HTTPS for Ambari server.
- [2] Encrypt passwords stored in `ambari.properties` file.
- [3] Setup Ambari kerberos JAAS configuration.

- b. Enter the current master key when prompted if necessary (if it is not persisted or set as an environment variable).

- c. At the Do you want to reset Master Key prompt, enter yes.
  - d. At the prompt, enter the new master key and confirm.
- If you do **not** know the current master key:
    - Remove encryption entirely, as described [here](#).
    - Re-run ambari-server setup-security as described [here](#).
    - Start or restart the Ambari Server.  
ambari-server restart

## 2.3. Configuring LDAP Authentication in Hue

You can configure Hue to authenticate users by using LDAP, including importing users and groups from the LDAP directory service, OpenLDAP, or through Active Directory (AD).

Integrating Hue with LDAP enables users to leverage existing authentication credentials' group permissions directly from their LDAP profiles.

For you to configure LDAP authentication in Hue, Hue must be running and the Hue UI must be accessible.

Each of the following subsections describes a property that needs to be setup for Hue to work with LDAP.

### 2.3.1. Enabling the LDAP Backend

To use LDAP, you must specify the following Hue values in the Hue configuration file, /etc/hue/conf/hue.ini. Specifying this configuration enables Hue to validate login credentials against the LDAP directory service:

```
[desktop]
 [[auth]]

 backend=desktop.auth.backend.LdapBackend

```

### 2.3.2. Enabling User Authentication with Search Bind

Settings related to LDAP are in the LDAP section of the Hue configuration file, /etc/hue/conf/hue.ini:

```
[desktop]
 [[ldap]]
```

There are two ways to authenticate users by using the LDAP directory service in Hue:

- Search Bind (default)

Setting the `search_bind_authentication` property to `true` in `/etc/hue/conf/hue.ini` enables LDAP search using the bind credentials specified for the `bind_dn` and `bind_password` properties.

Search bind performs an LDAP search against the directory service and then binds the results by using the found Distinguished Name (DN) and provided password. The search process starts from the base DN specified for the `base_dn` property and continues to search the base DN for an entry with an attribute that matches the specified in `user_name_attr` of the username provided at login.

You can restrict the results of this search process by using the `user_filter` (default value `objectclass=*`) and `user_name_attr` (default value `sAMAccountName`) properties in the `[desktop] > [[ldap]] > [[[users]]]` section of `/etc/hue/conf/hue.ini`.

If you use the default values of `user_filter` and `user_name_attr`, the LDAP search filter appears as follows, where `<username>` is the user name provided on the Hue login page:

```
(&(objectClass=*)(sAMAccountName=<username>))
```

- Direct Bind

Setting the `search_bind_authentication` property to `false` in `/etc/hue/conf/hue.ini` enables the LDAP direct bind mechanism to authenticate users. Hue binds to the LDAP server using the user name and password provided on the login page.

Depending on the value of the `nt_domain` property, there are two ways that direct bind works:

- If `nt_domain` is specified, the `nt_domain` property is intended to be used only with Active Directory (AD) service.

This property allows Hue to authenticate with AD without having to follow LDAP references to other partitions.

Hue forms the User Principal Name (UPN) as a concatenation of the user name provided on the Hue login page and the `nt_domain` property value: for example, `<username>@<nt_domain>`. The `ldap_username_pattern` property is ignored.

- If `nt_domain` is not specified, the `nt_domain` property is intended to be used for all other directory services.

Without the `nt_domain` property specified, the `ldap_username_pattern` appears as follows, where `<username>` is the user name provided on the Hue login page:

```
uid=<username>,ou=People,dc=mycompany,dc=com
```

### 2.3.3. Setting the Search Base to Find Users and Groups

You must set the correct `base_dn` value in the `/etc/hue/conf/hue.ini` file to enable Hue to find users and groups:

```
The search base for finding users and groups
base_dn="DC=mycompany,DC=com"
```

## 2.3.4. Specifying the URL of the LDAP Server

Specify the following URL in the `/etc/hue/conf/hue.ini` file to specify the endpoint of the corporate LDAP server:

```
URL of the LDAP server
ldap_url=ldap://auth.mycompany.com
```

## 2.3.5. Specifying LDAPS and StartTLS Support

LDAPS (secure communication with LDAP) is provided using the SSL/TLS and StartTLS protocols. Using these protocols allows Hue to validate the directory service with which it is going to interact. Optionally, specify the path to the certificate for authentication over TLS in the `/etc/hue/conf/hue.ini` file:

```
A PEM-format file containing certificates for the CA's that
Hue will trust for authentication over TLS.
The certificate for the CA that signed the
LDAP server certificate must be included among these certificates.
See more here http://www.openldap.org/doc/admin24/tls.html.
ldap_cert=<path/to/cert/file
use_start_tls=true
```

## 2.3.6. Specifying Bind Credentials for LDAP Searches

If the LDAP server does not support anonymous searches, you must specify the distinguished name of the user to bind and the bind password in the `/etc/hue/conf/hue.ini` file:

```
Distinguished name of the user to bind as -- not necessary if the LDAP
server
supports anonymous searches
bind_dn="CN=ServiceAccount,DC=mycompany,DC=com"

Password of the bind user -- not necessary if the LDAP server supports
anonymous searches
bind_password=your_password
```

## 2.3.7. Synchronizing Users and Groups

You can use the LDAP username pattern to restrict users when performing searches. Using this pattern provides a template for the DN that is sent to the directory service when authenticating. Replace the `<username>` parameter with the user name provided on the Hue login page. Specify this pattern in the `/etc/hue/conf/hue.ini` file:

```
Pattern for searching for usernames -- Use <username> for the parameter
For use when using LdapBackend for Hue authentication
ldap_username_pattern="uid=<username>,ou=People,dc=mycompany,dc=com"
```

When performing the authentication, Hue must import users to its database to work properly. In this case, passwords are never imported.

By default, the LDAP authentication backend automatically creates users that do not exist in Hue database. The purpose of disabling the automatic import process is to allow only a predefined list of manually imported users to log in.

```
Create users in Hue when they try to login with their LDAP credentials
For use when using LdapBackend for Hue authentication
create_users_on_login = true
```

You can specify that user groups be synchronized when a user logs in (to keep the user permission up to date):

```
Synchronize a users groups when they login
sync_groups_on_login=false
```

You can configure Hue to ignore username lettercasing or to force lowercasing:

```
Ignore the case of usernames when searching for existing users in Hue.
ignore_username_case=false

Force usernames to lowercase when creating new users from LDAP.
force_username_lowercase=false
```

## 2.3.8. Setting Search Bind Authentication and Importing Users and Groups

Hue uses search bind authentication by default. To enable direct bind authentication, set the `search_bind_authentication` property to `false` in the `/etc/hue/conf/hue.ini` file:

```
Do not use search bind authentication.
search_bind_authentication=false
```

When you set search bind authentication and you also need to set the kind of subgrouping and referrals for users and groups in the `/etc/hue/conf/hue.ini` file:

```
Choose which kind of subgrouping to use: nested or suboordinate(deprecated).
subgroups=subordinate

Define the number of levels to search for nested members.
nested_members_search_depth=10

Whether or not to follow referrals
follow_referrals=false
```

## 2.3.9. Setting LDAP Users' Filter

You can restrict user access by setting the LDAP filter (`user_filter` attribute) and the `username` attribute in the LDAP schema (`user_name_attr` attribute) in the `/etc/hue/conf/hue.ini` file. The typical attributes for search in the LDAP schema are `uid` and `SAMAccountName`:

```
[[[users]]]

Base filter for searching for users
user_filter="objectclass=*"

The username attribute in the LDAP schema
user_name_attr=sAMAccountName
```

## 2.3.10. Setting an LDAP Groups Filter

You can restrict the synchronization of LDAP directory groups when using the Hue useradmin application by setting a base filter (`group_filter` attribute) and the `username` attribute in the LDAP schema (`group_name_attr` attribute) of the `/etc/hue/conf/hue.ini` file:

```
[[[groups]]]

Base filter for searching for groups
group_filter="objectclass=*"

The username attribute in the LDAP schema
group_name_attr=cn
```

## 2.3.11. Setting Multiple LDAP Servers

Hue enables you to configure multiple LDAP servers by providing the multiple server declaration in `/etc/hue/conf/hue.ini`:

```
[[[ldap_servers]]]

[[[[mycompany]]]]

The search base for finding users and groups
base_dn="DC=mycompany,DC=com"

URL of the LDAP server
ldap_url=ldap://auth.mycompany.com

A PEM-format file containing certificates for the CA's that
Hue will trust for authentication over TLS.
The certificate for the CA that signed the
LDAP server certificate must be included among these certificates.
See more here http://www.openldap.org/doc/admin24/tls.html.
ldap_cert=
use_start_tls=true

Distinguished name of the user to bind as -- not necessary if the LDAP
server
supports anonymous searches
bind_dn="CN=ServiceAccount,DC=mycompany,DC=com"

Password of the bind user -- not necessary if the LDAP server supports
anonymous searches
bind_password=your_password

Pattern for searching for usernames -- Use <username> for the parameter
```

```
For use when using LdapBackend for Hue authentication
ldap_username_pattern="uid=<username>,ou=People,dc=mycompany,dc=com"

Whether or not to follow referrals
follow_referrals=false

[[[[[users]]]]]

Base filter for searching for users
user_filter="objectclass=Person"

The username attribute in the LDAP schema
user_name_attr=sAMAccountName

[[[[[groups]]]]]

Base filter for searching for groups
group_filter="objectclass=groupOfNames"

The username attribute in the LDAP schema
group_name_attr=cn
```

## 2.4. Advanced Security Options for Ambari

This section describes several security options for an Ambari-monitored-and-managed Hadoop cluster.

- [Configuring Ambari for Non-Root \[42\]](#)
- [Optional: Ambari Web Inactivity Timeout \[45\]](#)
- [Set Up Kerberos for Ambari Server \[46\]](#)
- [Optional: Set Up Two-Way SSL Between Ambari Server and Ambari Agents \[47\]](#)
- [Optional: Configure Ciphers and Protocols for Ambari Server \[47\]](#)
- [Optional: HTTP Cookie Persistence \[47\]](#)

### 2.4.1. Configuring Ambari for Non-Root

In most secure environments, restricting access to and limiting services that run as root is a hard requirement. For these environments, Ambari can be configured to operate without direct root access. Both Ambari Server and Ambari Agent components allow for non-root operation, and the following sections will walk you through the process.

- [How to Configure Ambari Server for Non-Root \[42\]](#)
- [How to Configure an Ambari Agent for Non-Root \[43\]](#)

#### 2.4.1.1. How to Configure Ambari Server for Non-Root

You can configure the Ambari Server to run as a non-root user.

During the [ambari-server setup](#) process, when prompted to Customize user account for ambari-server daemon?, choose y.

The setup process prompts you for the appropriate, non-root user to run the Ambari Server as; for example: ambari.



### Note

The non-root user you choose to run the Ambari Server should be part of the Hadoop group. This group must match the service Hadoop group accounts referenced in the Customize Services > Misc tab during the Install Wizard configuration step. The default group name is hadoop but if you customized this value during cluster install, be sure to make the non-root user a part of that group. See [Customizing HDP Services](#) for more information on service account users and groups.



### Note

If Ambari Server is running as a non-root user, such as 'ambari', and you are planning on using Ambari Views, the following properties in **Services > HDFS > Configs > Advanced core-site** must be added:

```
hadoop.proxyuser.ambari.groups=*
hadoop.proxyuser.ambari.hosts=*
```

## 2.4.1.2. How to Configure an Ambari Agent for Non-Root

You can configure the Ambari Agent to run as a non-privileged user as well. That user requires specific sudo access in order to su to Hadoop service accounts and perform specific privileged commands. Configuring Ambari Agents to run as non-root requires that you manually install agents on all nodes in the cluster. For these details, see [Installing Ambari Agents Manually](#). After installing each agent, you must configure the agent to run as the desired, non-root user. In this example we will use the `ambari` user.

Change the `run_as_user` property in the `/etc/ambari-agent/conf/ambari-agent.ini` file, as illustrated below:

```
run_as_user=ambari
```

Once this change has been made, the `ambari-agent` must be restarted to begin running as the non-root user.

The non-root functionality relies on sudo to run specific commands that require elevated privileges as defined in the [Sudoer Configuration](#). The sudo configuration is split into three sections: [Customizable Users](#), [Non-Customizable Users](#), [Commands](#), and [Sudo Defaults](#).

### 2.4.1.2.1. Sudoer Configuration

The [Customizable Users](#), [Non-Customizable Users](#), [Commands](#), and [Sudo Defaults](#) sections will cover how sudo should be configured to enable Ambari to run as a non-root user. Each of the sections includes the specific sudo entries that should be placed in `/etc/sudoers` by running the `visudo` command.

### 2.4.1.2.2. Customizable Users

This section contains the `su` commands and corresponding Hadoop service accounts that are configurable on install:

```
Ambari Customizable Users
ambari ALL=(ALL) NOPASSWD:SETENV: /bin/su hdfs *,/bin/su ambari-qa *,/bin/su
ranger *,/bin/su zookeeper *,/bin/su knox *,/bin/su falcon *,/bin/su ams *,
/bin/su flume *,/bin/su hbase *,/bin/su spark *,/bin/su accumulo *,/bin/su
hive *,/bin/su hcat *,/bin/su kafka *,/bin/su mapred *,/bin/su oozie *,/bin/
su sqoop *,/bin/su storm *,/bin/su tez *,/bin/su atlas *,/bin/su yarn *,/bin/
su kms *
```



### Note

These user accounts must match the service user accounts referenced in the Customize Services > Misc tab during the Install Wizard configuration step. For example, if you customize YARN to run as xyz\_yarn, modify the su command above to be /bin/su xyz\_yarn.

These user accounts must match the service user accounts referenced in the Customize Services > Misc tab during the Install Wizard configuration step. For example, if you customize YARN to run as xyz\_yarn, modify the su command above to be /bin/su xyz\_yarn.

#### 2.4.1.2.3. Non-Customizable Users

This section contains the su commands for the system accounts that cannot be modified, and is **only required** if you are using the Ambari-installed-and-managed MySQL instance for the Hive Metastore. If you choose to use an existing MySQL, PostgreSQL or Oracle database for the Hive Metastore, you do not need to include this sudoer command.

```
Ambari Non-Customizable Users
ambari ALL=(ALL) NOPASSWD:SETENV: /bin/su mysql *
```

#### 2.4.1.2.4. Commands

This section contains the specific commands that must be issued for standard agent operations:

```
Ambari Commands
ambari ALL=(ALL) NOPASSWD:SETENV: /usr/bin/yum,/usr/bin/zypper,/usr/bin/apt-
get, /bin/mkdir, /usr/bin/test, /bin/ln, /bin/chown, /bin/chmod, /bin/chgrp,
/usr/sbin/groupadd, /usr/sbin/groupmod, /usr/sbin/useradd, /usr/sbin/usermod,
/bin/cp, /usr/sbin/setenforce, /usr/bin/test, /usr/bin/stat, /bin/mv, /bin/
sed, /bin/rm, /bin/kill, /bin/readlink, /usr/bin/pgrep, /bin/cat, /usr/bin/
unzip, /bin/tar, /usr/bin/tee, /bin/touch, /usr/bin/hdp-select, /usr/bin/
conf-select, /usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh, /usr/lib/
hadoop/bin/hadoop-daemon.sh, /usr/lib/hadoop/sbin/hadoop-daemon.sh, /sbin/
chkconfig gmond off, /sbin/chkconfig gmetad off, /etc/init.d/httpd *, /sbin/
service hdp-gmetad start, /sbin/service hdp-gmond start, /usr/sbin/gmond, /
usr/sbin/update-rc.d ganglia-monitor *, /usr/sbin/update-rc.d gmetad *, /etc/
init.d/apache2 *, /usr/sbin/service hdp-gmond *, /usr/sbin/service hdp-gmetad
*, /sbin/service mysqld *, /usr/bin/python2.6 /var/lib/ambari-agent/data/tmp/
validateKnoxStatus.py *, /usr/hdp/current/knox-server/bin/knoxcli.sh *, /usr/
bin/dpkg *, /bin/rpm *, /usr/sbin/hst *
```

```
Ambari Ranger Commands
ambari ALL=(ALL) NOPASSWD:SETENV: /usr/hdp/*/ranger-usersync/setup.sh, /usr/
bin/ranger-usersync-stop, /usr/bin/ranger-usersync-start, /usr/hdp/*/ranger-
admin/setup.sh *, /usr/hdp/*/ranger-knox-plugin/disable-knox-plugin.sh *, /
usr/hdp/*/ranger-storm-plugin/disable-storm-plugin.sh *, /usr/hdp/*/ranger-
```

```
hbase-plugin/disable-hbase-plugin.sh *, /usr/hdp/*/ranger-hdfs-plugin/disable-hdfs-plugin.sh *, /usr/hdp/current/ranger-admin/ranger_credential_helper.py, /usr/hdp/current/ranger-kms/ranger_credential_helper.py, /usr/hdp/*/ranger-*/*/ranger_credential_helper.py
```



### Important

Do not modify the command lists, only the usernames in the [Customizable Users](#) section may be modified.

To re-iterate, you must do this sudo configuration on every node in the cluster. To ensure that the configuration has been done properly, you can su to the ambari user and run sudo -l. There, you can double check that there are no warnings, and that the configuration output matches what was just applied.

#### 2.4.1.2.5. Sudo Defaults

Some versions of sudo have a default configuration that prevents sudo from being invoked from a non-interactive shell. In order for the agent to run its commands non-interactively, some defaults need to be overridden.

```
Defaults exempt_group = ambari
Defaults !env_reset,env_delete-=PATH
Defaults: ambari !requiretty
```

To re-iterate, this sudo configuration must be done on every node in the cluster. To ensure that the configuration has been done properly, you can su to the ambari user and run sudo -l. There, you can double-check that there are no warnings, and that the configuration output matches what was just applied.

## 2.4.2. Optional: Ambari Web Inactivity Timeout

Ambari is capable of automatically logging a user out of Ambari Web after a period of inactivity. After a configurable amount of time, the user's session will be terminated and they will be redirected to the login page.

This capability can be separately configured for Operators and Read-Only users. This allows you to distinguish a read-only user (useful when Ambari Web is used as a monitoring dashboard) from other operators. Alternatively, you can set both inactivity timeout values to be the same so that regardless of the user type, automatic logout will occur after a set period of time.

By default, the Ambari Web inactivity timeout is not enabled (i.e. is set to 0). The following instructions should be used to enable inactivity timeout and set as the amount of time in seconds before users are automatically logged out.

Ensure the Ambari Server is completely stopped before making changes to the inactivity timeout. Either make these changes before you start Ambari Server the first time, or bring the server down before making these changes.

1. On the Ambari Server host, open

`/etc/ambari-server/conf/ambari.properties` with a text editor.

2. There are two properties for the inactivity timeout setting. Both are initially set to 0 (which means this capability is disabled).

| Property                                      | Description                                                                    |
|-----------------------------------------------|--------------------------------------------------------------------------------|
| user.inactivity.timeout.default               | Sets the inactivity timeout (in seconds) for all users except Read-Only users. |
| user.inactivity.timeout.role.readonly.default | Sets the inactivity timeout (in seconds) for all Read-Only users.              |

3. Modify the values to enable the capability. The values are in seconds.
4. Save changes and restart Ambari Server.
5. After a user logs into Ambari Web, once a period of inactivity occurs, the user will be presented with an Automatic Logout dialog 60 seconds from logout. The user can click to remain logged in or if no activity occurs, Ambari Web will automatically log the user out and redirect the application to the login page.

### 2.4.3. Set Up Kerberos for Ambari Server

When a cluster is enabled for Kerberos, the component REST endpoints (such as the YARN ATS component) require [SPNEGO](#) authentication.

Depending on the Services in your cluster, Ambari Web needs access to these APIs. As well, views such as the [Tez View](#) need access to ATS. Therefore, the Ambari Server requires a Kerberos principal in order to authenticate via SPNEGO against these APIs. This section describes how to configure Ambari Server with a Kerberos principal and keytab to allow views to authenticate via SPNEGO against cluster components.

1. Create a principal in your KDC for the Ambari Server. For example, using kadmin:

```
addprinc -randkey ambari-server@EXAMPLE.COM
```

2. Generate a keytab for that principal.

```
xst -k ambari.server.keytab ambari-server@EXAMPLE.COM
```

3. Place that keytab on the Ambari Server host. Be sure to set the file permissions so the user running the Ambari Server daemon can access the keytab file.

```
/etc/security/keytabs/ambari.server.keytab
```

4. Stop the ambari server.

```
ambari-server stop
```

5. Run the setup-security command.

```
ambari-server setup-security
```

6. Select 3 for Setup Ambari kerberos JAAS configuration.

7. Enter the Kerberos principal name for the Ambari Server you set up earlier.

8. Enter the path to the keytab for the Ambari principal.

9. Restart Ambari Server.

```
ambari-server restart
```

## 2.4.4. Optional: Set Up Two-Way SSL Between Ambari Server and Ambari Agents

Two-way SSL provides a way to encrypt communication between Ambari Server and Ambari Agents. By default Ambari ships with Two-way SSL disabled. To enable Two-way SSL:

Ambari Server should not be running when you do this: either make the edits before you start Ambari Server the first time or bring the server down to make the edits.

1. On the Ambari Server host, open /etc/ambari-server/conf/ambari.properties with a text editor.
2. Add the following property:

```
security.server.two_way_ssl = true
```

3. Start or restart the Ambari Server.

```
ambari-server restart
```

The Agent certificates are downloaded automatically during Agent Registration.

## 2.4.5. Optional: Configure Ciphers and Protocols for Ambari Server

Ambari provides control of ciphers and protocols that are exposed via Ambari Server.

1. To disable specific ciphers, you can optionally add a list of the following format to ambari.properties. If you specify multiple ciphers, separate each cipher using a vertical bar |.

```
security.server.disabled.ciphers=TLS_ECDHE_RSA_WITH_3DES_EDE_CBC_SHA
```

2. To disable specific protocols, you can optionally add a list of the following format to ambari.properties. If you specify multiple protocols, separate each protocol using a vertical bar |.

```
security.server.disabled.protocols=SSL|SSLv2|SSLv3
```

## 2.4.6. Optional: HTTP Cookie Persistence

During HTTP authentication, a cookie is dropped. This is a persistent cookie that is valid across browser sessions. For clusters that require enhanced security, it is desirable to have a session cookie that gets deleted when the user closes the browser session.

In HDP-2.3.4 and higher versions, you can use the following property in the etc/hadoop/conf/core-site.xml file to specify cookie persistence across browser sessions.

```
<property>
 <name>hadoop.http.authentication.cookie.persistent</name>
 <value>true</value>
</property>
```

The default value for this property is `false`.

## 2.5. Enabling SPNEGO Authentication for Hadoop

By default, access to the HTTP-based services and UIs for the cluster are not configured to require authentication. Kerberos authentication can be configured for the Web UIs for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon, and Storm. SPNEGO authentication for HBase Web UIs is only available in HDP 2.5 and later.

- [Configure Ambari Server for Authenticated HTTP \[48\]](#)
- [Configuring HTTP Authentication for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon and Storm \[48\]](#)

### 2.5.1. Configure Ambari Server for Authenticated HTTP

In order for Ambari to work with a cluster in which authenticated HTTP access to the Web UI's is required, you must configure the Ambari Server for Kerberos. Refer to [Set Up Kerberos for Ambari Server](#) for more information.

### 2.5.2. Configuring HTTP Authentication for HDFS, YARN, MapReduce2, HBase, Oozie, Falcon and Storm

1. Create a secret key used for signing authentication tokens. This file should contain random data and be placed on every host in the cluster. It should also be owned by the `hdfs` user and group owned by the `hadoop` group. Permissions should be set to 440. For example:

```
dd if=/dev/urandom of=/etc/security/http_secret bs=1024 count=1
chown hdfs:hadoop /etc/security/http_secret
chmod 440 /etc/security/http_secret
```

2. In Ambari Web, browse to **Services > HDFS > Configs** .
3. Add or modify the following configuration properties to Advanced core-site .

Property	New Value
<code>hadoop.http.authentication.simple.anonymous.allowed</code>	<code>false</code>
<code>hadoop.http.authentication.signature.secret.file</code>	<code>/etc/security/http_secret</code>
<code>hadoop.http.authentication.type</code>	<code>kerberos</code>
<code>hadoop.http.authentication.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>
<code>hadoop.http.authentication.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>
<code>hadoop.http.filter.initializers</code>	<code>org.apache.hadoop.security.AuthenticationFilterInitializer</code>
<code>hadoop.http.authentication.cookie.domain</code>	<code>hortonworks.local</code>



#### Important

The entries listed in the above table in **bold** and italicized are site-specific. The `hadoop.http.authentication.cookie.domain` property is based off

of the fully qualified domain names of the servers in the cluster. For example if the FQDN of your NameNode is host1.hortonworks.local, the hadoop.http.authentication.cookie.domain should be set to hortonworks.local.

4. For sites using **HBase**: Add or modify the following configuration properties in the `hbase-site.xml` file.

Property	New Value
<code>hbase.security.authentication.ui</code>	kerberos
<code>hbase.security.authentication.signature.secret.file</code>	<code>/etc/security/http_secret</code>
<code>hbase.security.authentication.spnego.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>
<code>hbase.security.authentication.spnego.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>

5. Save the configuration, then restart the affected services.

## 2.6. Setting Up Kerberos Authentication for Non-Ambari Clusters

This section provides information for enabling security for a manually installed version of HDP.

- [Preparing Kerberos \[49\]](#)
- [Configuring HDP for Kerberos \[55\]](#)
- [Configuring HBase and ZooKeeper \[73\]](#)
- [Configuring Hue \[80\]](#)
- [Setting up One-Way Trust with Active Directory \[82\]](#)
- [Configuring Proxy Users \[84\]](#)

### 2.6.1. Preparing Kerberos

This subsection provides information on setting up Kerberos for an HDP installation.

#### 2.6.1.1. Kerberos Overview

To create secure communication among its various components, HDP uses Kerberos. Kerberos is a third-party authentication mechanism, in which users and services that users wish to access rely on the Kerberos server to authenticate each to the other. This mechanism also supports encrypting all traffic between the user and the service.

The Kerberos server itself is known as the *Key Distribution Center*, or KDC. At a high level, it has three parts:

- A database of users and services (known as *principals*) and their respective Kerberos passwords
- An *authentication server* (AS) which performs the initial authentication and issues a *Ticket Granting Ticket* (TGT)

- A *Ticket Granting Server* (TGS) that issues subsequent service tickets based on the initial TGT.

A user principal requests authentication from the AS. The AS returns a TGT that is encrypted using the user principal's Kerberos password, which is known only to the user principal and the AS. The user principal decrypts the TGT locally using its Kerberos password, and from that point forward, until the ticket expires, the user principal can use the TGT to get service tickets from the TGS.

Because a service principal cannot provide a password each time to decrypt the TGT, it uses a special file, called a *keytab*, which contains its authentication credentials.

The service tickets allow the principal to access various services. The set of hosts, users, and services over which the Kerberos server has control is called a *realm*.



### Note

Because Kerberos is a time-sensitive protocol, all hosts in the realm must be time-synchronized, for example, by using the Network Time Protocol (NTP). If the local system time of a client differs from that of the KDC by as little as 5 minutes (the default), the client will not be able to authenticate.

## 2.6.1.2. Installing and Configuring the KDC

To use Kerberos with HDP, either use an existing KDC or install a new one for HDP only. The following gives a very high level description of the installation process. For more information, see [RHEL documentation](#), [CentOS documentation](#), [SLES documentation](#), or [Ubuntu and Debian documentation](#).

### 1. Install the KDC server:

- On RHEL, CentOS, or Oracle Linux, run:

```
yum install krb5-server krb5-libs krb5-auth-dialog krb5-workstation
```

- On SLES, run:

```
zypper install krb5 krb5-server krb5-client
```

- On Ubuntu or Debian, run:

```
apt-get install krb5 krb5-server krb5-client
```



### Note

The host on which you install the KDC must itself be secure.

### 2. When the server is installed you must edit the two main configuration files.

Update the KDC configuration by replacing EXAMPLE.COM with your domain and kerberos.example.com with the FQDN of the KDC host. Configuration files are in the following locations:

- On RHEL, CentOS, or Oracle Linux:

```
/etc/krb5.conf
```

```
/var/kerberos/krb5kdc/kdc.conf
```

- On SLES:

```
/etc/krb5.conf
/var/lib/kerberos/krb5kdc/kdc.conf
```

- On Ubuntu or Debian:

```
/etc/krb5.conf
/var/kerberos/krb5kdc/kdc.conf
```

3. Copy the updated krb5.conf to every cluster node.

### 2.6.1.3. Creating the Database and Setting Up the First Administrator

1. Use the utility kdb5\_util to create the Kerberos database:

- On RHEL, CentOS, or Oracle Linux:

```
/usr/sbin/kdb5_util create -s
```

- On SLES:

```
kdb5_util create -s
```

- On Ubuntu or Debian:

```
kdb5_util -s create
```



#### Note

The -s option stores the master server key for the database in a stash file. If the stash file is not present, you must log into the KDC with the master password (specified during installation) each time it starts. This will automatically regenerate the master server key.

2. Set up the KDC Access Control List (ACL):

- On RHEL, CentOS, or Oracle Linux add administrators to /var/kerberos/krb5kdc/kadm5.acl.
- On SLES, add administrators to /var/lib/kerberos/krb5kdc/kadm5.acl .



#### Note

For example, the following line grants full access to the database for users with the admin extension: \* /admin@EXAMPLE.COM \*

3. Start kadmin for the change to take effect.

4. Create the first user principal. This must be done at a terminal window on the KDC machine itself, while you are logged in as root. Notice the .local. Normal kadmin usage requires that a principal with appropriate access already exist. The kadmin.local command can be used even if no principals exist:

```
/usr/sbin/kadmin.local -q "addprinc $username/admin
```

Now this user can create additional principals either on the KDC machine or through the network. The following instruction assumes that you are using the KDC machine.

5. On the KDC, start Kerberos:

- On RHEL, CentOS, or Oracle Linux:

```
/sbin/service krb5kdc start
/sbin/service kadmin start
```

- On SLES:

```
rckrb5kdc start
rckadmind start
```

- On Ubuntu or Debian:

```
/etc/init.d/krb5-kdc start
/etc/init.d/kadmin start
```

#### 2.6.1.4. Creating Service Principals and Keytab Files for HDP

Each service in HDP must have its own principal. Because services do not login with a password to acquire their tickets, their principal's authentication credentials are stored in a keytab file, which is extracted from the Kerberos database and stored locally with the service principal.

First create the principal, using mandatory naming conventions. Then create the keytab file with that principal's information, and copy the file to the keytab directory on the appropriate service host.

1. To create a service principal you will use the kadmin utility. This is a command-line driven utility into which you enter Kerberos commands to manipulate the central database. To start kadmin, enter:

```
'kadmin $USER/admin@REALM'
```

To create a service principal, enter the following:

```
kadmin: addprinc -randkey $principal_name/$service-host-FQDN@$hadoop.realm
```

You must have a principal with administrative permissions to use this command. The randkey is used to generate the password.

The \$principal\_name part of the name must match the values in the following table.

In the example each service principal's name has appended to it the fully qualified domain name of the host on which it is running. This is to provide a unique principal name for services that run on multiple hosts, like DataNodes and TaskTrackers. The addition of the hostname serves to distinguish, for example, a request from DataNode A from a request from DataNode B.

This is important for two reasons:

- a. If the Kerberos credentials for one DataNode are compromised, it does not automatically lead to all DataNodes being compromised

- b. If multiple DataNodes have exactly the same principal and are simultaneously connecting to the NameNode, and if the Kerberos authenticator being sent happens to have same timestamp, then the authentication would be rejected as a replay request.

Note: The NameNode, Secondary NameNode, and Oozie require two principals each.

If you are configuring High Availability (HA) for a Quorum-based NameNode, you must also generate a principle (jn/\$FQDN) and keytab (jn.service.keytab) for each JournalNode. JournalNode also requires the keytab for its HTTP service. If the JournalNode is deployed on the same host as a NameNode, the same keytab file (spnego.service.keytab) can be used for both. In addition, HA requires two NameNodes. Both the active and standby NameNodes require their own principle and keytab files. The service principles of the two NameNodes can share the same name, specified with the dfs.namenode.kerberos.principal property in hdfs-site.xml, but the NameNodes still have different fully qualified domain names.

**Table 2.7. Service Principals**

Service	Component	Mandatory Principal Name
HDFS	NameNode	nn/\$FQDN
HDFS	NameNode HTTP	HTTP/\$FQDN
HDFS	SecondaryNameNode	nn/\$FQDN
HDFS	SecondaryNameNode HTTP	HTTP/\$FQDN
HDFS	DataNode	dn/\$FQDN
MR2	History Server	jhs/\$FQDN
MR2	History Server HTTP	HTTP/\$FQDN
YARN	ResourceManager	rm/\$FQDN
YARN	NodeManager	nm/\$FQDN
Oozie	Oozie Server	oozie/\$FQDN
Oozie	Oozie HTTP	HTTP/\$FQDN
Hive	Hive Metastore	hive/\$FQDN
Hive	HiveServer2	
Hive	WebHCat	HTTP/\$FQDN
HBase	MasterServer	hbase/\$FQDN
HBase	RegionServer	hbase/\$FQDN
Storm	Nimbus server	nimbus/\$FQDN **
Storm	DRPC daemon	
Storm	Storm UI daemon	storm/\$FQDN **
Storm	Storm Logviewer daemon	
Storm	Nodes running process controller (such as Supervisor)	
Kafka	KafkaServer	kafka/\$FQDN
Hue	Hue Interface	hue/\$FQDN
ZooKeeper	ZooKeeper	zookeeper/\$FQDN
JournalNode Server*	JournalNode	jn/\$FQDN
Gateway	Knox	knox/\$FQDN

\* Only required if you are setting up NameNode HA.

\*\* For more information, see [Configure Kerberos Authentication for Storm](#).

For example: To create the principal for a DataNode service, issue this command:

```
kadmin: addprinc -randkey dn/$datanode-host@$hadoop.realm
```

2. Extract the related keytab file and place it in the keytab directory of the appropriate respective components. The default directory is /etc/krb5.keytab.

```
kadmin: xst -k $keytab_file_name $principal_name/fully.qualified.domain.name
```

You must use the mandatory names for the \$keytab\_file\_name variable shown in the following table.

**Table 2.8. Service Keytab File Names**

Component	Principal Name	Mandatory Keytab File Name
NameNode	nn/\$FQDN	nn.service.keytab
NameNode HTTP	HTTP/\$FQDN	spnego.service.keytab
SecondaryNameNode	nn/\$FQDN	nn.service.keytab
SecondaryNameNode HTTP	HTTP/\$FQDN	spnego.service.keytab
DataNode	dn/\$FQDN	dn.service.keytab
MR2 History Server	jhs/\$FQDN	nm.service.keytab
MR2 History Server HTTP	HTTP/\$FQDN	spnego.service.keytab
YARN	rm/\$FQDN	rm.service.keytab
YARN	nm/\$FQDN	nm.service.keytab
Oozie Server	oozie/\$FQDN	oozie.service.keytab
Oozie HTTP	HTTP/\$FQDN	spnego.service.keytab
Hive Metastore	hive/\$FQDN	hive.service.keytab
HiveServer2		
WebHCat	HTTP/\$FQDN	spnego.service.keytab
HBase Master Server	hbase/\$FQDN	hbase.service.keytab
HBase RegionServer	hbase/\$FQDN	hbase.service.keytab
Storm	storm/\$FQDN	storm.service.keytab
Kafka	kafka/\$FQDN	kafka.service.keytab
Hue	hue/\$FQDN	hue.service.keytab
ZooKeeper	zookeeper/\$FQDN	zk.service.keytab
Journal Server*	jn/\$FQDN	jn.service.keytab
Knox Gateway**	knox/\$FQDN	knox.service.keytab

\* Only required if you are setting up NameNode HA.

\*\* Only required if you are using a Knox Gateway.

For example: To create the keytab files for the NameNode, issue these commands:

```
kadmin: xst -k nn.service.keytab nn/$namenode-host kadmin: xst -k spnego.
service.keytab HTTP/$namenode-host
```

When you have created the keytab files, copy them to the keytab directory of the respective service hosts.

3. Verify that the correct keytab files and principals are associated with the correct service using the `klist` command. For example, on the NameNode:

```
klist -k -t /etc/security/nn.service.keytab
```

Do this on each respective service in your cluster.

## 2.6.2. Configuring HDP for Kerberos

Configuring HDP for Kerberos has two parts:

- Creating a mapping between service principals and UNIX usernames.

Hadoop uses group memberships of users at various places, such as to determine group ownership for files or for access control.

A user is mapped to the groups it belongs to using an implementation of the `GroupMappingServiceProvider` interface. The implementation is pluggable and is configured in `core-site.xml`.

By default Hadoop uses `ShellBasedUnixGroupsMapping`, which is an implementation of `GroupMappingServiceProvider`. It fetches the group membership for a username by executing a UNIX shell command. In secure clusters, since the usernames are actually Kerberos principals, `ShellBasedUnixGroupsMapping` will work only if the Kerberos principals map to valid UNIX usernames. Hadoop provides a feature that lets administrators specify mapping rules to map a Kerberos principal to a local UNIX username.

- Adding information to three main service configuration files.

There are several optional entries in the three main service configuration files that must be added to enable security on HDP.

This section provides information on configuring HDP for Kerberos.

- [Creating Mappings Between Principals and UNIX Usernames \[56\]](#)
- [Adding Security Information to Configuration Files \[57\]](#)
- [Configuring HBase and ZooKeeper \[73\]](#)
- [Configuring Hue \[80\]](#)



### Note

You must adhere to the existing upper and lower case naming conventions in the configuration file templates.

## 2.6.2.1. Creating Mappings Between Principals and UNIX Usernames

HDP uses a rule-based system to create mappings between service principals and their related UNIX usernames. The rules are specified in the `core-site.xml` configuration file as the value to the optional key `hadoop.security.auth_to_local`.

The default rule is simply named `DEFAULT`. It translates all principals in your default domain to their first component. For example, `myusername@APACHE.ORG` and `myusername/admin@APACHE.ORG` both become `myusername`, assuming your default domain is `APACHE.ORG`.

While mapping the Kerberos principals, if the Kerberos principal names are in the `UPPERCASE` or `CaMeLcase`, the names will not be recognized on the Linux machine (as Linux users are always in lower case). You must add the extra switch `"/L"` in the rule definition to force the conversion to lower case.

### Creating Rules

To accommodate more complex translations, you can create a hierarchical set of rules to add to the default. Each rule is divided into three parts: base, filter, and substitution.

- **The Base**

The base begins with the number of components in the principal name (excluding the realm), followed by a colon, and the pattern for building the username from the sections of the principal name. In the pattern section `$0` translates to the realm, `$1` translates to the first component, and `$2` to the second component.

For example:

```
[1:$1@$0] translates myusername@APACHE.ORG to myusername@APACHE.ORG
[2:$1] translates myusername/admin@APACHE.ORG to myusername
[2:$1%$2] translates myusername/admin@APACHE.ORG to "myusername%admin"
```

- **The Filter**

The filter consists of a regular expression (regex) in a parentheses. It must match the generated string for the rule to apply.

For example:

```
(.*%admin) matches any string that ends in %admin
(.*@SOME.DOMAIN) matches any string that ends in @SOME.DOMAIN
```

- **The Substitution**

The substitution is a sed rule that translates a regex into a fixed string. For example:

```
s/@ACME\.COM// removes the first instance of @ACME.DOMAIN
s/@[A-Z]*\.COM// remove the first instance of @ followed by a name followed
by COM.
s/X/Y/g replace all of X's in the name with Y
```

### 2.6.2.1.1. Examples

- If your default realm was APACHE.ORG, but you also wanted to take all principals from ACME.COM that had a single component joe@ACME.COM, the following rule would do this:

```
RULE:[1:$1@$0](. @ACME.COM)s/@.//
DEFAULT
```

- To translate names with a second component, you could use these rules:

```
RULE:[1:$1@$0](. @ACME.COM)s/@.//
RULE:[2:$1@$0](. @ACME.COM)s/@.// DEFAULT
```

- To treat all principals from APACHE.ORG with the extension /admin as admin, your rules would look like this:

```
RULE[2:$1%$2@$0](.%admin@APACHE.ORG)s/. /admin/
DEFAULT
```

- To force username conversion from CaMeLcase or UPPERCASE to lowercase, you could model the following auth\_to\_local rule examples which have the lowercase switch added:

```
RULE:[1:$1]/L
RULE:[2:$1]/L
RULE:[2:$1;$2](^.*;admin$)s;/admin$/i/L
RULE:[2:$1;$2](^.*;guest$)s;/guest$/i/g/L
```

And based on these rules, here are the expected output for the following inputs:

```
"JOE@FOO.COM" to "joe"
"Joe/root@FOO.COM" to "joe"
"Joe/admin@FOO.COM" to "joe"
"Joe/guestguest@FOO.COM" to "joe"
```

### 2.6.2.2. Adding Security Information to Configuration Files

To enable security on HDP, you must add optional information to various configuration files.

Before you begin, set JSVC\_Home in hadoop-env.sh.

- For RHEL/CentOS/Oracle Linux:

```
export JSVC_HOME=/usr/libexec/bigtop-utils
```

- For SLES and Ubuntu:

```
export JSVC_HOME=/usr/hdp/current/bigtop-utils
```

#### 2.6.2.2.1. core-site.xml

Add the following information to the core-site.xml file on every host in your cluster:

**Table 2.9. General core-site.xml, Knox, and Hue**

Property Name	Property Value	Description
hadoop.security.authentication	kerberos	Set the authentication type for the cluster. Valid values are: simple or kerberos.
hadoop.rpc.protection	authentication; integrity; privacy	This is an [OPTIONAL] setting. If not set, defaults to authentication.  authentication = authentication only; the client and server mutually authenticate during connection setup.  integrity = authentication and integrity; guarantees the integrity of data exchanged between client and server as well as authentication.  privacy = authentication, integrity, and confidentiality; guarantees that data exchanged between client and server is encrypted and is not readable by a "man in the middle".
hadoop.security.authorization	true	Enable authorization for different protocols.
hadoop.security.auth_to_local	The mapping rules. For example:  RULE: [2:\$1@\$0] ([jt]t@.*EXAMPLE.COM)s/.*/mapred/ RULE: [2:\$1@\$0] ([nd]n@.*EXAMPLE.COM)s/.*/hdfs/ RULE: [2:\$1@\$0] (hm@.*EXAMPLE.COM)s/.*/hbase/ RULE: [2:\$1@\$0] (rs@.*EXAMPLE.COM)s/.*/hbase/ DEFAULT	The mapping from Kerberos principal names to local OS user names. See <a href="#">Creating Mappings Between Principals and UNIX Usernames</a> for more information.

Following is the XML for these entries:

```

<property>
 <name>hadoop.security.authentication</name>
 <value>kerberos</value>
 <description> Set the authentication for the cluster.
 Valid values are: simple or kerberos.</description>
</property>

<property>
 <name>hadoop.security.authorization</name>
 <value>true</value>
 <description>Enable authorization for different protocols.</description>
</property>

<property>
 <name>hadoop.security.auth_to_local</name>
 <value>
 RULE: [2:$1@$0]([jt]t@.*EXAMPLE.COM)s/.*/mapred/
 RULE: [2:$1@$0]([nd]n@.*EXAMPLE.COM)s/.*/hdfs/
 RULE: [2:$1@$0](hm@.*EXAMPLE.COM)s/.*/hbase/
 RULE: [2:$1@$0](rs@.*EXAMPLE.COM)s/.*/hbase/
 DEFAULT
 </value>
 <description>The mapping from kerberos principal names
 to local OS user names.</description>
</property>

```

```
</property>
```

When using the Knox Gateway, add the following to the `core-site.xml` file on the master nodes host in your cluster:

**Table 2.10. core-site.xml Master Node Settings – Knox Gateway**

Property Name	Property Value	Description
<code>hadoop.proxyuser.knox.groups</code>	<code>users</code>	Grants proxy privileges for Knox user.
<code>hadoop.proxyuser.knox.hosts</code>	<code>\$knox_host_FQDN</code>	Identifies the Knox Gateway host.

When using Hue, add the following to the `core-site.xml` file on the master nodes host in your cluster:

**Table 2.11. core-site.xml Master Node Settings – Hue**

Property Name	Property Value	Description
<code>hue.kerberos.principal.shortname</code>	<code>hue</code>	Group to which all the Hue users belong. Use the wild card character to select multiple groups, for example <code>cli*</code> .
<code>hadoop.proxyuser.hue.groups</code>	<code>*</code>	Group to which all the Hue users belong. Use the wild card character to select multiple groups, for example <code>cli*</code> .
<code>hadoop.proxyuser.hue.hosts</code>	<code>*</code>	
<code>hadoop.proxyuser.knox.hosts</code>	<code>\$hue_host_FQDN</code>	Identifies the Knox Gateway host.

Following is the XML for both Knox and Hue settings:

```
<property>
 <name>hadoop.security.authentication</name>
 <value>kerberos</value>
 <description>Set the authentication for the cluster.
 Valid values are: simple or kerberos.</description>
</property>

<property>
 <name>hadoop.security.authorization</name>
 <value>true</value>
 <description>Enable authorization for different protocols.
 </description>
</property>

<property>
 <name>hadoop.security.auth_to_local</name>
 <value>
 RULE:[2:$1@$0]([jt]t@.*EXAMPLE.COM)s/.*/mapred/
 RULE:[2:$1@$0]([nd]n@.*EXAMPLE.COM)s/.*/hdfs/
 RULE:[2:$1@$0](hm@.*EXAMPLE.COM)s/.*/hbase/
 RULE:[2:$1@$0](rs@.*EXAMPLE.COM)s/.*/hbase/
 DEFAULT
 </value>
 <description>The mapping from kerberos principal names
 to local OS user names.</description>
</property>

<property>
 <name>hadoop.proxyuser.knox.groups</name>
 <value>users</value>
</property>
```

```
<property>
 <name>hadoop.proxyuser.knox.hosts</name>
 <value>Knox.EXAMPLE.COM</value>
</property>
```

#### 2.6.2.2.1.1. HTTP Cookie Persistence

During HTTP authentication, a cookie is dropped. This is a persistent cookie that is valid across browser sessions. For clusters that require enhanced security, it is desirable to have a session cookie that gets deleted when the user closes the browser session.

You can use the following `core-site.xml` property to specify cookie persistence across browser sessions.

```
<property>
 <name>hadoop.http.authentication.cookie.persistent</name>
 <value>true</value>
</property>
```

The default value for this property is `false`.

#### 2.6.2.2.2. hdfs-site.xml

To the `hdfs-site.xml` file on every host in your cluster, you must add the following information:

**Table 2.12. hdfs-site.xml File Property Settings**

Property Name	Property Value	Description
<code>dfs.permissions.enabled</code>	<code>true</code>	If true, permission checking in HDFS is enabled. If false, permission checking is turned off, but all other behavior is unchanged. Switching from one parameter value to the other does not change the mode, owner or group of files or directories.
<code>dfs.permissions.supergroup</code>	<code>hdfs</code>	The name of the group of super-users.
<code>dfs.block.access.token.enable</code>	<code>true</code>	If true, access tokens are used as capabilities for accessing DataNodes. If false, no access tokens are checked on accessing DataNodes.
<code>dfs.namenode.kerberos.principal</code>	<code>nn/_HOST@EXAMPLE.COM</code>	Kerberos principal name for the NameNode.
<code>dfs.secondary.namenode.kerberos.principal</code>	<code>nn/_HOST@EXAMPLE.COM</code>	Kerberos principal name for the secondary NameNode.
<code>dfs.web.authentication.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>	The HTTP Kerberos principal used by Hadoop-Auth in the HTTP endpoint.  The HTTP Kerberos principal MUST start with 'HTTP/' per Kerberos HTTP SPNEGO specification.
<code>dfs.web.authentication.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>	The Kerberos keytab file with the credentials for the HTTP Kerberos principal used by Hadoop-Auth in the HTTP endpoint.
<code>dfs.datanode.kerberos.principal</code>	<code>dn/_HOST@EXAMPLE.COM</code>	The Kerberos principal that the DataNode runs as. "_HOST" is replaced by the real host name.

Property Name	Property Value	Description
dfs.namenode.keytab.file	/etc/security/keytabs/ nn.service.keytab	Combined keytab file containing the NameNode service and host principals.
dfs.secondary.namenode.keytab.file	/etc/security/keytabs/ nn.service.keytab	Combined keytab file containing the NameNode service and host principals. <question?>
dfs.datanode.keytab.file	/etc/security/keytabs/ dn.service.keytab	The filename of the keytab file for the DataNode.
dfs.https.port	50470	The HTTPS port to which the NameNode binds.
dfs.namenode.https-address	Example:  ip-10-111-59-170.ec2.internal:50470	The HTTPS address to which the NameNode binds.
dfs.datanode.data.dir.perm	750	The permissions that must be set on the dfs.data.dir directories. The DataNode will not come up if all existing dfs.data.dir directories do not have this setting. If the directories do not exist, they will be created with this permission.
dfs.cluster.administrators	hdfs	ACL for who all can view the default servlets in the HDFS.
dfs.namenode.kerberos.internal.spnego.principal	\${dfs.web.authentication.kerberos.principal}	
dfs.secondary.namenode.kerberos.internal.spnego.principal	\${dfs.web.authentication.kerberos.principal}	

Following is the XML for these entries:

```

<property>
 <name>dfs.permissions</name>
 <value>true</value>
 <description> If "true", enable permission checking in
 HDFS. If "false", permission checking is turned
 off, but all other behavior is
 unchanged. Switching from one parameter value to the other does
 not change the mode, owner or group of files or
 directories. </description>
</property>

<property>
 <name>dfs.permissions.supergroup</name>
 <value>hdfs</value>
 <description>The name of the group of
 super-users.</description>
</property>

<property>
 <name>dfs.namenode.handler.count</name>
 <value>100</value>
 <description>Added to grow Queue size so that more
 client connections are allowed</description>
</property>

<property>
 <name>ipc.server.max.response.size</name>
 <value>5242880</value>
</property>

```

```
<property>
 <name>dfs.block.access.token.enable</name>
 <value>true</value>
 <description> If "true", access tokens are used as capabilities
for accessing datanodes. If "false", no access tokens are checked on
accessing datanodes. </description>
</property>

<property>
 <name>dfs.namenode.kerberos.principal</name>
 <value>nn/_HOST@EXAMPLE.COM</value>
 <description> Kerberos principal name for the
NameNode </description>
</property>

<property>
 <name>dfs.secondary.namenode.kerberos.principal</name>
 <value>nn/_HOST@EXAMPLE.COM</value>
 <description>Kerberos principal name for the secondary NameNode.
 </description>
</property>

<property>
 <!--cluster variant -->
 <name>dfs.secondary.http.address</name>
 <value>ip-10-72-235-178.ec2.internal:50090</value>
 <description>Address of secondary namenode web server</description>
</property>

<property>
 <name>dfs.secondary.https.port</name>
 <value>50490</value>
 <description>The https port where secondary-namenode
binds</description>
</property>

<property>
 <name>dfs.web.authentication.kerberos.principal</name>
 <value>HTTP/_HOST@EXAMPLE.COM</value>
 <description> The HTTP Kerberos principal used by Hadoop-Auth in the HTTP
endpoint.
 The HTTP Kerberos principal MUST start with 'HTTP/' per Kerberos HTTP
SPNEGO specification.
 </description>
</property>

<property>
 <name>dfs.web.authentication.kerberos.keytab</name>
 <value>/etc/security/keytabs/spnego.service.keytab</value>
 <description>The Kerberos keytab file with the credentials for the HTTP
Kerberos principal used by Hadoop-Auth in the HTTP endpoint.
 </description>
</property>

<property>
 <name>dfs.datanode.kerberos.principal</name>
 <value>dn/_HOST@EXAMPLE.COM</value>
 <description>
 The Kerberos principal that the DataNode runs as. "_HOST" is replaced by
the real
 </description>
</property>
```

```
 host name.
 </description>
</property>

<property>
 <name>dfs.namenode.keytab.file</name>
 <value>/etc/security/keytabs/nn.service.keytab</value>
 <description>
 Combined keytab file containing the namenode service and host
 principals.
 </description>
</property>

<property>
 <name>dfs.secondary.namenode.keytab.file</name>
 <value>/etc/security/keytabs/nn.service.keytab</value>
 <description>
 Combined keytab file containing the namenode service and host
 principals.
 </description>
</property>

<property>
 <name>dfs.datanode.keytab.file</name>
 <value>/etc/security/keytabs/dn.service.keytab</value>
 <description>
 The filename of the keytab file for the DataNode.
 </description>
</property>

<property>
 <name>dfs.https.port</name>
 <value>50470</value>
 <description>The https port where namenode
 binds</description>
</property>

<property>
 <name>dfs.https.address</name>
 <value>ip-10-111-59-170.ec2.internal:50470</value>
 <description>The https address where namenode binds</description>
</property>

<property>
 <name>dfs.datanode.data.dir.perm</name>
 <value>750</value>
 <description>The permissions that should be there on
 dfs.data.dir directories. The datanode will not come up if the
 permissions are different on existing dfs.data.dir directories. If
 the directories don't exist, they will be created with this
 permission.</description>
</property>

<property>
 <name>dfs.access.time.precision</name>
 <value>0</value>
 <description>The access time for HDFS file is precise upto this
 value. The default value is 1 hour. Setting a value of 0
 disables access times for HDFS.
 </description>
```

```

</property>

<property>
 <name>dfs.cluster.administrators</name>
 <value> hdfs</value>
 <description>ACL for who all can view the default
 servlets in the HDFS</description>
</property>

<property>
 <name>ipc.server.read.threadpool.size</name>
 <value>5</value>
 <description></description>
</property>

<property>
 <name>dfs.namenode.kerberos.internal.spnego.principal</name>
 <value>${dfs.web.authentication.kerberos.principal}</value>
</property>

<property>
 <name>dfs.secondary.namenode.kerberos.internal.spnego.principal</name>
 <value>${dfs.web.authentication.kerberos.principal}</value>
</property>

```

In addition, you must set the user on all secure DataNodes:

```

export HADOOP_SECURE_DN_USER=hdfs
export HADOOP_SECURE_DN_PID_DIR=/grid/0/var/run/hadoop/$HADOOP_SECURE_DN_USER

```

### 2.6.2.2.3. yarn-site.xml

You must add the following information to the `yarn-site.xml` file on every host in your cluster:

**Table 2.13. `yarn-site.xml` Property Settings**

Property	Value	Description
yarn.resourcemanager.principal	yarn/localhost@EXAMPLE.COM	The Kerberos principal for the ResourceManager.
yarn.resourcemanager.keytab	/etc/krb5.keytab	The keytab for the ResourceManager.
yarn.nodemanager.principal	yarn/localhost@EXAMPLE.COM	The Kerberos principal for the NodeManager.
yarn.nodemanager.keytab	/etc/krb5.keytab	The keytab for the NodeManager.
yarn.nodemanager.container-executor.class	org.apache.hadoop.yarn.server.nodemanager.LinuxContainerExecutor	The class that will execute (launch) the containers.
yarn.nodemanager.linux-container-executor.path	hadoop-3.0.0-SNAPSHOT/bin/container-executor	The path to the Linux container executor.
yarn.nodemanager.linux-container-executor.group	hadoop	A special group (e.g., hadoop) with executable permissions for the container executor, of which the NodeManager UNIX user is the group member and no ordinary application user is. If any application user belongs to this special group, security will be compromised. This special group name should be specified for the configuration property.

Property	Value	Description
yarn.timeline-service.principal	yarn/localhost@EXAMPLE.COM	The Kerberos principal for the Timeline Server.
yarn.timeline-service.keytab	/etc/krb5.keytab	The Kerberos keytab for the Timeline Server.
yarn.resourcemanager.webapp.delegation-token-auth-filter.enabled	true	Flag to enable override of the default Kerberos authentication filter with the RM authentication filter to allow authentication using delegation tokens (fallback to Kerberos if the tokens are missing). Only applicable when the http authentication type is Kerberos.
yarn.timeline-service.http-authentication.type	kerberos	Defines authentication used for the Timeline Server HTTP endpoint. Supported values are: simple   kerberos   \$AUTHENTICATION_HANDLER_CLASSNAME
yarn.timeline-service.http-authentication.kerberos.principal	HTTP/localhost@EXAMPLE.COM	The Kerberos principal to be used for the Timeline Server HTTP endpoint.
yarn.timeline-service.http-authentication.kerberos.keytab	authentication.kerberos.keytab /etc/krb5.keytab	The Kerberos keytab to be used for the Timeline Server HTTP endpoint.

Following is the XML for these entries:

```

<property>
 <name>yarn.resourcemanager.principal</name>
 <value>yarn/localhost@EXAMPLE.COM</value>
</property>

<property>
 <name>yarn.resourcemanager.keytab</name>
 <value>/etc/krb5.keytab</value>
</property>

<property>
 <name>yarn.nodemanager.principal</name>
 <value>yarn/localhost@EXAMPLE.COM</value>
</property>

<property>
 <name>yarn.nodemanager.keytab</name>
 <value>/etc/krb5.keytab</value>
</property>

<property>
 <name>yarn.nodemanager.container-executor.class</name>
 <value>org.apache.hadoop.yarn.server.nodemanager.LinuxContainerExecutor</value>
</property>

<property>
 <name>yarn.nodemanager.linux-container-executor.path</name>
 <value>hadoop-3.0.0-SNAPSHOT/bin/container-executor</value>
</property>

<property>
 <name>yarn.nodemanager.linux-container-executor.group</name>
 <value>hadoop</value>
</property>
```

```

<property>
 <name>yarn.timeline-service.principal</name>
 <value>yarn/localhost@EXAMPLE.COM</value>
</property>

<property>
 <name>yarn.timeline-service.keytab</name>
 <value>/etc/krb5.keytab</value>
</property>

<property>
 <name>yarn.resourcemanager.webapp.delegation-token-auth-filter.enabled</name>
 <value>true</value>
</property>

<property>
 <name>yarn.timeline-service.http-authentication.type</name>
 <value>kerberos</value>
</property>

<property>
 <name>yarn.timeline-service.http-authentication.kerberos.principal</name>
 <value>HTTP/localhost@EXAMPLE.COM</value>
</property>

<property>
 <name>yarn.timeline-service.http-authentication.kerberos.keytab</name>
 <value>/etc/krb5.keytab</value>
</property>

```

#### 2.6.2.2.4. mapred-site.xml

You must add the following information to the `mapred-site.xml` file on every host in your cluster:

**Table 2.14. mapred-site.xml Property Settings**

Property Name	Property Value	Description
<code>mapreduce.jobhistory.keytab</code>	<code>/etc/security/keytabs/jhs.service.keytab</code>	Kerberos keytab file for the MapReduce JobHistory Server.
<code>mapreduce.jobhistory.principal</code>	<code>jhs/_HOST@TODO-KERBEROS-DOMAIN</code>	Kerberos principal name for the MapReduce JobHistory Server.
<code>mapreduce.jobhistory.webapp.address</code>	<code>TODO-JOBHISTORYNODE-HOSTNAME:19888</code>	MapReduce JobHistory Server Web UI host:port
<code>mapreduce.jobhistory.webapp.https-address</code>	<code>TODO-JOBHISTORYNODE-HOSTNAME:19889</code>	MapReduce JobHistory Server HTTPS Web UI host:port
<code>mapreduce.jobhistory.webapp.spnego-keytab-file</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>	Kerberos keytab file for the spnego service.
<code>mapreduce.jobhistory.webapp.spnego-principal</code>	<code>HTTP/_HOST@TODO-KERBEROS-DOMAIN</code>	Kerberos principal name for the spnego service.

Following is the XML for these entries:

```

<property>
 <name>mapreduce.jobhistory.keytab</name>
 <value>/etc/security/keytabs/jhs.service.keytab</value>
</property>

```

```

<property>
 <name>mapreduce.jobhistory.principal</name>
 <value>jhs/_HOST@TODO-KERBEROS-DOMAIN</value>
</property>

<property>
 <name>mapreduce.jobhistory.webapp.address</name>
 <value>TODO-JOBHISTORYNODE-HOSTNAME:19888</value>
</property>

<property>
 <name>mapreduce.jobhistory.webapp.https.address</name>
 <value>TODO-JOBHISTORYNODE-HOSTNAME:19889</value>
</property>

<property>
 <name>mapreduce.jobhistory.webapp.spnego-keytab-file</name>
 <value>/etc/security/keytabs/spnego.service.keytab</value>
</property>

<property>
 <name>mapreduce.jobhistory.webapp.spnego-principal</name>
 <value>HTTP/_HOST@TODO-KERBEROS-DOMAIN</value>
</property>

```

#### 2.6.2.2.5. hbase-site.xml

For HBase to run on a secured cluster, HBase must be able to authenticate itself to HDFS. Add the following information to the `hbase-site.xml` file on your HBase server. There are no default values; the following are only examples:

**Table 2.15. hbase-site.xml Property Settings for HBase Server**

Property Name	Property Value	Description
hbase.master.keytab.file	/etc/security/keytabs/ hm.service.keytab	The keytab for the HMaster service principal.
hbase.master.kerberos.principal	hm/_HOST@EXAMPLE.COM	The Kerberos principal name that should be used to run the HMaster process. If _HOST is used as the hostname portion, it will be replaced with the actual hostname of the running instance.
hbase.regionserver.keytab.file	/etc/security/keytabs/ hbase.service.keytab	The keytab for the HRegionServer service principal.
hbase.regionserver.kerberos.principal	hbase/_HOST@EXAMPLE.COM	The Kerberos principal name that should be used to run the HRegionServer process. If _HOST is used as the hostname portion, it will be replaced with the actual hostname of the running instance.
hbase.superuser	hbase	A comma-separated list of users or groups that are allowed full privileges, regardless of stored ACLs, across the cluster. Only used when HBase security is enabled.
hbase.coprocessor.region.classes	<i>Setting 1:org.apache.hadoop.hbase.security.token.TokenProvider,</i>	A comma-separated list of coprocessors that are loaded by default on all tables. For any implemented coprocessor methods, the listed classes will be

Property Name	Property Value	Description
	<i>Setting 2:</i> org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint <i>Setting 3:</i> org.apache.hadoop.hbase.security.access.AccessController	called in order. After implementing your own coprocessor, add the class to HBase's classpath and add the fully qualified class name here. Coprocessors can also be loaded programmatically using HTableDescriptor.
hbase.coprocessor.master.classes	org.apache.hadoop.hbase.security.access.AccessController	A comma-separated list of MasterObserver coprocessors that are loaded by the active HMaster process. For any implemented coprocessor methods, the listed classes will be called in order. After implementing your own MasterObserver, add the class to HBase's classpath and add the fully qualified class name here.
hbase.coprocessor.regionserver.classes	org.apache.hadoop.hbase.security.access.AccessController	A comma-separated list of RegionServerObserver coprocessors that are loaded by the HRegionServer processes. For any implemented coprocessor methods, the listed classes will be called in order. After implementing your own RegionServerObserver, add the class to the HBase classpath and fully qualified class name here.
phoenix.queryserver.kerberos.principal	hbase/_HOST@EXAMPLE.COM	The Kerberos principal for the Phoenix Query Server process. The Phoenix Query Server is an optional component; this property only needs to be set when the query server is installed.
phoenix.queryserver.keytab.file	/etc/security/keytabs/hbase.service.keytab	The path to the Kerberos keytab file for the Phoenix Query Server process. The Phoenix Query Server is an optional component; this property only needs to be set when the query server is installed.

Following is the XML for these entries:

```

<property>
 <name>hbase.master.keytab.file</name>
 <value>/etc/security/keytabs/hbase.service.keytab</value>
 <description>Full path to the kerberos keytab file to use for logging in the configured HMaster server principal.
 </description>
</property>

<property>
 <name>hbase.master.kerberos.principal</name>
 <value>hm/_HOST@EXAMPLE.COM</value>
 <description>Ex. "hbase/_HOST@EXAMPLE.COM". The Kerberos principal name that should be used to run the HMaster process. The principal name should be in the form: user/hostname@DOMAIN. If "_HOST" is used as the hostname portion, it will be replaced with the actual hostname of the running instance.
 </description>
</property>

<property>
```

```
<name>hbase.regionserver.keytab.file</name>
<value>/etc/security/keytabs/hbase.service.keytab</value>
<description>Full path to the kerberos keytab file to use for logging
in the configured HRegionServer server principal.
</description>
</property>

<property>
 <name>hbase.regionserver.kerberos.principal</name>
 <value>hbase/_HOST@EXAMPLE.COM</value>
 <description>Ex. "hbase/_HOST@EXAMPLE.COM".
The kerberos principal name that
should be used to run the HRegionServer process. The
principal name should be in the form:
user/hostname@DOMAIN. If _HOST
is used as the hostname portion, it will be replaced
with the actual hostname of the running
instance. An entry for this principal must exist
in the file specified in hbase.regionserver.keytab.file
</description>
</property>

<!--Additional configuration specific to HBase security -->

<property>
 <name>hbase.superuser</name>
 <value>hbase</value>
 <description>List of users or groups (comma-separated), who are
allowed full privileges, regardless of stored ACLs, across the cluster.
Only used when HBase security is enabled.
</description>
</property>

<property>
 <name>hbase.coprocessor.region.classes</name>
 <value>org.apache.hadoop.hbase.security.token.TokenProvider,
org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint,
org.apache.hadoop.hbase.security.access.AccessController</value>
 <description>A comma-separated list of coprocessors that are loaded
by default on all tables. For any override coprocessor method,
these classes will be called in order. After implementing your
own coprocessor, just put it in HBase's classpath and add the
fully qualified class name here. A coprocessor can also be loaded on
demand by setting HTableDescriptor.
</description>
</property>

<property>
 <name>hbase.coprocessor.master.classes</name>
 <value>org.apache.hadoop.hbase.security.access.AccessController</value>
 <description>A comma-separated list of MasterObserver coprocessors that
are loaded by the active HMaster process. For any implemented
coprocessor
methods, the listed classes will be called in order. After implementing
your
own MasterObserver, add the class to HBase's classpath and add the fully
qualified class name here.
</description>
</property>
```

```

<property>
 <name>hbase.coprocessor.regionserver.classes</name>
 <value>org.apache.hadoop.hbase.security.access.AccessController</value>
 <description>A comma-separated list of RegionServerObserver coprocessors
 that are loaded by the HRegionServer processes. For any implemented
 coprocessor methods, the listed classes will be called in order. After
 implementing your own RegionServerObserver, add the class to the HBase
 classpath and fully qualified class name here.
 </description>
</property>

<property>
 <name>phoenix.queryserver.kerberos.principal</name>
 <value>hbase/_HOST@EXAMPLE.COM</value>
 <description>The Kerberos principal for the Phoenix Query Server
 process. The Phoenix Query Server is an optional component; this
 property only needs to be set when the query server is installed.
 </description>
</property>

<property>
 <name>phoenix.queryserver.keytab.file</name>
 <value>/etc/security/keytabs/hbase.service.keytab</value>
 <description>The path to the Kerberos keytab file for the
 Phoenix Query Server process. The Phoenix Query Server is an optional
 component; this property only needs to be set when the query server
 is installed.</description>
</property>

```

### 2.6.2.2.6. hive-site.xml

HiveServer2 supports Kerberos authentication for all clients.

Add the following information to the `hive-site.xml` file on every host in your cluster:

**Table 2.16. `hive-site.xml` Property Settings**

Property Name	Description
<code>hive.metastore.sasl.enabled</code>	If true, the Metastore Thrift interface will be secured with SASL and clients must authenticate with Kerberos.
<code>hive.metastore.kerberos.keytab.file</code>	The keytab for the Metastore Thrift service principal.
<code>hive.metastore.kerberos.principal</code>	The service principal for the Metastore Thrift server. If <code>_HOST</code> is used as the hostname portion, it will be replaced with the actual hostname of the running instance.

Following is the XML for these entries:

```

<property>
 <name>hive.metastore.sasl.enabled</name>
 <value>true</value>
 <description>If true, the metastore thrift interface will be secured with
 SASL.
 Clients must authenticate with Kerberos.</description>
</property>

<property>
 <name>hive.metastore.kerberos.keytab.file</name>
 <value>/etc/security/keytabs/hive.service.keytab</value>
 <description>The path to the Kerberos Keytab file containing the

```

```

 metastore thrift server's service principal.
 </description>
</property>

<property>
 <name>hive.metastore.kerberos.principal</name>
 <value>hive/_HOST@EXAMPLE.COM</value>
 <description>The service principal for the metastore thrift server. The
special string _HOST will be replaced automatically with the correct
hostname.</description>
</property>

```

### 2.6.2.2.7. oozie-site.xml

To the `oozie-site.xml` file, add the following information:

**Table 2.17. oozie-site.xml Property Settings**

Property Name	Property Value	Description
<code>oozie.service.AuthorizationService.security.enabled</code>	true	Specifies whether security (user name/admin role) is enabled or not. If it is disabled any user can manage the Oozie system and manage any job.
<code>oozie.service.HadoopAccessorService.kerberos.enabled</code>	true	Indicates if Oozie is configured to use Kerberos.
<code>local.realm</code>	EXAMPLE.COM	Kerberos Realm used by Oozie and Hadoop. Using local.realm to be aligned with Hadoop configuration.
<code>oozie.service.HadoopAccessorService.keytab.file</code>	<code>/etc/security/keytabs/oozie.service.keytab</code>	The keytab for the Oozie service principal.
<code>oozie.service.HadoopAccessorService.kerberos.principaloozie/_HOST@EXAMPLE.COM</code>	<code>oozie/_HOST@EXAMPLE.COM</code>	Kerberos principal for Oozie service.
<code>oozie.authentication.type</code>	kerberos	
<code>oozie.authentication.kerberos.principal</code>	<code>HTTP/_HOST@EXAMPLE.COM</code>	Whitelisted job tracker for Oozie service.
<code>oozie.authentication.kerberos.keytab</code>	<code>/etc/security/keytabs/spnego.service.keytab</code>	Location of the Oozie user keytab file.
<code>oozie.service.HadoopAccessorService.nameNode.whitelist</code>		
<code>oozie.authentication.kerberos.name.rules</code>	<code>RULE:[2:\$1@\$0]([jt]t@.*EXAMPLE.COM)s/.*/mapred/ RULE:[2:\$1@\$0]([nd]n@.*EXAMPLE.COM)s/.*/hdfs/ RULE:[2:\$1@\$0](hm@.*EXAMPLE.COM)s/.*/hbase/ RULE:[2:\$1@\$0](rs@.*EXAMPLE.COM)s/.*/hbase/ DEFAULT</code>	The mapping from Kerberos principal names to local OS user names. See <a href="#">Creating Mappings Between Principals and UNIX Usernames</a> for more information.
<code>oozie.service.ProxyUserService.proxyuser.knox.groups</code>	users	Grant proxy privileges to the Knox user. Note only required when using a Knox Gateway.
<code>oozie.service.ProxyUserService.proxyuser.knox.hosts</code>	<code>\$knox_host_FQDN</code>	Identifies the Knox Gateway. Note only required when using a Knox Gateway.

### 2.6.2.2.8. webhcat-site.xml

To the `webhcat-site.xml` file, add the following information:

**Table 2.18. webhcat-site.xml Property Settings**

Property Name	Property Value	Description
templeton.kerberos.principal	HTTP/_HOST@EXAMPLE.COM	
templeton.kerberos.keytab	/etc/security/keytabs/ spnego.service.keytab	
templeton.kerberos.secret	secret	
hadoop.proxyuser.knox.groups	users	Grant proxy privileges to the Knox user. Note only required when using a Knox Gateway.
hadoop.proxyuser.knox.hosts	\$knox_host_FQDN	Identifies the Knox Gateway. Note only required when using a Knox Gateway.

## 2.6.2.2.9. limits.conf

### Adjust the Maximum Number of Open Files and Processes

In a secure cluster, if the DataNodes are started as the root user, JSVC downgrades the processing using setuid to hdfs. However, the ulimit is based on the ulimit of the root user, and the default ulimit values assigned to the root user for the maximum number of open files and processes may be too low for a secure cluster. This can result in a "Too Many Open Files" exception when the DataNodes are started.

Therefore, when configuring a secure cluster you should increase the following root ulimit values:

- **nofile:** The maximum number of open files. Recommended value: 32768
- **nproc:** The maximum number of processes. Recommended value: 65536

To set system-wide ulimits to these values, log in as root and add the following lines to the /etc/security/limits.conf file on every host in your cluster:

```
* - nofile 32768
* - nproc 65536
```

To set only the root user ulimits to these values, log in as root and add the following lines to the the /etc/security/limits.conf file.

```
root - nofile 32768
root - nproc 65536
```

You can use the ulimit -a command to view the current settings:

```
[root@node-1 /]# ulimit -a
core file size (blocks, -c) 0
data seg size (kbytes, -d) unlimited
scheduling priority (-e) 0
file size (blocks, -f) unlimited
pending signals (-i) 14874
max locked memory (kbytes, -l) 64
max memory size (kbytes, -m) unlimited
open files (-n) 1024
pipe size (512 bytes, -p) 8
POSIX message queues (bytes, -q) 819200
```

```
real-time priority (-r) 0
stack size (kbytes, -s) 10240
cpu time (seconds, -t) unlimited
max user processes (-u) 14874
virtual memory (kbytes, -v) unlimited
file locks (-x) unlimited
```

You can also use the ulimit command to dynamically set these limits until the next reboot. This method sets a temporary value that will revert to the settings in the /etc/security/limits.conf file after the next reboot, but it is useful for experimenting with limit settings. For example:

```
[root@node-1 ~]# ulimit -n 32768
```

The updated value can then be displayed:

```
[root@node-1 ~]# ulimit -n
32768
```

### 2.6.2.3. Configuring HBase and ZooKeeper

Use the following instructions to set up secure HBase and ZooKeeper:

1. [Configure HBase Master \[73\]](#)
2. [Create JAAS configuration files \[75\]](#)
3. [Start HBase and ZooKeeper services \[77\]](#)
4. [Configure secure client side access for HBase \[77\]](#)
5. [Optional: Configure client-side operation for secure operation - Thrift Gateway \[78\]](#)
6. [Optional: Configure client-side operation for secure operation - REST Gateway \[79\]](#)
7. [Configure HBase for Access Control Lists \(ACL\) \[79\]](#)

#### 2.6.2.3.1. Configure HBase Master

Edit \$HBASE\_CONF\_DIR/hbase-site.xml file on your HBase Master server to add the following information (\$HBASE\_CONF\_DIR is the directory to store the HBase configuration files. For example, /etc/hbase/conf):



#### Note

There are no default values. The following are all examples.

```
<property>
 <name>hbase.master.keytab.file</name>
 <value>/etc/security/keytabs/hbase.service.keytab</value>
 <description>Full path to the kerberos keytab file to use
 for logging in the configured HMaster server principal.

 </description>
</property>
```

```
<property>
 <name>hbase.master.kerberos.principal</name>
 <value>hbase/_HOST@EXAMPLE.COM</value>
 <description>Ex. "hbase/_HOST@EXAMPLE.COM".
 The kerberos principal name that should be used to run the HMaster
 process.
 The principal name should be in the form: user/hostname@DOMAIN.
 If "_HOST" is used as the hostname portion,
 it will be replaced with the actual hostname of the running instance.

 </description>
</property>

<property>
 <name>hbase.regionserver.keytab.file</name>
 <value>/etc/security/keytabs/hbase.service.keytab</value>
 <description>Full path to the kerberos keytab file to use for logging
 in the configured HRegionServer server principal.
 </description>
</property>

<property>
 <name>hbase.regionserver.kerberos.principal</name>
 <value>hbase/_HOST@EXAMPLE.COM</value>
 <description>Ex. "hbase/_HOST@EXAMPLE.COM".
 The kerberos principal name that
 should be used to run the HRegionServer process.
 The
 principal name should be in the form:
 user/hostname@DOMAIN.
 If _HOST
 is used as the hostname portion, it will be replaced
 with the actual hostname of the running
 instance.
 An entry for this principal must exist
 in the file specified in hbase.regionserver.keytab.file
 </description>
</property>

<!--Additional configuration specific to HBase security -->

<property>
 <name>hbase.superuser</name>
 <value>hbase</value>
 <description>List of users or groups (comma-separated), who are
 allowed full privileges, regardless of stored ACLs, across the cluster.
 Only used when HBase security is enabled.
 </description>
</property>

<property>
 <name>hbase.coprocessor.region.classes</name>
 <value>org.apache.hadoop.hbase.security.token.TokenProvider,
org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint,
org.apache.hadoop.hbase.security.access.AccessController </value>
 <description>A comma-separated list of Coprocessors that are loaded by
 default on all tables.
 </description>
</property>
```

```
<property>
 <name>hbase.security.authentication</name>
 <value>kerberos</value>

</property>

<property>
 <name>hbase.rpc.engine</name>
 <value>org.apache.hadoop.hbase.ipc.SecureRpcEngine</value>

</property>

<property>
 <name>hbase.security.authorization</name>
 <value>true</value>
 <description>Enables HBase authorization.
Set the value of this property to false to disable HBase authorization.
 </description>

</property>

<property>
 <name>hbase.coprocessor.master.classes</name>
 <value>org.apache.hadoop.hbase.security.access.AccessController</
value>

</property>

<property>
 <name>hbase.bulkload.staging.dir</name>
 <value>/apps/hbase/staging</value>
 <description>Directory in the default filesystem,
owned by the hbase user, and has permissions(-rwx--x--x, 711) </description>

</property>
```

For more information on bulk loading in secure mode, see [HBase Secure BulkLoad](#). Note that the `hbase.bulkload.staging.dir` is created by HBase.

### 2.6.2.3.2. Create JAAS configuration files

1. Create the following JAAS configuration files on the HBase Master, RegionServer, and HBase client host machines.

These files must be created under the `$HBASE_CONF_DIR` directory:

where `$HBASE_CONF_DIR` is the directory to store the HBase configuration files. For example, `/etc/hbase/conf`.

- On each machine running an HBase server, create the `hbase-server.jaas` file under the `/etc/hbase/conf` directory and add the following content:

```
Client {
 com.sun.security.auth.module.Krb5LoginModule required
 useKeyTab=true
 storeKey=true
 useTicketCache=false
 keyTab="/etc/security/keytabs/hbase.service.keytab"
 principal="hbase/$fully.qualified.domain.name";
};
```

- On HBase client machines, create the `hbase-client.jaas` file under the `/etc/hbase/conf` directory. HBase servers include the HMaster and RegionServer. In this file, add the following content:

```
Client {
 com.sun.security.auth.module.Krb5LoginModule required
 useKeyTab=false
 useTicketCache=true;
};
```

2. Create the following JAAS configuration files on the ZooKeeper Server and client host machines.

These files must be created under the `$ZOOKEEPER_CONF_DIR` directory, where `$ZOOKEEPER_CONF_DIR` is the directory to store the HBase configuration files. For example, `/etc/zookeeper/conf`:

- On ZooKeeper server host machines, create the `zookeeper-server.jaas` file under the `/etc/zookeeper/conf` directory and add the following content:

```
Server {
 com.sun.security.auth.module.Krb5LoginModule required
 useKeyTab=true
 storeKey=true
 useTicketCache=false
 keyTab="/etc/security/keytabs/zookeeper.service.keytab"
 principal="zookeeper/$ZooKeeper.Server.hostname";
};
```

- On ZooKeeper client host machines, create the `zookeeper-client.jaas` file under the `/etc/zookeeper/conf` directory and add the following content:

```
Client {
 com.sun.security.auth.module.Krb5LoginModule required
 useKeyTab=false
 useTicketCache=true;
};
```

3. Edit the `hbase-env.sh` file on your HBase server to add the following information:

```
export HBASE_OPTS="-Djava.security.auth.login.config=
$HBASE_CONF_DIR/hbase-client.jaas"
export HBASE_MASTER_OPTS="-Djava.security.auth.login.config=
$HBASE_CONF_DIR/hbase-server.jaas"
export HBASE_REGIONSERVER_OPTS="-Djava.security.auth.login.config=
$HBASE_CONF_DIR/hbase-server.jaas"
```

where `HBASE_CONF_DIR` is the HBase configuration directory. For example, `/etc/hbase/conf`.

4. Edit `zoo.cfg` file on your ZooKeeper server to add the following information:

```
authProvider.1=org.apache.zookeeper.server.auth.SASLAuthenticationProvider
jaasLoginRenew=3600000
kerberos.removeHostFromPrincipal=true
kerberos.removeRealmFromPrincipal=true
```

5. Edit `zookeeper-env.sh` file on your ZooKeeper server to add the following information:

```
export SERVER_JVMFLAGS ="-Djava.security.auth.login.config=$ZOOKEEPER_CONF_DIR/zookeeper-server.jaas"
export CLIENT_JVMFLAGS ="-Djava.security.auth.login.config=$ZOOKEEPER_CONF_DIR/zookeeper-client.jaas"
```

where `$ZOOKEEPER_CONF_DIR` is the ZooKeeper configuration directory. For example, `/etc/zookeeper/conf`.

#### 2.6.2.3.3. Start HBase and ZooKeeper services

Start the HBase and ZooKeeper services using the instructions provided in the HDP Reference Manual, [Starting HDP Services](#).

If the configuration is successful, you should see the following in your ZooKeeper server logs:

```
11/12/05 22:43:39 INFO zookeeper.Login: successfully logged in.
11/12/05 22:43:39 INFO server.NIOServerCnxnFactory: binding to port 0.0.0.0/0.0.0.0:2181
11/12/05 22:43:39 INFO zookeeper.Login: TGT refresh thread started.
11/12/05 22:43:39 INFO zookeeper.Login: TGT valid starting at: Mon Dec 05 22:43:39 UTC 2011
11/12/05 22:43:39 INFO zookeeper.Login: TGT expires: Tue Dec 06 22:43:39 UTC 2011
11/12/05 22:43:39 INFO zookeeper.Login: TGT refresh sleeping until: Tue Dec 06 18:36:42 UTC 2011
...
11/12/05 22:43:59 INFO auth.SaslServerCallbackHandler:
 Successfully authenticated client: authenticationID=hbase/ip-10-166-175-249.us-west-1.compute.internal@HADOOP.LOCALDOMAIN;
 authorizationID=hbase/ip-10-166-175-249.us-west-1.compute.internal@HADOOP.LOCALDOMAIN.
11/12/05 22:43:59 INFO auth.SaslServerCallbackHandler: Setting authorizedID: hbase
11/12/05 22:43:59 INFO server.ZooKeeperServer: adding SASL authorization for authorizationID: hbase
```

#### 2.6.2.3.4. Configure secure client side access for HBase

HBase configured for secure client access is expected to be running on top of a secure HDFS cluster. HBase must be able to authenticate to HDFS services.

1. Provide a Kerberos principal to the HBase client user using the instructions provided [here](#).

- **Option I:** Provide Kerberos principal to normal HBase clients.

For normal HBase clients, Hortonworks recommends setting up a password to the principal.

- Set `maxrenewlife`.

The client principal's `maxrenewlife` should be set high enough so that it allows enough time for the HBase client process to complete. Client principals are not renewed automatically.

For example, if a user runs a long-running HBase client process that takes at most three days, we might create this user's principal within kadmin with the following command:

```
addprinc -maxrenewlife 3days
```

- **Option II:** Provide Kerberos principal to long running HBase clients.
  - a. Set-up a keytab file for the principal and copy the resulting keytab files to where the client daemon will execute.

Ensure that you make this file readable only to the user account under which the daemon will run.

2. On every HBase client, add the following properties to the `$HBASE_CONF_DIR/hbase-site.xml` file:

```
<property>
 <name>hbase.security.authentication</name>
 <value>kerberos</value>
</property>
```



### Note

The client environment must be logged in to Kerberos from KDC or keytab via the `kinit` command before communication with the HBase cluster is possible. Note that the client will not be able to communicate with the cluster if the `hbase.security.authentication` property in the client-and server-side site files fails to match.

```
<property>
 <name>hbase.rpc.engine</name>
 <value>org.apache.hadoop.hbase.ipc.SecureRpcEngine</value>
</property>
```

#### 2.6.2.3.5. Optional: Configure client-side operation for secure operation - Thrift Gateway

Add the following to the `$HBASE_CONF_DIR/hbase-site.xml` file for every Thrift gateway:

```
<property>
 <name>hbase.thrift.keytab.file</name>
 <value>/etc/hbase/conf/hbase.keytab</value>
</property>
<property>
 <name>hbase.thrift.kerberos.principal</name>
 <value>$USER/_HOST@HADOOP.LOCALDOMAIN</value>
</property>
```

Substitute the appropriate credential and keytab for `$USER` and `$KEYTAB` respectively.

The Thrift gateway will authenticate with HBase using the supplied credential. No authentication will be performed by the Thrift gateway itself. All client access via the Thrift gateway will use the Thrift gateway's credential and have its privilege.

#### 2.6.2.3.6. Optional: Configure client-side operation for secure operation - REST Gateway

Add the following to the `$HBASE_CONF_DIR/hbase-site.xml` file for every REST gateway:

```
<property>
 <name>hbase.rest.keytab.file</name>
 <value>$KEYTAB</value>
</property>
<property>
 <name>hbase.rest.kerberos.principal</name>
 <value>$USER/_HOST@HADOOP.LOCALDOMAIN</value>
</property>
```

Substitute the appropriate credential and keytab for `$USER` and `$KEYTAB` respectively.

The REST gateway will authenticate with HBase using the supplied credential. No authentication will be performed by the REST gateway itself. All client access via the REST gateway will use the REST gateway's credential and have its privilege.

#### 2.6.2.3.7. Configure HBase for Access Control Lists (ACL)

Use the following instructions to configure HBase for ACL:

1. Open kinit as HBase user.

a. Create a keytab for principal `hbase@REALM` and store it in the `hbase.headless.keytab` file. See instructions provided [here](#) for creating principal and keytab file.

b. Open kinit as HBase user. Execute the following command on your HBase Master:

```
kinit -kt hbase.headless.keytab hbase
```

2. Start the HBase shell. On the HBase Master host machine, execute the following command:

```
hbase shell
```

3. Set ACLs using HBase shell:

```
grant '$USER', '$permissions'
```

where

- `$USER` is any user responsible for create/update/delete operations in HBase.



#### Note

You must set the ACLs for all those users who will be responsible for create/update/delete operations in HBase.

- *\$permissions* is zero or more letters from the set "RWCA": READ('R'), WRITE('W'), CREATE('C'), ADMIN('A').

## 2.6.2.4. Configuring Hue

Before you can configure Hue to work with an HDP cluster that is configured for Kerberos, you must refer to and complete the instructions for [Configuring Ambari and Hadoop for Kerberos](#) or [Setting Up Kerberos Security for Manual Installs](#).

To enable Hue to work with an HDP cluster configured for Kerberos, make the following changes to Hue and Kerberos.:

1. Where \$FQDN is the host name of the Hue server and EXAMPLE.COM is the Hadoop realm, create a principal for the Hue server:

```
kadmin.local
kadmin.local: addprinc -randkey hue/$FQDN@EXAMPLE.COM
```

2. Where \$FQDN is the host name of the Hue server and EXAMPLE.COM is the Hadoop realm, generate a keytab for the Hue principal:

```
kadmin.local: xst -k hue.service.keytab hue/$FQDN@EXAMPLE.COM
```

3. Put the hue.service.keytab file on the host where the Hue server is installed, in the directory /etc/security/keytabs.

4. Set the permissions and ownership of the /etc/security/keytabs/hue.service.keytab file as follows:

```
chown hue:hadoop /etc/security/keytabs/hue.service.keytab
chmod 600 /etc/security/keytabs/hue.service.keytab
```

5. Where \$FQDN is the host name of the Hue server and EXAMPLE.COM is the Hadoop realm, use **kinit** to confirm that the /etc/security/keytabs/hue.service.keytab file is accessible to Hue:

```
su - hue kinit -k -t /etc/security/keytabs/hue.service.keytab hue/
$FQDN@EXAMPLE.COM
```

6. Where \$FQDN is the host name of the Hue server and EXAMPLE.COM is the Hadoop realm, add the following to the [kerberos] section in the /etc/hue/conf/hue.ini configuration file:

```
[[kerberos]]
Path to Hue's Kerberos keytab file
hue_keytab=/etc/security/keytabs/hue.service.keytab
Kerberos principal name for Hue
hue_principal=hue/$FQDN@EXAMPLE.COM
```

7. Set the path to **kinit**, based on the OS.

If you do not know the full path to **kinit**, you can find it by issuing the command **where is kinit**.

The following is an example of setting the path to **kinit** for RHEL/CentOS 6.x:

```
Path to kinit
For RHEL/CentOS 6.x, kinit_path is /usr/bin/kinit
kinit_path=/usr/kerberos/bin/kinit
```

8. Optionally, for faster performance, you can keep Kerberos credentials cached:

```
ccache_path=/tmp/hue_krb5_ccache
```

9. Edit the /etc/hue/conf/hue.ini configuration file and set set security\_enabled=true for every component in the configuration file.

10 Save the /etc/hue/conf/hue.ini configuration file.

11 Restart Hue:

```
/etc/init.d/hue start
```

12 Validate the Hue installation.

- a. To view the current configuration of your Hue server, select **About > Configuration** or [http://hue.server:8000/dump\\_config](http://hue.server:8000/dump_config).
- b. To ensure that Hue server was configured properly, select **About > Check** for misconfiguration or [http://hue.server:8000/debug/check\\_config](http://hue.server:8000/debug/check_config).

If you detect any potential misconfiguration, fix it and restart Hue.

### 2.6.2.5. Configuring Phoenix Query Server

The HBase configuration provides most of the settings that enable secure Kerberos environments for Phoenix. However, there are additional configuration properties that complete the setup of Kerberos security for the Phoenix Query Server.

**Prerequisite:** The value of the hbase.security.authentication property in the \$HBASE\_CONF\_DIR/hbase-site.xml file must be set to kerberos.

Provide the Kerberos principal and keytab for the Phoenix Query Server in the \$HBASE\_CONF\_DIR/hbase-site.xml file, as follows:

```
<property>
 <name>phoenix.queryserver.kerberos.principal</name>
 <value>hbase/_HOST@EXAMPLE.COM</value>
 <description>The Kerberos principal name that should be used to run the Phoenix Query Server process.
 The principal name should be in the form: user/hostname@DOMAIN. If "_HOST" is used as the hostname
 portion, it will be replaced with the actual hostname of the running instance.
 </description>
</property>

<property>
 <name>phoenix.queryserver.keytab.file</name>
 <value>/etc/security/keytabs/hbase.service.keytab</value>
 <description>Full path to the Kerberos keytab file to use for logging in the configured Phoenix Query Server service principal.
 </description>
```

```
</property>
```

## 2.6.3. Setting up One-Way Trust with Active Directory

In environments where users from Active Directory (AD) need to access Hadoop Services, set up one-way trust between Hadoop Kerberos realm and the AD (Active Directory) domain.



### Important

Hortonworks recommends setting up one-way trust after fully configuring and testing your Kerberized Hadoop Cluster.

### 2.6.3.1. Configure Kerberos Hadoop Realm on the AD DC

Configure the Hadoop realm on the AD DC server and set up the one-way trust.

1. Add the Hadoop Kerberos realm and KDC host to the DC:

```
ksetup /addkdc $hadoop.realm $KDC-host
```

2. Establish one-way trust between the AD domain and the Hadoop realm:

```
netdom trust $hadoop.realm /Domain:$AD.domain /add /realm /passwordt:
$trust_password
```

3. (Optional) If Windows clients within the AD domain need to access Hadoop Services, and the domain does not have a search route to find the services in Hadoop realm, run the following command to create a hostmap for Hadoop service host:

```
ksetup /addhosttorealmmap $hadoop-service-host $hadoop.realm
```



### Note

Run the above for each \$hadoop-host that provides services that need to be accessed by Windows clients. For example, Oozie host, WebHCat host, etc.

4. (Optional) Define the encryption type:

```
ksetup /SetEncTypeAttr $hadoop.realm $encryption_type
```

Set encryption types based on your security requirements. Mismatched encryption types cause problems.



### Note

Run ksetup /GetEncTypeAttr \$krb\_realm to list the available encryption types. Verify that the encryption type is configured for the Hadoop realm in the krb5.conf.

### 2.6.3.2. Configure the AD Domain on the KDC and Hadoop Cluster Hosts

Add the AD domain as a realm to the krb5.conf on the Hadoop cluster hosts. Optionally configure encryption types and UDP preferences.

## 1. Open the krb5.conf file with a text editor and make the following changes:

- To libdefaults, add the following properties.

- Set the Hadoop realm as default:

```
[libdefaults]
default_domain = $hadoop.realm
```

- Set the encryption type:

```
[libdefaults]
default_tkt_enctypes = $encryption_types
default_tgs_enctypes = $encryption_types
permitted_enctypes = $encryption_types
```

where the \$encryption\_types match the type supported by your environment.

For example:

```
default_tkt_enctypes = aes256-cts aes128-cts rc4-hmac arcfour-hmac-md5
des-cbc-md5 des-cbc-crc
default_tgs_enctypes = aes256-cts aes128-cts rc4-hmac arcfour-hmac-md5
des-cbc-md5 des-cbc-crc
permitted_enctypes = aes256-cts aes128-cts rc4-hmac arcfour-hmac-md5
des-cbc-md5 des-cbc-crc
```

- If TCP is open on the KDC and AD Server:

```
[libdefaults]
udp_preference_limit = 1
```

- Add a realm for the AD domain:

```
[realms]
$AD.DOMAIN = {
kdc = $AD-host-FQDN
admin_server = $AD-host-FQDN
default_domain = $AD-host-FQDN
}
```

- Save the krb5.conf changes to all Hadoop Cluster hosts.

## 2. Add the trust principal for the AD domain to the Hadoop MIT KDC:

```
kadmin
kadmin:addprinc krbtgt/$hadoop.realm@$AD.domain
```

This command will prompt you for the trust password. Use the same password as the earlier step.



### Note

If the encryption type was defined, then use the following command to configure the AD principal:

```
kadmin:addprinc -e "$encryption_type"krbtgt/$hadoop.realm@$AD.domain
```

When defining encryption, be sure to also enter the encryption type (e.g., 'normal')

## 2.6.4. Configuring Proxy Users

For information about configuring a superuser account that can submit jobs or access HDFS on behalf of another user, see the following information on the Apache site:

[Proxy user - Superusers Acting on Behalf of Other Users.](#)

# 2.7. Perimeter Security with Apache Knox


## 2.7.1. Apache Knox Gateway Overview

The Apache Knox Gateway ("Knox") is a system to extend the reach of Apache™Hadoop® services to users outside of a Hadoop cluster without reducing Hadoop Security. Knox also simplifies Hadoop security for users who access the cluster data and execute jobs.

Knox integrates with Identity Management and SSO systems used in enterprises and allows identity from these systems be used for access to Hadoop clusters.

Knox Gateways provides security for multiple Hadoop clusters, with these advantages:

- **Simplifies access:** Extends Hadoop's REST/HTTP services by encapsulating Kerberos to within the Cluster.
- **Enhances security:** Exposes Hadoop's REST/HTTP services without revealing network details, providing SSL out of the box.
- **Centralized control:** Enforces REST API security centrally, routing requests to multiple Hadoop clusters.
- **Enterprise integration:** Supports LDAP, Active Directory, SSO, SAML and other authentication systems.



### Typical Security Flow: Firewall, Routed Through Knox Gateway


Knox can be used with both unsecured Hadoop clusters, and Kerberos secured clusters. In an enterprise solution that employs Kerberos secured clusters, the Apache Knox Gateway provides an enterprise security solution that:

- Integrates well with enterprise identity management solutions
- Protects the details of the Hadoop cluster deployment (hosts and ports are hidden from end users)
- Simplifies the number of services with which a client needs to interact

### 2.7.1.1. Knox Gateway Deployment Architecture

Users who access Hadoop externally do so either through Knox, via the Apache REST API, or through the Hadoop CLI tools.

The following diagram shows how Apache Knox fits into a Hadoop deployment.



NN=NameNode, RM=Resource Manager, DN=DataNode, NM=NodeManager

### 2.7.1.2. Supported Hadoop Services

Apache Knox Gateway supports the following Hadoop services versions in both Kerberized and Non-Kerberized clusters:

**Table 2.19. Supported Hadoop Services**

Service	Version
YARN	2.7.0
WebHDFS	2.7.0
WebHCat/Templeton	0.13.0
Oozie	4.2.0
HBase/Stargate	1.1
Hive (via WebHCat)	1.2.0
Hive (via JDBC)	1.2.0

#### Note



UIs in the Apache Knox project that are not listed above are considered Community Features.

Community Features are developed and tested by the Apache Knox community but are not officially supported by Hortonworks. These features are excluded for a variety of reasons, including insufficient reliability or incomplete test case coverage, declaration of non-production readiness by the community at

large, and feature deviation from Hortonworks best practices. Do not use these features in your production environments.

### 2.7.1.3. Knox Gateway Samples

There are a number of different methods you can use to deploy the Knox Gateway in your cluster. Each of these methods consists of different ways you can use to install and configure the Knox Gateway. For more information on these methods, refer to the following Apache documentation:

- <http://knox.apache.org/books/knox-0-5-0/knox-0-5-0.html#Gateway+Samples>

## 2.7.2. Configuring the Knox Gateway

This section describes how to configure the Knox Gateway. This section describes how you can:

- [Create and Secure the Gateway Directories \[86\]](#)
- [Customize the Gateway Port and Path \[87\]](#)
- [Manage the Master Secret \[87\]](#)
- [Manually Redeploy Cluster Topologies \[88\]](#)
- [Manually Start and Stop Apache Knox \[90\]](#)

### 2.7.2.1. Create and Secure the Gateway Directories

Installing Knox Gateway with the platform-specific installers creates the following directories:

- HADOOP\_NODE\_INSTALL\_ROOT
- knox-X.X.X.X.X.X-XXXX – the \$gateway directory.

For example, *D:/hdp/knox-0.4.0.2.1.1.0-1557* The directory contains the following files:

**Table 2.20. Apache Service Gateway Directores**

Directory/Filename	Description
conf/topologies	Contains global gateway configuration files.
bin	Contains the executable shell scripts, batch files, and JARs for clients and servers.
deployments	Contains cluster topology descriptor files that define Hadoop clusters.
lib	Contains the JARs for all the components that make up the gateway.
dep	Contains the JARs for all of the component upon which the gateway depends.
ext	A directory where user-supplied extensions JARs can be placed to extends the gateway functionality.
samples	Contains a number of samples that can be used to explore the functionality of the gateway.

Directory/Filename	Description
templates	Contains default configuration files that can be copied and customized.
README	Provides basic information about the Apache Knox Gateway.
ISSUES	Describes significant known issues.
CHANGES	Enumerates the changes between releases.
LICENSE	Documents the license under which this software is provided.
NOTICE	Documents required attribution notices for included dependencies.
DISCLAIMER	Documents that this release is from a project undergoing incubation at Apache.

- *SystemDrive/hadoop/logs knox*

This contains the output files from the Knox Gateway.

### 2.7.2.2. Customize the Gateway Port and Path

The Knox Gateway properties effect the URL used by the external clients to access the internal cluster. By default the port is set to 8443 and the context path is gateway.

To change the context path or port:

1. Edit `gateway-site.xml` and modify the following properties:

- `propertyname`
- `gateway.port namevalue`
- `gateway.portvalue`

where:

- `$gateway_port` is the HTTP port for the gateway (default port=8443)
- `$gateway` is the context path in the external URL (preconfigured value=gateway). For example, `https://knox.hortonworks.com:8443/hadoop/`, where `hadoop` is the context path.

2. Restart the gateway:

```
cd $gateway/bin/gateway.sh stop bin/gateway.sh start
```

The gateway loads the new configuration on startup.

### 2.7.2.3. Manage the Master Secret

The master secret is required to start the gateway. The secret protects artifacts used by the gateway instance, such as the keystore, trust stores and credential stores.

You configure the gateway to persist the master secret, which is saved in the `$gateway / data/security/master` file. Ensure that this directory has the appropriate permissions set for your environment. To set the master secret, enter:

```
cd $gateway bin/knoxcli.cmd create-master
```

A warning displays indicating that persisting the secret is less secure than providing it at startup. Knox protects the password by encrypting it with AES 128 bit encryption; where possible, the file permissions are set to be accessible only by the knox user.



## Warning

Ensure that the security directory, `$gateway/data/security`, and its contents are readable and writable only by the knox user. This is the most important layer of defense for master secret. **Do not assume that the encryption is sufficient protection.**

### Changing the Master Secret

The Master Secret can be changed under dire situations where the Administrator has to redo all the configurations for every dateway instance in a deployment, and no longer knows the Master Secret. Recreating the Master Secret requires not only recreating the master, but also removing all existing keystores and reprovisioning the certificates and credentials.

1. To change the Master Secret:

```
cd $gateway bin/knoxcli.cmd create-master--force
```

2. If there is an existing keystore, update the keystore.

### 2.7.2.4. Manually Redeploy Cluster Topologies

You are not required to manually redeploy clusters after updating cluster properties. The gateway monitors the topology descriptor files in the `$gateway/conf/topologies` directory and automatically redeploys the cluster if any descriptor changes or a new one is added. (The corresponding deployment is in `$gateway/data/deployments`.)

However, you must redeploy the clusters after changing any of the following gateway properties or gateway-wide settings:

- Time settings on the gateway host
- Implementing or updating Kerberos
- Implementing or updating SSL certificates
- Changing a cluster alias

#### Redeploying all clusters at the same time

When making gateway-wide changes (such as implementing Kerberos or SSL), or if you change the system clock, you must redeploy all the Cluster Topologies. Do the following:

1. To verify the timestamp on the currently deployed clusters enter: `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments
```

```
04/17/2014 05:30 PM <DIR> .
04/17/2014 05:30 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
 0 File(s) 0 bytes
 5 Dir(s) 9,730,977,792 bytes free
```

2. To redeploy all clusters, enter `/bin/knoxcli.cmd redeploy`.
3. To verify that a new cluster WAR was created, enter `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments

04/17/2014 05:34 PM <DIR> .
04/17/2014 05:34 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:34 PM <DIR> cluster.war.1457241b5dc
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/17/2014 05:34 PM <DIR> myCluster.war.1457241b5dc
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
04/17/2014 05:34 PM <DIR> sandbox.war.1457241b5dc
 0 File(s) 0 bytes
 8 Dir(s) 9,730,850,816 bytes free
```

A new file is created for each cluster, with the current timestamp.

### Redeploy only specific clusters

When making changes that impact a single cluster, such as changing an alias or restoring from an earlier cluster topology descriptor file, you only redeploy the effected cluster. Do the following:

1. To verify the timestamp on the currently deployed Cluster Topology WAR files, enter: `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments

04/17/2014 05:30 PM <DIR> .
04/17/2014 05:30 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
 0 File(s) 0 bytes
 5 Dir(s) 9,730,977,792 bytes free
```

2. To redeploy a specific cluster, enter:

```
cd $gateway bin/knoxcli.cmd redeploy --cluster $cluster_name
```

where `$cluster_name` is the name of the cluster topology descriptor (without the `.xml` extension). For example, `myCluster`.

3. To verify that the cluster was deployed, enter: `cd $gatewaydir data/deployments`. The system displays something similar to:

```
Directory of C:/hdp/knox-0.4.0.2.1.1.0-1557/data/deployments
```

```
04/17/2014 05:30 PM <DIR> .
04/17/2014 05:30 PM <DIR> ..
04/17/2014 05:30 PM <DIR> cluster.war.145514f4dc8
04/17/2014 05:30 PM <DIR> myCluster.war.145514f4dc8
04/17/2014 05:34 PM <DIR> myCluster.war.1457241b5dc
04/11/2014 08:35 AM <DIR> sandbox.war.145514f4dc8
 0 File(s) 0 bytes
 5 Dir(s) 9,730,977,792 bytes free
```

You should see that existing cluster war files are unchanged, but the war file for myCluster was updated (has a current timestamp).

### 2.7.2.5. Manually Start and Stop Apache Knox

Except for changes to .. / .. /conf /topology / \*.xml, changes to the Knox Gateway global settings in \$gateway /conf /gateway-site.xml cannot be loaded before the Gateway is restarted.

**To manually stop Knox:**

```
cd $gateway/bin/gateway.sh stop
```

This is known as a clean shutdown, as the gateway script cleans out all .out and .err files in the logs directory.

**To manually start Knox for the first time, or re-start Knox after a clean shutdown:**

```
cd $gateway /bin/gateway.sh start
```

**To manually re-start Knox after an unclean shutdown:**

```
cd $gateway/bin/gateway.sh clean /bin/gateway.sh start
```

This command eliminates old .out and .err files in the logs directory.

### 2.7.3. Defining Cluster Topologies

The Knox Gateway supports one or more Hadoop clusters. Each Hadoop cluster configuration is defined in a topology deployment descriptor file in the \$gateway /conf /topologies directory and is deployed to a corresponding WAR file in the \$gateway /data /deployments directory. These files define how the gateway communicates with each Hadoop cluster.

The descriptor is an XML file contains the following sections:

- gateway/provider – configuration settings enforced by the Knox Gateway while providing access to the Hadoop cluster.
- service – defines the Hadoop service URLs used by the gateway to proxy communications from external clients.

The gateway automatically redeploys the cluster whenever it detects a new topology descriptor file, or detects a change in an existing topology descriptor file.

The following table provides an overview of the providers and services:

**Table 2.21. Cluster Topology Provider and Service Roles**

Type	Role	Description
gateway/provider	hostmap	Maps external to internal node hostnames, replacing the internal hostname with the mapped external name when the hostname is embedded in a response from the cluster.
	authentication	Integrates an LDAP store to authenticate external requests accessing the cluster via the Knox Gateway. Refer to Set Up LDAP Authentication for more information.
	federation	Defines HTTP header authentication fields for an SSO or federation solution provider. Refer to Set up HTTP Header Authentication for Federation/SSO
	identity-assertion	Responsible for the way that the authenticated user's identity is asserted to the service that the request is intended for. Also maps external authenticated users to an internal cluster that the gateway asserts as the current session user or group. Refer to Configure Identity Assertion for more information.
	authorization	Service level authorization that restricts cluster access to specified users, groups, and/or IP addresses. Refer to Configure Service Level Authorization for more information.
	webappspec	Configures a web application security plugin that provides protection filtering against Cross Site Request Forgery Attacks. Refer to Configure Web Application Security for more information.
HA provider	high availability	Syncs all Knox instances to use the same topologies credentials keystores.
service	\$service_name	Binds a Hadoop service with an internal URL that the gateway uses to proxy requests from external clients to the internal cluster services. Refer to Configure Hadoop Service URLs for more information.

Cluster topology descriptors have the following XML format:

```
<topology>
 <gateway>
 <provider>
 <role></role>
 <name></name>
 <enabled></enabled>
 <param>
 <name></name>
 <value></value>
 </param>
 </provider>
 </gateway>
```

```
<service></service>
</topology>
```

## 2.7.4. Configuring a Hadoop Server for Knox

The Apache Knox Gateway redirects external requests to an internal Hadoop service using service name and URL of the service definition.

This chapter describes:

- [Setting up Hadoop Service URLs \[92\]](#)
- [Example Service Definitions \[93\]](#)
- [Validating Service Connectivity \[93\]](#)
- [Adding a New Service to the Knox Gateway \[95\]](#)

### 2.7.4.1. Setting up Hadoop Service URLs

To configure access to an internal Hadoop service through the Knox Gateway:

1. Edit `$gateway/conf/topologies$cluster-name.xml` to add an entry similar to the following, for each Hadoop service:

```
<topology>
 <gateway>
 ...
 </gateway>
 <service>
 <role> $service_name </role>
 <url> $schema://$hostname:$port</url>
 </service>
</topology>
```

where:

- `$service_name` is either WEBHDFS, WEBHCAT, WEBHBASE, Oozie, HIVE, NAMENODE, or JOBTRACKER.
- `<url>` is the complete internal cluster URL required to access the service, including:
  - `$schema` – the service protocol
  - `$hostname` – the resolvable internal host name
  - `$port` – the service listening port

2. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.



#### Note

It is not necessary to restart the Knox server after making changes to the topology/Hadoop Cluster services.

## 2.7.4.2. Example Service Definitions

Configure each service that you want to expose externally, being careful to define the internal hostname and service ports of your cluster.

The following example uses the defaults ports and supported service names.

```
<service>
 <role>NAMENODE</role>
 <url>hdfs://namenode-host:8020</url>
</service>

<service>
 <role>JOBTRACKER</role>
 <url>rpc://jobtracker-host:8050</url>
</service>

<service>
 <role>RESOURCEMANAGER</role>
 <url>http://red3:8088/ws</url>
</service>

<service>
 <role>WEBHDFS</role>
 <url>http://localhost:50070/webhdfs</url>
</service>

<service>
 <role>WEBHCAT</role>
 <url>http://webcat-host:50111/templeton</url>
</service>

<service>
 <role>OOZIE</role>
 <url>http://oozie-host:11000/oozie</url>
</service>

<service>
 <role>WEBHBASE</role>
 <url>http://webhbbase-host:60080</url>
</service>

<service>
 <role>HIVE</role>
 <url>http://hive-host:10001/cliservice</url>
</service>
```

## 2.7.4.3. Validating Service Connectivity

Use the commands in this section to test connectivity between the gateway host and the Hadoop service, and then test connectivity between an external client to the Hadoop service through the gateway.



### Tip

If the communication between the gateway host and an internal Hadoop service fails, telnet to the service port to verify that the gateway is able to

access the cluster node. Use the hostname and ports you specified in the service definition.

### Testing WebHDFS by getting the home directory

- At the gateway host, enter the following command:

```
curl http://$webhdfs-host:50070/webhdfs/v1?op=GETHOMEDIRECTORY
```

The host displays:

```
{"Path": "/user/gopher"}
```

- At an external client, enter the following command:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/ $webhdfs_service_name/v1?op=GETHOMEDIRECTORY
```

The external client displays:

```
{"Path": "/user/gopher"}
```

### Testing WebHCat/Templeton by getting the version

- At the gateway host, enter the following command:

```
curl http://$webhdfs-host:50111/templeton/v1/version
```

The host displays:

```
{"supportedVersions": ["v1"], "version": "v1"}
```

- At an external client, enter the following command:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/ $webhcatt_service_name/v1/version
```

The external client displays:

```
{"supportedVersions": ["v1"], "version": "v1"}
```

### Testing Oozie by getting the version

- At the gateway host, enter the following command:

```
curl http://$oozie-host:11000/oozie/v1/admin/build-version
```

The host displays:

```
{"buildVersion": "4.0.0.2.1.1.0-302"}
```

- At an external client, enter the following command:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/ $oozie_service_name/v1/admin/build-version
```

The external client displays:

```
{"buildVersion": "4.0.0.2.1.1.0-302"}
```

### Testing HBase/Stargate by getting the version

- At the gateway host, enter the following command:

```
curl http://$hbase-host:17000/version
```

The host displays:

```
rest 0.0.2 JVM: Oracle Corporation 1.7.0_51-24.45-b08 OS: Linux 3.8.0-29-
generic amd64 Server:jetty/6.1.26 Jersey:1.8:
```

- At an external client, enter the following command:

```
curl http://$hbase-host:17000/version
```

The external client displays:

```
rest 0.0.2 JVM: Oracle Corporation 1.7.0_51-24.45-b08 OS: Linux 3.8.0-29-
generic amd64 Server:jetty/6.1.26 Jersey:1.8
```

### Testing HiveServer2

Both of the following URLs return an authentication error, which users can safely ignore.

1. At the gateway host, enter:

```
curl http://$hive-host:10001/cliservice
```

2. At an external client, enter:

```
curl https://$gateway-host:$gateway_port/$gateway/$cluster_name/
$hive_service_name/cliservice
```

## 2.7.4.4. Adding a New Service to the Knox Gateway

Services and service additions in the Knox Gateway are defined as extensions to existing Knox Gateway functionality that enable you to extend the gateway's capabilities. You use these services to convert information contained in the topology file to runtime descriptors.

The Knox Gateway supports a declarative way for you to "plug in" a new service into the gateway simply and easily by using the following two files:

- `service.xml`-file that contains the routes (paths) that the service will provide and the rewrite rules to bind these paths.
- `rewrite.xml` – file that contains the rewrite rules for the service.



### Note

The `service.xml` file is required, whereas the `rewrite.xml` file is optional.

### 2.7.4.4.1. Service Directory Structure

The Knox Gateway consists of a directory structure that you should become familiar with before attempting to add a new service to the gateway.

If you navigate to the data directory in your Knox home directory (`{GATEWAY_HOME}/data`), you will see the following directory structure:

```
Services
```

```
Service name
Version
 service.xml
 rewrite.xml
```

For example, if you were to navigate to the WebHDFS Service directory, you would see the following directory structure:

```
Services
 WebHDFS
 2.4.0
 service.xml
 rewrite.xml
```

#### 2.7.4.4.2. Adding a New Service to the Knox Gateway

Adding a new service to the Knox gateway is a very easy and straightforward process, only requiring you to perform a few simple steps, which are listed below.

1. Navigate to the services directory in your Knox gateway HOME directory (`{GATEWAY_HOME}/data/services`)
2. Add the `service.xml` and `rewrite.xml` files to the directory.



#### Note

If you want to add the service to the Knox build, then add the `service.xml` and `rewrite` files to the `gateway-services-definitions` module.

### 2.7.5. Mapping the Internal Nodes to External URLs

Hostmapping is an advanced configuration topic. Generally, it is only required in deployments in virtualized environments, such as Cloud deployments and some development and testing environments.

The isolation of the Hadoop cluster is accomplished through virtualization that will hide the internal networking details (such as IP addresses and/or hostnames) from the outside world, while exposing other IP addresses and/or hostnames for use by clients accessing the cluster from outside of the virtualized environment. The exposed IP addresses and hostnames are available for use in the topology descriptor service definitions. This configuration works great for requests that are initiated from the external clients themselves which only ever use the Knox Gateway exposed endpoints.

Difficulties from these virtualized environments arise when the Hadoop cluster redirects client requests to other nodes within the cluster and indicates the internal hostname locations, rather than those designated to be exposed externally. Since the Hadoop services don't know or care whether a request is coming from an external or internal client, it uses its only view of the cluster, which is the internal details of the virtualized environment.

The Knox Gateway needs to know how to route a request that has been redirected by the Hadoop service to an address that is not actually accessible by the gateway. Hostmapping acts as an adapter that intercepts the redirects from the Hadoop service and converts the indicated internal address to a known external address that Knox will be able to route

to once the client resends the request through the client facing gateway endpoint. The gateway uses the hostmap to replace the internal hostname within the routing policy for the particular request with the externally exposed hostname. This enables the dispatching from the Knox Gateway to successfully connect to the Hadoop service within the virtualized environment. Otherwise, attempting to route to an internal-only address will result in connection failures.

A number of the REST API operations require multi-step interactions that facilitate the client's interaction with multiple nodes within a distributed system such as Hadoop. External clients performing multi-step operations use the URL provided by the gateway in the responses to form the next request. Since the routing policy is hidden by the gateway from the external clients, the fact that the subsequent requests in the multi-stepped interaction are mapped to the appropriate externally exposed endpoints is not exposed to the client.

For example, when uploading a file with WebHDFS service:

1. The external client sends a request to the gateway WebHDFS service.
2. The gateway proxies the request to WebHDFS using the service URL.
3. WebHDFS determines which DataNodes to create the file on and returns the path for the upload as a Location header in a HTTP redirect, which contains the datanode host information.
4. The gateway augments the routing policy based on the datanode hostname in the redirect by mapping it to the externally resolvable hostname.
5. The external client continues to upload the file through the gateway.
6. The gateway proxies the request to the datanode by using the augmented routing policy.
7. The datanode returns the status of the upload and the gateway again translates the information without exposing any internal cluster details.

### 2.7.5.1. Setting Up a Hostmap Provider

Add the `hostmap` provider to the cluster topology descriptor and a parameter for each DataNode in the cluster, as follows:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add the Hostmap provider to `topology/gateway` using the following format:

```
<provider>
 <role>hostmap</role>
 <name>static</name>
 <enabled>true</enabled>
 <param>
 <name>$external-name</name>
 <value>$internal-dn-host</value>
 </param>
</provider>
```

where:

- `$cluster-name.xml` is the name of the topology descriptor file, located in `$gateway/conf/topologies`.
- `$external-name` is the value that the gateway uses to replace `$internal_host` host names in responses.
- `$internal-dn-host` is a comma-separated list of host names that the gateway will replace when rewriting responses.

3. To the `hostmap` provider, add a `param` for each additional DataNode in your cluster:

```
<param> <name> $external-name2 </name> <value> $internal-dn2-host </value> </param>
```

4. Save the file.

Saving the results automatically deploys the topology with the change. The result is the creation of a new WAR file with modified timestamp in `$gateway/data/deployments`.

### 2.7.5.2. Example of an EC2 Hostmap Provider

In this EC2 example two VMs have been allocated. Each VM has an external hostname by which it can be accessed via the internet. However the EC2 VM is unaware of this external host name, and instead is configured with the internal hostname.

- **External hostnames** - `ec2-23-22-31-165.compute-1.amazonaws.com`, `ec2-23-23-25-10.compute-1.amazonaws.com`
- **Internal hostnames** - `ip-10-118-99-172.ec2.internal`, `ip-10-39-107-209.ec2.internal`

The following shows the Hostmap definition required to allow access external to the Hadoop cluster via the Apache Knox Gateway.

```
<topology>
 <gateway>
 ...
 <provider>
 <role>hostmap</role>
 <name>static</name>
 <enabled>true</enabled>
 <!-- For each host enter a set of parameters -->
 <param>
 <name>ec2-23-22-31-165.compute-1.amazonaws.com</name>
 <value>ip-10-118-99-172.ec2.internal</value>
 </param>
 <param>
 <name>ec2-23-23-25-10.compute-1.amazonaws.com</name>
 <value>ip-10-39-107-209.ec2.internal</value>
 </param>
 </provider>
 ...
 </gateway>
 <service>
 ...
 </service>
 ...
</topology>
```

```
</topology>
```

### 2.7.5.3. Example of Sandbox Hostmap Provider

Hortonwork's Sandbox 2.x poses a different challenge for hostname mapping. This Sandbox version uses port mapping to make Sandbox appear as though it is accessible via localhost. However, Sandbox is internally configured to consider sandbox.hortonworks.com as the hostname. So from the perspective of a client accessing Sandbox the external host name is localhost.

The following shows the `hostmap` definition required to allow access to Sandbox from the local machine:

```
<topology>
 <gateway>
 ...
 <provider>
 <role>hostmap</role>
 <name>static</name>
 <enabled>true</enabled>
 <param>
 <name>localhost</name>
 <value>sandbox.sandbox.hortonworks.com</value>
 </param>
 </provider>
 ...
 </gateway>
...
</topology>
```

### 2.7.5.4. Enabling Hostmap Debugging



#### Warning

Changing the `rootLogger` value from `ERROR` to `DEBUG` generates a large amount of debug logging.

Enable additional logging by editing the `gateway-log4j.properties` file in the directory.

1. Edit the `$gateway /conf/gateway-log4j.properties` file to enable additional logging.
2. Change `ERROR` to `DEBUG` on the following line:

```
log4j.rootLogger=ERROR, drfa
```



#### Warning

Changing the `rootLogger` value from `ERROR` to `DEBUG` generates a large amount of debug logging.

3. Stop and then restart the gateway:

```
cd $gateway bin/gateway.sh stop bin/gateway.sh start
```

## 2.7.6. Configuring Authentication

Apache Knox Gateway supports authentication using either an LDAP or federation provider for each configured cluster. This section explains how to configure authentication:

- [Setting Up LDAP Authentication \[100\]](#)
- [LDAP Authentication Caching \[102\]](#)
- [Example Active Directory Configuration \[104\]](#)
- [Example OpenLDAP Configuration \[107\]](#)
- [Testing an LDAP Provider \[107\]](#)
- [Setting Up HTTP Header Authentication for Federation\\_SSO \[107\]](#)
- [Example SiteMinder Configuration \[109\]](#)
- [Testing HTTP Header Tokens \[109\]](#)
- [Setting Up 2-Way SSL Authentication \[109\]](#)



### Note

For information on how to configure an identity assertion provider, see [Configuring Identity Assertion](#).

### 2.7.6.1. Setting Up LDAP Authentication

LDAP authentication is configured by adding a "ShiroProvider" authentication provider to the cluster's topology file. When enabled, the Knox Gateway uses Apache Shiro (`org.apache.shiro.realm.ldap.JndiLdapRealm`) to authenticate users against the configured LDAP store.



### Note

Knox Gateway provides HTTP BASIC authentication against an LDAP user directory. It currently supports only a single Organizational Unit (OU) and does not support nested OUs.

To enable LDAP authentication:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add the ShiroProvider authentication provider to `/topology/gateway` as follows:

```
<provider>
 <role>authentication</role>
 <name>ShiroProvider</name>
 <enabled>true</enabled>
 <param>
 <name>main.ldapRealm</name>
 <value>org.apache.shiro.realm.ldap.JndiLdapRealm</value>
 <param>
 <param>
```

```
<name>main.ldapRealm.userDnTemplate</name>
<value>$USER_DN</value>
</param>
<param>
 <name>main.ldapRealm.contextFactory.url</name>
 <value>$protocol://$ldaphost:$port</value>
</param>
<param>
 <name>main.ldapRealm.contextFactory.authenticationMechanism</name>
 <value>simple</value>
</param>
<param>
 <name>urls./**</name>
 <value>$auth_type</value>
</param>
<param>
 <name>sessionTimeout</name>
 <value>$minutes</value>
</param>
</provider>
```

where:

- \$USER\_DN

is a comma-separated list of attribute and value pairs that define the User Distinguished Name (DN). The first pair must be set to " \$attribute\_name ={0}" indicating that the \$attribute\_name is equal to the user token parsed from the request. For example, the first attribute in an OpenLdap definition is UID={0}. The main.ldapRealm.userDnTemplate parameter is only required when authenticating against an LDAP store that requires a full User DN.

- \$protocol :// \$ldaphost : \$port

is the URL of the LDAP service, Knox Gateway supports LDAP or LDAPS protocols.

- \$auth\_type

is either authcBasic, which provides basic authentication for both secured and non-secured requests, or ssl authcBasic, which rejects non-secured requests and provides basic authentication of secured requests.

- \$minutes

is the session idle time in minutes, the default timeout is 30 minutes.

### 3. Save the file.

The gateway creates a new WAR file with modified timestamp in \$gateway/data/deployments.



#### Note

If the Active Directory and Kerberos names differ in case (e.g. the Active Directory name is in upper case and the Kerberos name is lower case), the Knox Gateway enables you to resolve this conflict using the auth\_to\_local flag.

You can also configure LDAP authentication over SSL by following the steps below.

1. Change the LDAP protocol from ldap :// to ldaps://.
2. If LDAP is using a self-signed certificate, then import the LDAP's certificate into the CACerts file of the Java Virtual Machine (JVM) being used to run the Apache Knox Gateway. To import the LDAP certificate, enter the following commands:

```
%JAVA_HOME%\bin\keytool
-import -trustcerts -alias ldap_ssl -file C:\temp\FileFromLDAP.cert -
keystore %JAVA_HOME%/jre/lib/security/cacerts -storepass "changeit"
```

## 2.7.6.2. LDAP Authentication Caching

You can also configure the Apache Knox Gateway to cache LDAP authentication information by leveraging built-in caching mechanisms that the Shiro EhCache Manager provides. The ability to cache LDAP authentication information is useful in eliminating the need to authenticate against the LDAP server each time you use.



### Note

When the authentication information is cached, the Knox gateway will not authenticate the user again until the cache expires.

To enable LDAP authentication caching using the Shiro Provider, follow the steps listed below.

1. Use the `org.apache.hadoop.gateway.shirorealm.knoxLdapRealm` in the Shiro configuration.
2. Set the `main.ldaprealm.authenticationcachingEnabled` property similar to the example shown below.

```
<provider>
 <role>authentication</role>
 <enabled>true</enabled>
 <param>
 <name>main.ldapRealm</name>
 <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapRealm</value>
 </param>
 <param>
 <name>main.ldapGroupContextFactory</name>
 <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapContextFactory</value>
 </param>
 <param>
 <name>main.ldapRealm.ContextFactory</name>
 <value>$ldapGroupContextFactory</value>
 </param>
 <param>
 <name>main.ldapRealm.ContextFactory.url</name>
 <value>$ldap://localhost:33389</value>
 </param>
 <param>
 <name>main.ldapRealm.authorizationEnabled</name>
 <value>true</value>
 </param>
 <param>
```

```
<name>main.ldapRealm.searchBase</name>
<value>ou-groups,dc=hadoop,dc=apache,dc=org</value>
</param>
<param>
 <name>main.cacheManager</name>
 <value>org.apache.shiro.cache.ehcache.EhCacheManager</value>
</param>
<param>
 <name>main.securityManager.cacheManager</name>
 <value>$cacheManager</value>
</param>
<param>
 <name>main.ldapRealm.authenticationCachingEnabled</name>
 <value>true</value>
</param>
<param>
 <name>main.ldapRealm.memberAttributeValueTemplate</name>
 <value>uid={0}ou=people,dc=hadoop,dc=apache,dc=org</value>
</param>
<param>
 <name>main.ldapRealm.contextFactory.systemUsername</name>
 <value>uid=guest,ou=people,dc=hadoop,dc=apache,dc=org</value>
</param>
<param>
 <name>main.ldapRealm.contextFactory.systemPassword</name>
 <value>guest=password</value>
</param>
<param>
 <name>urls./**</name>
 <value>authBasic</value>
</param>
</provider>
```

In this example, you need to configure these properties to set the Knox Gateway for LDAP authentication caching. The Knox Gateway also includes several template topology files that you can use to test the caching function. You can locate these template files in the templates directory. To test the caching function, perform the steps listed below.

- a. Navigate to the Knox gateway HOME directory.

```
cd {GATEWAY_HOME}
```

- b. Copy the templates files to your sandbox.

```
cp templates/sandbox.knoxrealm.ehcache.xml
conf.topologies/sandbox.xml
```

- c. Start the LDAP authentication provider.

```
bin/ldap.sh start
```

- d. Start the Knox gateway.

```
bin/gateway.sh start
```

- e. Once the gateway is started, make the following WebHDFS API call:

```
curl -ivk -u tom:tom-password -X GET
https://localhost:8443/gateway/sandbox/webhdfs/v1?op=GETHOMEDIRECTORY
```

- f. To see LDAP authentication caching working, shut down the LDAP authentication provider.

```
bin/ldap.sh stop
```

- g. Run the WebHDFS API call again.

```
curl -ivk -u tom:tom=password -X GET
https://localhost:8443/gateway/sandbox/webhdfs/v1?op=GETHOMEDIRECTORY
```

### 2.7.6.3. Example Active Directory Configuration

Typically the AD main.ldapRealm.userDnTemplate value looks slightly different than OpenLDAP. The value for main.ldapRealm.userDnTemplate is only required if AD authentication requires the full User DN.



#### Note

If Active Directory allows authentication based on the Common Name (CN) and password only, then no value will be required for main.ldapRealm.userDnTemplate.

```
<topology>

 <gateway>

 <provider>
 <role>authentication</role>
 <name>ShiroProvider</name>
 <enabled>true</enabled>
 <param>
 <name>sessionTimeout</name>
 <value>30</value>
 </param>
 <param>
 <name>main.ldapRealm</name>
 <value>org.apache.hadoop.gateway.shirorealm.
KnoxLdapRealm</value>
 </param>

 <!-- changes for AD/user sync -->

 <param>
 <name>main.ldapContextFactory</name>
 <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapContextFactory</value>
 </param>

 <!-- main.ldapRealm.contextFactory needs to be placed before other main.
ldapRealm.contextFactory* entries -->
 <param>
 <name>main.ldapRealm.contextFactory</name>
 <value>$ldapContextFactory</value>
 </param>

 <!-- AD url -->
 <param>
 <name>main.ldapRealm.contextFactory.url</name>
```

```
 <value>ldap://ad01.lab.hortonworks.net:389</value>
</param>

<!-- system user -->
<param>
 <name>main.ldapRealm.contextFactory.systemUsername</name>
 <value>cn=ldap-reader,ou=ServiceUsers,dc=lab,dc=hortonworks,dc=net</value>
</param>

<!-- pass in the password using the alias created earlier -->
<param>
 <name>main.ldapRealm.contextFactory.systemPassword</name>
 <value>${ALIAS=knoxLdapSystemPassword}</value>
</param>

 <param>
 <name>main.ldapRealm.contextFactory.
authenticationMechanism</name>
 <value>simple</value>
 </param>
 <param>
 <name>urls./**</name>
 <value>authcBasic</value>
 </param>

<!-- AD groups of users to allow -->
<param>
 <name>main.ldapRealm.searchBase</name>
 <value>ou=CorpUsers,dc=lab,dc=hortonworks,dc=net</value>
</param>
<param>
 <name>main.ldapRealm.userObjectClass</name>
 <value>person</value>
</param>
<param>
 <name>main.ldapRealm.userSearchAttributeName</name>
 <value>sAMAccountName</value>
</param>

<!-- changes needed for group sync-->
<param>
 <name>main.ldapRealm.authorizationEnabled</name>
 <value>true</value>
</param>
<param>
 <name>main.ldapRealm.groupSearchBase</name>
 <value>ou=CorpUsers,dc=lab,dc=hortonworks,dc=net</value>
</param>
<param>
 <name>main.ldapRealm.groupObjectClass</name>
 <value>group</value>
</param>
<param>
 <name>main.ldapRealm.groupIdAttribute</name>
 <value>cn</value>
</param>

 </provider>
```

```
<provider>
 <role>identity-assertion</role>
 <name>Default</name>
 <enabled>true</enabled>
</provider>

<provider>
 <role>authorization</role>
 <name>XASecurePDPKnox</name>
 <enabled>true</enabled>
</provider>

</gateway>

<service>
 <role>NAMENODE</role>
 <url>hdfs://{{namenode_host}}:{{namenode_rpc_port}}</url>
</service>

<service>
 <role>JOBTRACKER</role>
 <url>rpc://{{rm_host}}:{{jt_rpc_port}}</url>
</service>

<service>
 <role>WEBHDFS</role>
 <url>http://{{namenode_host}}:{{namenode_http_port}}/webhdfs</
url>
</service>

<service>
 <role>WEBHCAT</role>
 <url>http://{{webhcatt_server_host}}:{{templeton_port}}/
templeton</url>
</service>

<service>
 <role>OOZIE</role>
 <url>http://{{oozie_server_host}}:{{oozie_server_port}}/
oozie</url>
</service>

<service>
 <role>WEBHBASE</role>
 <url>http://{{hbase_master_host}}:{{hbase_master_port}}</url>
</service>

<service>
 <role>HIVE</role>
 <url>http://{{hive_server_host}}:{{hive_http_port}}/
{{hive_http_path}}</url>
</service>

<service>
 <role>RESOURCEMANAGER</role>
 <url>http://{{rm_host}}:{{rm_port}}/ws</url>
</service>
</topology>
```

## 2.7.6.4. Example OpenLDAP Configuration

```
<provider>
 <role>authentication</role>
 <name>ShiroProvider</name>
 <enabled>true</enabled>
 <param>
 <name>main.ldapRealm</name>
 <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapRealm</value>
 </param>
 <param>
 <name>main.ldapContextFactory</name>
 <value>org.apache.hadoop.gateway.shirorealm.KnoxLdapContextFactory</
value>
 </param>
 <param>
 <name>mainLdapRealm.contextFactory</name>
 <value>$ldapContextFactory</value>
 </param>
</provider>
```

## 2.7.6.5. Testing an LDAP Provider

Using cURL, you can test your LDAP configuration as follows:

1. Open the command line on an external client.



### Note

cURL is not a built-in command line utility in Windows.

2. Enter the following command to list the contents of the directory `tmp/test`:

```
curl -i -k -u ldap_user : password -X GET / 'https:// gateway_host :8443/
 gateway_path / cluster_name /webhdfs/api/v1/tmp/test?op=LISTSTATUS'
```

If the directory exists, a content list displays; if the user cannot be authenticated, the request is rejected with an HTTP status of **401 unauthorized**.

## 2.7.6.6. Setting Up HTTP Header Authentication for Federation\_SSO

The Knox Gateway supports federation solution providers by accepting HTTP header tokens. This section explains how to configure HTTP header fields for SSO or Federation solutions that have simple HTTP header-type tokens. For further information, see the [Authentication](#) chapter of the Apache Knox 0.6.0 User's Guide.

The gateway extracts the user identifier from the HTTP header field. The gateway can also extract the group information and propagate it to the Identity-Assertion provider.



### Important

The Knox Gateway federation plug-in, `HeaderPreAuth`, trusts that the content provided in the authenticated header is valid. Using this provider requires proper network security.

Only use the HeaderPreAuth federation provider in environments where the identity system does not allow direct access to the Knox Gateway. Allowing direct access exposes the gateway to identity spoofing. Hortonworks recommends defining the preauth.ip.addresses parameter to ensure requests come from a specific IP addresses only.

To configure the HTTP header tokens:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a HeaderPreAuth federation provider to `topology/gateway` as follows:

```
<provider>
 <role>federation</role>
 <name>HeaderPreAuth</name>
 <enabled>true</enabled>
 <param>
 <name>preauth.validation.method</name>
 <value>$validation_type</value>
 </param>
 <param>
 <name>preauth.ip.addresses</name>
 <value>$trusted_ip</value>
 </param>
 <param>
 <name>preauth.custom.header</name>
 <value>$user_field</value>
 </param>
 <param>
 <name>preauth.custom.group.header</name>
 <value>$group_field</value>
 </param>
</provider>
```

where the values of the parameters are specific to your environment:

- `$validation_type` (Optional, recommended)

Indicates the type of trust, use either `preauth.ip.validation` indicating to trust only connections from the address defined in `preauth.ip.addresses` OR null (omitted) indicating to trust all IP addresses.

- `$trusted_ip` (Required when the pre-authentication method is set to `preauth.ip.validation`)

A comma-separated list of IP addresses, addresses may contain a wild card to indicate a subnet, such as `10.0.0.*`.

- `$user_field`

The name of the field in the header that contains the user name that the gateway extracts. Any incoming request that is missing the field is refused with **HTTP status 401, unauthorized**. If not otherwise specified, the default value is `SM_USER`.

- `$group_field` (Optional)

The name of the field in the header that contains the group name that the gateway extracts. Any incoming request that is missing the field results in no group name being extracted and the connection is allowed.

### 3. Save the file.

The gateway creates a new WAR file with modified timestamp in \$gateway/data/deployments.

## 2.7.6.7. Example SiteMinder Configuration

The following example is the bare minimum configuration for SiteMinder (with no IP address validation):

```
<provider>
 <role>federation</role>
 <name>HeaderPreAuth</name>
 <enabled>true</enabled>
 <param>
 <name>preatuh.custom.header</name>
 <value>SM_USER</value>
 </param>
 <param>
 <name>preatuh.ip.addresses</name>
 <value>10.10.0.*</value>
 </param>
</provider>
```

## 2.7.6.8. Testing HTTP Header Tokens

Use following cURL command to request a directory listing from HDFS while passing in the expected header SM\_USER, note that the example is specific to sandbox:

```
curl -k -i --header "SM_USER: guest" -v 'https://localhost:8443/gateway/sandbox/webhdfs/v1/tmp?op=LISTSTATUS'
```

Omitting the SM\_USER: guest--header: guest" above results in a **HTTP status 401 unauthorized**

## 2.7.6.9. Setting Up 2-Way SSL Authentication

Mutual authentication with SSL provides the Knox gateway with the means to establish a strong trust relationship with another party. This is especially useful when applications that act on behalf of end-users send requests to Knox. While this feature does establish an authenticated trust relationship with the client application, it does not determine the end-user identity through this authentication. It will continue to look for credentials or tokens that represent the end-user within the request and authenticate or federate the identity accordingly.

To configure your Knox Gateway for 2-way SSL authentication, you must first configure the trust related elements within gateway-site.xml file. The table below lists the different elements that you can configure related to 2-way mutual authentication. Use following cURL command to request a directory listing from HDFS while passing in the expected header SM\_USER, note that the example is specific to sandbox:

**Table 2.22. gateway-site.xml Configuration Elements**

Name	Description	Possible Values	Default Value
gateway.client.auth.needed	Flag used to specify whether authentication is required for client communications to the server.	TRUE/FALSE	FALSE
gateway.truststore.path	The fully-qualified path to the truststore that will be used.		gateway.jks
gateway.truststore.type	The type of keystore used for the truststore.		JKS
gateway.trust.allcerts	Flag used to specify whether certificates passed by the client should be automatically trusted.	TRUE/FALSE	FALSE

Once you have configured the `gateway-site.xml` file, all topologies deployed within the Knox gateway with mutual authentication enabled will require all incoming connections to present trusted client certificates during the SSL handshake process; otherwise, the server will refuse the connection request.

## 2.7.7. Configuring Identity Assertion

The Knox Gateway `identity-assertion` provider maps an authenticated user to an internal cluster user and/or group. This allows the Knox Gateway accept requests from external users without requiring internal cluster user names to be exposed.

The gateway evaluates the authenticated user against the `identity-assertion` provider to determine the following:

1. Does the user match any user mapping rules:
  - **True:** The first matching `$cluster_user` is asserted, that is it becomes the authenticated user.
  - **False:** The authenticated user is asserted.
2. Does the authenticated user match any group mapping rules:
  - **True:** The authenticated user is a member of all matching groups (for the purpose of authorization).
  - **False:** The authenticated user is not a member of any mapped groups.



### Note

When authenticated by an SSO provider, the authenticated user is a member of all groups defined in the request as well as any that match the `group.principal.mapping`.

#### 2.7.7.1. Structure of the Identity-Assertion Provider

All cluster topology descriptors must contain a `identity-assertion` provider in the `topology/gateway` definition.

The following is the complete structure of the identity-assertion provider. The parameters are optional.

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
 <param>
 <name>principal.mapping</name>
 <value> $user_ids = $cluster_user [; $user_ids = $cluster_user1 ; ...]</value>
 </param>
 <param>
 <name>group.principal.mapping</name>
 <value> $cluster_users = $group1 ; $cluster_users = $group2 </value>
 </param>
</provider>
```

where:

- \$user\_ids is a comma-separated list of external users or the wildcard (\*) indicates all users.
- \$cluster\_user is the Hadoop cluster user name the gateway asserts, that is the authenticated user name.



### Note

Note that identity-assertion rules are not required; however, whenever an authentication provider is configured an identity-assertion provider is also required.

#### 2.7.7.2. Define Pseudo Identity Assertion

When you define the Pseudo identity-assertion provider without parameters, the authenticated user is asserted as the authenticated user. For example, using simple assertion if a user authenticates as "guest", the user's identity for grouping, authorization, and running the request is "guest".

To define a basic identity-assertion provider:

1. Open the cluster topology descriptor file, \$cluster-name.xml, in a text editor.
2. Add a Pseudoidentity-assertion provider to topology/gateway as follows:

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
</provider>

<provider> <role>identity-assertion</role> <name>Pseudo</name>
<enabled>true</enabled> </provider>
```

3. Save the file.

The gateway creates a new WAR file with modified timestamp in \$gateway/data/deployments.

### 2.7.7.3. Mapping Authenticated User to Cluster

The `principal.mapping` parameter of an identity-assertion provider determines the user name that the gateway asserts (uses as the authenticated user) for grouping, authorization, and to run the request on the cluster.



#### Note

If a user does not match a principal mapping definition, the authenticated user becomes the effective user.

To add user mapping rule to an identity-assertion provider:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a Pseudo identity-assertion provider to `topology/gateway` with the `principal.mapping` parameter as follows:

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
 <param>
 <name>principal.mapping</name>
 <value>$user_ids=$cluster_user;$user_ids=$cluster_user1;...</value>
 </param>
</provider>
```

where the value contains a semi-colon-separated list of external to internal user mappings, and the following variables match the names in your environment:

- `$user_ids`

is a comma-separated list of external users or the wildcard (\*) indicates all users.

- `$cluster_user`

is the Hadoop cluster user name the gateway asserts, that is the authenticated user name.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

#### 2.7.7.3.1. Principal Mapping Enhancements

Concat Identity Assertion is a new provider for the Knox Gateway that enables you to map principals by concatenating strings to either the front or the back of a specified username. The Identity Assertion Provider provides the critical function of determining the Identity Principal that you will want to use in your Hadoop cluster to represent the identity that has been authenticated at the gateway. For more information on the Identity Assertion Provider and how it is used in the Knox Gateway, refer to the Identity Assertion chapter in the Apache Knox 0.6.x User Guide. If you would like to convert the user principal into a

value that represents an identity from a particular user domain, use a configuration similar to the below example.

```
<provider>
 <role>identity-assertion</role>
 <name>Concat</name>
 <enabled>true</enabled>
 <param>
 <name>concat.suffix</name>
 <value>domain1</value>
 </param>
</provider>
```

Notice in this example that the `identity-assertion` role has been named `Concat` and has been enabled (true) for the Identity Assertion Provider, with the `concat.suffix` parameter given a value of `domain1` and concatenation will occur at the end of the username (`concat.suffix`). You may also use a parameter called `concat.prefix` to indicate a value to concatenate to the front of the username.

#### 2.7.7.4. Example User Mapping

The gateway evaluates the list in order, from left to right; therefore a user matching multiple entries, resolves to the first matching instance.

In the following example, when a user authenticates as, the gateway asserts the user and all other users as:

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
 <param>
 <name>principal.mapping</name>
 <value>guest=sam</value>
 </param>
</provider>
```

The following example shows how to map multiple users to different cluster accounts:

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
 <param>
 <name>principal.mapping</name>
 <value>guest,joe,brenda,administrator=same;janet,adam,sue-dwayne</
value>
 </param>
</provider>
```

#### 2.7.7.5. Mapping Authenticated Users to Groups

The Knox Gateway uses group membership for Service Level Authorization only. The gateway does not propagate the user's group when communicating with the Hadoop cluster.

The `group.principal.mapping` parameter of the `identity-assertion` provider determines the user's group membership. The gateway evaluates this parameter

after the `principal.mapping` parameter using the authenticated user. Unlike `principal.mapping`, the group mapping applies all the matching values. A user is a member of all matching groups.



### Note

Although user and group mappings are often used together, the instructions in this section only explain how to add group mappings.

## 2.7.7.6. Configuring Group Mapping

To map authenticated users to groups:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a Pseudo identity-assertion provider to `topology/gateway` with the `group.principal.mapping` parameter as follows:

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
 <param>
 <name>group.principal.mapping</name>
 <value>$group1;$user1,$user2=$group2;$user3=$group3</value>
 </param>
</provider>
```

where:

- the value is a semi-colon-separated list of user & group mappings and the variables are specific to your environment.
- `$user1`, `$user2`, `$user3` are a comma-separated list of authenticated usernames or the wildcard (\*) indicating all users. A username can be specified only once.
- `$group1`, `$group2`, `$group3` are the names of the group that the user is in for Service Level Authorization.

3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

## 2.7.7.7. Examples of Group Mapping

```
<provider>
 <role>identity-assertion</role>
 <name>Pseudo</name>
 <enabled>true</enabled>
 <param>
 <name>principal.mapping</name>
 <value>guest,alice=hdfs;mary=hive</value>
 </param>
 <param>
```

```
<name>group.principal.mapping</name>
<value>*=users; same,dwayne,brenda-admins; joe=analysts</value>
</param>
</provider>
```

## 2.7.8. Configuring Service Level Authorization



### Note

Group membership is determined by the identity-assertion parameter `group.principal.mapping`.

Group membership is determined by the identity-assertion parameter `group.principal.mapping`.

### 2.7.8.1. Setting Up an Authorization Provider

The `ACLAUTHZ` provider determines who is able to access a service through the Knox Gateway by comparing the authenticated user, group, and originating IP address of the request to the rules defined in the authorization provider.

Configure the `AclsAuthz` provider as follows:

1. Open the cluster topology descriptor file, `$cluster-name.xml`, in a text editor.
2. Add a `AclsAuthz` authorization provider to `topology/gateway` with a parameter for each service as follows:

```
<provider>
 <role>authorization</role>
 <name>AclsAuthz</name>
 <enabled>true</enabled>
 <param>
 <name>$service_name.acl.mode</name>
 <value>$mode</value>
 </param>
 <param>
 <name>$service_Name.acl</name>
 <value>$cluster_users;$groups_field;$IP_field</value>
 </param>
 ...
</provider>
```

where:

- `$service_name` matches the name of a service element. For example, `webhdfs`.
- `$mode` determines how the identity context (the effective user, their associated groups, and the original IP address) is evaluated against the fields as follows:
  - AND specifies that the request must match an entry in all three fields of the corresponding `$service_name.acl` parameter.
  - OR specifies that the request only needs to match an entry in any field, `$users_field` OR `$groups_field`, OR `$IP_field`.



## Note

The `$service_name .acl.mode` parameter is optional. When it is not defined, the default mode is AND ; therefore requests to that service must match all three fields.

- `$cluster_users` is a comma-separated list of authenticated users. Use a wildcard (\*) to match all users.
- `$groups_field` is a comma-separated list of groups. Use a wildcard (\*) to match all groups.
- `$IP_field` is a comma-separated list of IPv4 or IPv6 addresses. An IP address in the list can contain wildcard at the end to indicate a subnet (for example: 192.168.\*). Use a wildcard (\*) to match all addresses.

### 3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.

### 2.7.8.2. Examples of Authorization

The following examples illustrate how to define authorization rule types to restrict access to requests matching:

- **Only users in a specific group and from specific IP addresses**

The following rule is restrictive. It only allows the guest user in the admin group to access WebHDFS from a system with the IP address of either 127.0.0.2 or 127.0.0.3:

```
<provider>
 <role>authorization</role>
 <name>AclsAuthz</name>
 <enabled>true</enabled>
 <param>
 <name>webhdfs.acl</name>
 <value>guest;admin;127.0.0.2,127.0.0.3</value>
 </param>
</provider>
```

When the parameter `acl.mode` is not defined the default behavior is ALL, therefore following rule is the same as the one above:

```
<provider>
 <role>authorization</role>
 <name>AclsAuthz</name>
 <enabled>true</enabled>
 <param>
 <name>webhdfs.acl.mode</name>
 <value>AND</value>
 </param>
 <param>
 <name>webhdfs.acl</name>
 <value>guest;admin;127.0.0.2,127.0.0.3</value>
 </param>
</provider>
```

```
</param>
</provider>
```



## Note

If Guest is not in the admin group, the request is denied.

- **Two of the three conditions**

The following rule demonstrates how to require two conditions, user and group but not IP address, using the Wildcard. The rule allows the guest user that belongs to the admin group to send requests from anywhere because the IP field contains an asterisk which matches all IP addresses:

```
<provider>
 <role>authorization</role>
 <name>AclsAuthz</name>
 <enabled>true</enabled>
 <param>
 <name>webhdfs.acl</name>
 <value>guest;admin;*</value>
 </param>
</provider>
```

- **One of the three conditions**

When the \$service .acl.mode parameter is set to OR, the request only needs to match one entry in any of the fields. The request fails with HTTP Status 403 unauthorized, if no conditions are met.

The following example allows:

- guest to send requests to WebHDFS from anywhere.
- Any user in the admin group to send requests to WebHDFS from anywhere.
- Any user, in any group, to send a request to WebHDFS from 127.0.0.2 or 127.0.0.3.

```
<provider>
 <role>authorization</role>
 <name>AclsAuthz</name>
 <enabled>true</enabled>
 <param>
 <name>webhdfs.acl.mode</name>
 <value>OR</value>
 </param>
 <param>
 <name>webhdfs.acl</name>
 <value>guest;admin;127.0.0.2,127.0.0.3</value>
 </param>
</provider>
```

- **Allow all requests**

The following rule grants all users, in any group, and from any IP addresses to access WebHDFS:



### Note

When a wildcard is used in a field it matches any value. Therefore the Allow all requests example is the same as not defining an ACL.

```
<provider>
 <role>authorization</role>
 <name>AclsAuthz</name>
 <enabled>true</enabled>
 <param>
 <name>webhdfs.acl</name>
 <value>*,*,*</value>
 </param>
</provider>
```

## 2.7.9. Audit Gateway Activity

The Knox Gateway Audit Facility tracks actions that are executed by Knox Gateway per user request or that are produced by Knox Gateway internal events, such as topology deployments.



### Tip

The Knox Audit module is based on the Apache log4j. You can customize the logger by changing the `log4j.appender.auditfile.Layout` property in `$gateway/conf/gateway-log4j.properties` to another class that extends Log4j. For detailed information see [Apache's log4j](#).

### 2.7.9.1. Audit Log Fields

Auditing events on the gateway are informational, the default auditing level is informational (INFO) and it cannot be changed.

The Audit logs located at `C:/hadoop/logs/knox/gateway-audit.log` have the following structure:

`EVENT_PUBLISHING_TIMEROOT_REQUEST_ID | PARENT_REQUEST_ID | REQUEST_ID  
| LOGGER_NAME | TARGET_SERVICE_NAME | USER_NAME | PROXY_USER_NAME |  
SYSTEM_USER_NAME | ACTION | RESOURCE_TYPE | RESOURCE_NAME | OUTCOME |  
LOGGING_MESSAGE`

where:

- `EVENT_PUBLISHING_TIME` : contains the timestamp when record was written.
- `ROOT_REQUEST_ID` : Reserved, the field is empty.
- `PARENT_REQUEST_ID` : Reserved, the field is empty.
- `REQUEST_ID` : contains a unique value representing the request.
- `LOGGER_NAME` : contains the logger name. For example `audit`.

- TARGET\_SERVICE\_NAME : contains the name of Hadoop service. Empty indicates that the audit record is not linked to a Hadoop service. For example, an audit record for topology deployment.
- USER\_NAME : contains the ID of the user who initiated session with Knox Gateway.
- PROXY\_USER\_NAME : contains the authenticated user name.
- SYSTEM\_USER\_NAME : Reserved, field is empty.
- ACTION : contains the executed action type. The value is either authentication, authorization, redeploy, deploy, undeploy, identity-mapping, dispatch, or access.
- RESOURCE\_TYPE contains the resource type of the action. The value is either uri, topology, or principal.
- RESOURCE\_NAME : contains the process name of the resource. For example, topology shows the inbound or dispatch request path and principal shows the name of mapped user.
- OUTCOME contains the action results, success, failure, or unavailable.
- LOGGING\_MESSAGE contains additional tracking information, such as the HTTP status code.

### 2.7.9.2. Change Roll Frequency of the Audit Log

Audit records are written to the log file `/var/log/knox/gateway-audit.log` and by default roll monthly. When the log rolls, the date that it rolled is appended to the end of the current log file and a new one is created.

To change the frequency:

1. Open the `$gateway /conf/gateway-log4j.properties` file in a text editor.
2. Change the `log4j.appenders.auditfile.DatePattern` as follows:

```
log4j.appenders.auditfile.DatePattern = $interval
```

where `$interval` is one of the following:

Setting	Description
yyyy-MM	Rollover at the beginning of each month
yyyy-ww	Rollover at the first day of each week. The first day of the week depends on the locale.
yyyy-MM-dd	Rollover at midnight each day.
yyyy-MM-dd-a	Rollover at midnight and midday of each day.
yyyy-MM-dd-HH	Rollover at the top of every hour.
yyyy-MM-dd-HH-mm	Rollover at the beginning of every minute.



#### Tip

For more examples, see [Apache log4j: Class DailyRollingFileAppender](#).

3. Save the file.

#### 4. Restart the gateway:

```
cd $gateway bin/gateway.sh stop bin/gateway.sh start
```

## 2.7.10. Gateway Security

The Knox Gateway offers the following security features:

- [Implementing Web Application Security \[120\]](#)
- [Configuring Knox With a Secured Hadoop Cluster \[122\]](#)

### 2.7.10.1. Implementing Web Application Security

The Knox Gateway is a Web API (REST) Gateway for Hadoop clusters. REST interactions are HTTP based, and therefore the interactions are vulnerable to a number of web application security vulnerabilities. The web application security provider allows you to configure protection filter plugins.



#### Note

The initial vulnerability protection filter is for Cross Site Request Forgery (CSRF). Others will be added in future releases.

### 2.7.10.2. Configuring Protection Filter Against Cross Site Request Forgery Attacks

A Cross Site Request Forgery (CSRF) attack attempts to force a user to execute functionality without their knowledge. Typically the attack is initiated by presenting the user with a link or image that when clicked invokes a request to another site with which the user already has an established an active session. CSRF is typically a browser based attack.

The only way to create a HTTP request from a browser is with a custom HTTP header is to use Javascript XMLHttpRequest or Flash, etc. Browsers have built-in security that prevent web sites from sending requests to each other unless specifically allowed by policy. This means that a website www.bad.com cannot send a request to http://bank.example.com with the custom header X-XSRF-Header unless they use a technology such as a XMLHttpRequest. That technology would prevent such a request from being made unless the bank.example.com domain specifically allowed it. This then results in a REST endpoint that can only be called via XMLHttpRequest (or similar technology).



#### Note

After enabling CSRF protection within the gateway, a custom header is required for all clients that interact with it, not just browsers.

To add a CSRF protection filter:

1. Open the cluster topology descriptor file, `$cluster-name .xml`, in a text editor.
2. Add a `WebAppSec` `webappsec` provider to `topology/gateway` with a parameter for each service as follows:

```
<provider>
```

```
<role>webappsec</role>
<name>WebAppSec</name>
<enabled>true</enabled>
<param>
 <name>csrf.enabled</name>
 <value>$csrf_enabled</value>
</param>
<param><!-- Optional -->
 <name>csrf.customHeader</name>
 <value>$header_name</value>
</param>
<param><!-- Optional -->
 <name>csrf.methodsToIgnore</name>
 <value>$HTTP_methods</value>
</param>
</provider>
```

where:

- \$csrf\_enabled is either true or false.
- \$header\_name when the optional parameter csrf.customHeader is present the value contains the name of the header that determines if the request is from a trusted source. The default, X-XSRF-Header, is described by the NSA in its guidelines for dealing with CSRF in REST.

\$HTTP\_methods when the optional parameter csrf.methodsToIgnore is present the value enumerates the HTTP methods to allow without the custom HTTP header. The possible values are GET, HEAD, POST, PUT, DELETE, TRACE, OPTIONS, CONNECT, or PATCH. For example, specifying GET allows GET requests from the address bar of a browser. Only specify methods that adhere to REST principals in terms of being idempotent.

### 3. Save the file.

The gateway creates a new WAR file with modified timestamp in `$gateway/data/deployments`.



#### Note

Make sure you have properly set your \$JAVA\_HOME variable in your user environment; otherwise, Java will be used.

### 2.7.10.3. Validate CSRF Filtering

The following curl command can be used to request a directory listing from HDFS while passing in the expected header X-XSRF-Header.

```
curl -k -i --header "X-XSRF-Header: valid" -v -u guest:guest-password https://localhost:8443/gateway/sandbox/webhdfs/v1/tmp?op=LISTSTATUS
```



#### Note

The above LISTSTATUS request only works if you remove the GET method from the csrf.methodsToIgnore list.

Omitting the `-header "X-XSRF-Header: valid"` above results in an **HTTP 400 bad\_request**. Disabling the provider, by setting `csrf.enabled` to false allows a request that is missing the header.

## 2.7.10.4. Configuring Knox With a Secured Hadoop Cluster

Once you have a Hadoop cluster that uses Kerberos for authentication, you must configure Knox to work with that cluster.

To enable the Knox Gateway to interact with a Kerberos-protected Hadoop cluster, add a `knox` user and Knox Gateway properties to the cluster.

Do the following:

1. Find the fully-qualified domain name of the host running the gateway:

```
hostname -f
```

If the Knox host does not have a static IP address, you can define the `knox` host as `*` for local developer testing.

2. At every Hadoop Master:

- Create a UNIX account for Knox:

```
useradd -g hadoop knox
```

- Edit `core-site.xml` to include the following lines (near the end of the file):

```
<property>
 <name>hadoop.proxyuser.knox.groups</name>
 <value>users</value>
</property>

<property>
 <name>hadoop.proxyuser.knox.hosts</name>
 <value>$knox-host</value>
</property>
```

where `$knox-host` is the fully-qualified domain name of the host running the gateway.

- Edit `webhcat-site.xml` to include the following lines (near the end of the file):

```
<property>
 <name>hadoop.proxyuser.knox.groups</name>
 <value>users</value>
</property>

<property>
 <name>hadoop.proxyuser.knox.hosts</name>
 <value>$knox-host</value>
</property>
```

where `$knox_host` is the fully-qualified domain name of the host running the gateway.

3. At the Oozie host, edit `oozie-site.xml` to include the following lines (near the end of the file):

```
<property>
 <name>oozie.service.ProxyUserService.proxyuser.knox.groups</name>
 <value>users</value>
</property>

<property>
 <name>oozie.service.ProxyUserService.proxyuser.knox.hosts</name>
 <value>$knox-host</value>
</property>
```

where `$knox-host` is the fully-qualified domain name of the host running the gateway.

4. At each node running HiveServer2, edit `hive-site.xml` to include the following properties and values:

```
<property>
 <name>hive.server2.enable.doAs</name>
 <value>true</value>
</property>

<property>
 <name>hive.server2.allow.user.substitution</name>
 <value>true</value>
</property>

<property>
 <name>hive.server2.transport.mode</name>
 <value>http</value>
 <description>Server transport mode. "binary" or "http".</description>
</property>

<property>
 <name>hive.server2.thrift.http.port</name>
 <value>10001</value>
 <description>Port number when in HTTP mode.</description>
</property>

<property>
 <name>hive.server2.thrift.http.path</name>
 <value>cliservice</value>
 <description>Path component of URL endpoint when in HTTP mode.</description>
</property>
```

## 2.7.11. Setting Up Knox for WebHDFS HA

This chapter describes how to set up the Knox Gateway for WebHDFS HA (high availability).

To set up Knox for WebHDFS HA:

1. [Configure WebHDFS for Knox \[124\]](#)
2. [Configure Knox for WebHDFS HA \[124\]](#)

## 2.7.11.1. Configure WebHDFS for Knox

REST API access to HDFS in a Hadoop cluster is provided by [WebHDFS](#). The [WebHDFS REST API](#) documentation is available online. The following properties for Knox WebHDFS must be enabled in the `/etc/hadoop/conf/hdfs-site.xml` configuration file. The example values shown in these properties are from an installed instance of the Hortonworks Sandbox.

```
<property>
 <name>dfs.webhdfs.enabled</name>
 <value>true</value>
</property>
<property>
 <name>dfs.namenode.rpc-address</name>
 <value>sandbox.hortonworks.com:8020</value>
</property>
<property>
 <name>dfs.namenode.http-address</name>
 <value>sandbox.hortonworks.com:50070</value>
</property>
<property>
 <name>dfs.https.namenode.https-address</name>
 <value>sandbox.hortonworks.com:50470</value>
</property>
```

The values above must be reflected in each topology descriptor file deployed to the gateway. The gateway by default includes a sample topology descriptor file located at `{GATEWAY_HOME}/deployments/sandbox.xml`. The values in the following sample are also configured to work with an installed Hortonworks Sandbox VM.

```
<service>
 <role>NAMENODE</role>
 <url>hdfs://localhost:8020</url>
</service>
<service>
 <role>WEBHDFS</role>
 <url>http://localhost:50070/webhdfs</url>
</service>
```

The URL provided for the NAMENODE role does not result in an endpoint being exposed by the gateway. This information is only required so that other URLs can be rewritten that reference the Name Node's RPC address. This prevents clients from needing to be aware of the internal cluster details.

## 2.7.11.2. Configure Knox for WebHDFS HA



### Important

Before you can configure the Knox Gateway for WebHDFS HA (high availability), you must first [configure WebHDFS for Knox](#).

Knox provides basic failover and retry functionality for REST API calls made to WebHDFS when HDFS HA has been configured and enabled.

To enable HA functionality for WebHDFS in Knox the following configuration must be added to the topology file.

```
<provider>
 <role>ha</role>
 <name>HaProvider</name>
 <enabled>true</enabled>
 <param>
 <name>WEBHDFS</name>
 <value>maxFailoverAttempts=3;failoverSleep=1000;maxRetryAttempts=
300;retrySleep=1000;enabled=true</value>
 </param>
</provider>
```

The `<role>` and `<name>` of the provider must be as shown above. The `<name>` in the `<param>` section must match that of the service role name that is being configured for HA, and the `<value>` in the `<param>` section is the configuration for that particular service in HA mode. In this case the `<name>` is WEBHDFS.

The various configuration parameters are described below:

- `maxFailoverAttempts` – The maximum number of times a failover will be attempted. The current failover strategy is very simplistic in that the next URL in the list of URLs provided for the service is used, and the one that failed is put at the bottom of the list. If the list is exhausted and the maximum number of attempts has not been reached, the first URL that failed will be tried again (the list will start again from the original top entry).
- `failoverSleep` – The amount of time in milliseconds that the process will wait or sleep before attempting to failover.
- `maxRetryAttempts` – The maximum number of times that a retry request will be attempted. Unlike failover, the retry is done on the same URL that failed. This is a special case in HDFS when the node is in safe mode. The expectation is that the node will come out of safe mode, so a retry is desirable here as opposed to a failover.
- `retrySleep` – The amount of time in milliseconds that the process will wait or sleep before a retry is issued.
- `enabled` - Flag to turn the particular service on or off for HA.

For the service configuration itself, the additional URLs for standby nodes should be added to the list. The active URL (at the time of configuration) should ideally be added at the top of the list. For example:

```
<service>
 <role>WEBHDFS</role>
 <url>http://{host1}:50070/webhdfs</url>
 <url>http://{host2}:50070/webhdfs</url>
</service>
```

## 2.7.12. Knox CLI Testing Tools

This chapter describes how to use the Knox CLI (Command Line Interface) to run diagnostic tests.

The Knox CLI is a command line utility that can be used to manage and test various aspects of a Knox deployment.

The `knoxcli.sh` command line utility script is located in the `{GATEWAY_HOME}/bin` directory.

### 2.7.12.1. Knox CLI LDAP Authentication and Authorization Testing

You can use the following command format to authenticate a user name and password against LDAP.

```
bin/knoxcli.sh user-auth-test [--cluster c] [--u username] [--p password] [--g] [--d] [--help]
```

This command will test a topology's ability to connect, authenticate, and authorize a user with an LDAP server. The only required argument is the `--cluster` argument to specify the name of the topology you wish to use. The topology must be valid (passes a validate-topology command). If the `-u` and `-p` arguments are not specified, you will be prompted for a user name and password.

If authentication is successful, the command will attempt to use the topology to do an LDAP group lookup. The topology must be configured correctly to do this. If it is not, groups will not be returned and no errors will be printed unless the `--g` argument is specified. Currently this command only works if a topology supports the use of ShiroProvider for authentication.

**Table 2.23. LDAP Authentication and Authorization Arguments**

Argument	Description	Required?
<code>--cluster</code>	The name of the cluster to authenticate.	Yes
<code>-u</code>	The user name to authenticate with.	No
<code>-p</code>	The password to authenticate with.	No
<code>-g</code>	Specifies that you want to return a user's groups. If not specified, group lookup errors will not be returned.	No
<code>-d</code>	Print extra debug information for a failed authentication.	No

# 3. Configuring Authorization in Hadoop

## 3.1. Installing Ranger Using Ambari

### 3.1.1. Overview

Apache Ranger can be installed either manually using the Hortonworks Data Platform (HDP) or the Ambari 2.1 User Interface (UI). Unlike the manual installation process, which requires you to perform a number of installation steps, installing Ranger using the Ambari UI is simpler and easier. The Ranger service option will be made available through the Add Service wizard after the HDP cluster is installed using the installation wizard.

Once Ambari has been installed and configured, you can use the Add Service wizard to install the following components:

- Ranger Admin
- Ranger UserSync
- [Ranger Key Management Service](#)

After these components are installed and started, you can enable Ranger plugins by navigating to each individual Ranger service (HDFS, HBase, HiveServer2, Storm, Knox, YARN, and Kafka) and modifying the configuration under *advanced ranger-<service>-plugin-properties*.

Note that when you enable a Ranger plugin, you will need to restart the component.



#### Note

Enabling Apache Storm or Apache Kafka requires you to enable Kerberos. To enable Kerberos on your cluster, see [Enabling Kerberos Authentication Using Ambari](#).

### 3.1.2. Installation Prerequisites

Before you install Ranger, make sure your cluster meets the following requirements:

- It is recommended that you store audits in both HDFS and Solr, so you should [install Apache Solr](#).
- To ensure that LDAP/AD group level authorization is enforced in Hadoop, you should [set up Hadoop group mapping](#) for LDAP.
- A MySQL, Oracle, or PostgreSQL database instance must be running and available to be used by Ranger.

The Ranger installation will create two new users (default names: rangeradmin and rangerlogger) and two new databases (default names: ranger and ranger\_audit).

- Configuration of the database instance for Ranger is described in the following sections for some of the databases supported by Ranger.
  - [Configuring MySQL for Ranger \[130\]](#)
  - [Configuring PostgreSQL for Ranger \[131\]](#)
  - [Configuring Oracle for Ranger \[132\]](#)
- If you choose not to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. You can then run the normal Ambari Ranger installation without specifying a DBA user name and password. For more information see [Setting up Database Users Without Sharing DBA Credentials](#).

### 3.1.2.1. Setting Up Hadoop Group Mapping for LDAP/AD

To ensure that LDAP/AD group level authorization is enforced in Hadoop, you should set up Hadoop group mapping for LDAP/AD.

**Prerequisites:** Access to LDAP and the connection details. Note that LDAP settings can vary depending on what LDAP implementation you are using.

There are three ways to set up Hadoop group mapping:

- [Configure Hadoop Group Mapping for LDAP/AD Using SSSD \(Recommended\) \[128\]](#)
- [Configure Hadoop Group Mapping in core-site.xml \[129\]](#)
- [Manually Create the Users and Groups in the Linux Environment \[130\]](#)

#### 3.1.2.1.1. Configure Hadoop Group Mapping for LDAP/AD Using SSSD (Recommended)

The recommended method for group mapping is to use [SSSD](#) or one of the following services to connect the Linux OS with LDAP:

- Centrify
- NSLCD
- Winbind
- SAMBA

Note that most of these services allow you to not only look up a user and enumerate their groups, but also allow you to perform other actions on the host. None of these features are required for LDAP group mapping on Hadoop – all that is required is the ability to lookup (or "validate") a user within LDAP and enumerate their groups. Therefore, when evaluating these services, take the time to understand the difference between the NSS module (which performs user/group resolution) and the PAM module (which performs user authentication). NSS is required. PAM is not required, and may represent a security risk.

### 3.1.2.1.2. Configure Hadoop Group Mapping in core-site.xml

You can use the following steps to configure Hadoop to use LDAP-based group mapping in core-site.xml.

1. Add the properties shown in the example below to the core-site.xml file. You will need to provide the value for the bind user, the bind password, and other properties specific to your LDAP instance, and make sure that object class, user, and group filters match the values specified in your LDAP instance.

```
<property>
<name>hadoop.security.group.mapping</name>
<value>org.apache.hadoop.security.LdapGroupsMapping</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.bind.user</name>
<value>cn=Manager,dc=hadoop,dc=apache,dc=org</value>
</property>

<!--
<property>
<name>hadoop.security.group.mapping.ldap.bind.password.file</name>
<value>/etc/hadoop/conf/ldap-conn-pass.txt</value>
</property>
-->

<property>
<name>hadoop.security.group.mapping.ldap.bind.password</name>
<value>hadoop</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.url</name>
<value>ldap://localhost:389/dc=hadoop,dc=apache,dc=org</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.url</name>
<value>ldap://localhost:389/dc=hadoop,dc=apache,dc=org</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.base</name>
<value></value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.search.filter.user</name>
<value>(&(|(objectclass=person)(objectclass=applicationProcess))(cn={0}))</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.search.filter.group</name>
<value>(objectclass=groupOfNames)</value>
</property>

<property>
```

```
<name>hadoop.security.group.mapping.ldap.search.attr.member</name>
<value>member</value>
</property>

<property>
<name>hadoop.security.group.mapping.ldap.search.attr.group.name</name>
<value>cn</value>
</property>
```

2. Depending on your configuration, you may be able to refresh user and group mappings using the following HDFS and YARN commands:

```
hdfs dfsadmin -refreshUserToGroupsMappings
yarn rmadmin -refreshUserToGroupsMappings
```

If a restart is required, you can use the applicable instructions on [this page](#) to re-start the HDFS NameNode and the YARN ResourceManager.

3. Verify LDAP group mapping by running the `hdfs groups` command. This command will fetch groups from LDAP for the current user. Note that with LDAP group mapping configured, the HDFS permissions can leverage groups defined in LDAP for access control.

### 3.1.2.1.3. Manually Create the Users and Groups in the Linux Environment

You can also [manually create users and groups](#) in your Linux environment.

### 3.1.2.2. Configuring MySQL for Ranger

1. The MySQL database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the `rangerdba` user with password `rangerdba`.

- a. Log in as the root user, then use the following commands to create the `rangerdba` user and grant it adequate privileges.

```
CREATE USER 'rangerdba'@'localhost' IDENTIFIED BY 'rangerdba';

GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'localhost';

CREATE USER 'rangerdba'@'%' IDENTIFIED BY 'rangerdba';

GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'%';

GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'localhost' WITH GRANT OPTION;

GRANT ALL PRIVILEGES ON *.* TO 'rangerdba'@'%' WITH GRANT OPTION;

FLUSH PRIVILEGES;
```

- b. Use the `exit` command to exit MySQL.
  - c. You should now be able to reconnect to the database as `rangerdba` using the following command:

```
mysql -u rangerdba -prangerdba
```

After testing the `rangerdba` login, use the `exit` command to exit MySQL.

2. Use the following command to confirm that the `mysql-connector-java.jar` file is in the Java share directory. This command must be run on the server where Ambari server is installed.

```
ls /usr/share/java/mysql-connector-java.jar
```

If the file is not in the Java share directory, use the following command to install the MySQL connector .jar file.

#### RHEL/CentOS/Oracle Linux

```
yum install mysql-connector-java*
```

#### SLES

```
zypper install mysql-connector-java*
```

3. Use the following command format to set the `jdbcdriver/path` based on the location of the MySQL JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbcdb={database-type} --jdbcdriver={/jdbcdriver/path}
```

For example:

```
ambari-server setup --jdbcdb=mysql --jdbcdriver=/usr/share/java/mysql-connector-java.jar
```

### 3.1.2.3. Configuring PostgreSQL for Ranger

1. On the PostgreSQL host, install the applicable PostgreSQL connector.

#### RHEL/CentOS/Oracle Linux

```
yum install postgresql-jdbc*
```

#### SLES

```
zypper install -y postgresql-jdbc
```

2. Confirm that the .jar file is in the Java share directory.

```
ls /usr/share/java/postgresql-jdbc.jar
```

3. Change the access mode of the .jar file to 644.

```
chmod 644 /usr/share/java/postgresql-jdbc.jar
```

4. The PostgreSQL database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the `rangerdba` user and grant it adequate privileges.

```
echo "CREATE DATABASE $dbname;" | sudo -u $postgres psql -U postgres
```

```
echo "CREATE USER $rangerdba WITH PASSWORD '$passwd' ;" | sudo -u $postgres
psql -U postgres
echo "GRANT ALL PRIVILEGES ON DATABASE $dbname TO $rangerdba;" | sudo -u
postgres psql -U $postgres
```

Where:

- \$postgres is the Postgres user.
- \$dbname is the name of your PostgreSQL database

5. Use the following command format to set the jdbc/driver/path based on the location of the PostgreSQL JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/
path}
```

For example:

```
ambari-server setup --jdbc-db=postgres --jdbc-driver=/usr/share/java/
postgresql.jar
```

6. Run the following command:

```
export HADOOP_CLASSPATH=${HADOOP_CLASSPATH}: ${JAVA_JDBC_LIBS} : /connector jar
path
```

7. Add Allow Access details for Ranger users:

- change listen\_addresses='localhost' to listen\_addresses='\*' ('\*' = any) to listen from all IPs in postgresql.conf.
- Make the following changes to the Ranger db user and Ranger audit db user in the pg\_hba.conf file.

```
TYPE DATABASE USER CIDR-ADDRESS METHOD
"local" is for Unix domain socket connections only
local all postgres,rangeradmin,rangerlogger trust
IPv4 local connections:
host all postgres,rangeradmin,rangerlogger 0.0.0.0/0 trust
IPv6 local connections:
host all postgres,rangeradmin,rangerlogger ::/0 trust
"/var/lib/pgsql/data/pg_hba.conf" 74L, 3445C
```

8. After editing the pg\_hba.conf file, run the following command to refresh the PostgreSQL database configuration:

```
sudo -u postgres /usr/bin/pg_ctl -D $PGDATA reload
```

For example, if the pg\_hba.conf file is located in the /var/lib/pgsql/data directory, the value of \$PGDATA is /var/lib/pgsql/data.

### 3.1.2.4. Configuring Oracle for Ranger

1. On the Oracle host, install the appropriate JDBC .jar file.

- Download the Oracle JDBC (OJDBC) driver from <http://www.oracle.com/technetwork/database/features/jdbc/index-091264.html>.

- For **Oracle Database 11g**: select Oracle Database 11g Release 2 drivers > ojdbc6.jar.
- For **Oracle Database 12c**: select Oracle Database 12c Release 1 driver > ojdbc7.jar.
- Copy the .jar file to the Java share directory. For example:

```
cp ojdbc7.jar /usr/share/java
```



### Note

Make sure the .jar file has the appropriate permissions. For example:

```
chmod 644 /usr/share/java/ojdbc7.jar
```

2. The Oracle database administrator should be used to create the Ranger databases.

The following series of commands could be used to create the RANGERDBA user and grant it permissions using SQL\*Plus, the Oracle database administration utility:

```
sqlplus sys/root as sysdba
CREATE USER $RANGERDBA IDENTIFIED BY $RANGERDBAPASSWORD;
GRANT SELECT_CATALOG_ROLE TO $RANGERDBA;
GRANT CONNECT, RESOURCE TO $RANGERDBA;
QUIT;
```

3. Use the following command format to set the jdbc/driver/path based on the location of the Oracle JDBC driver .jar file. This command must be run on the server where Ambari server is installed.

```
ambari-server setup --jdbc-db={database-type} --jdbc-driver={/jdbc/driver/
path}
```

For example:

```
ambari-server setup --jdbc-db=oracle --jdbc-driver=/usr/share/java/ojdbc6.
jar
```

## 3.1.3. Ranger Installation

To install Ranger using Ambari:

1. Start the Installation [ ]
2. Customize Services [138]
3. Complete the Ranger Installation [164]


### Related Topics

- [Setting up Database Users Without Sharing DBA Credentials \[168\]](#)
- [Updating Ranger Admin Passwords \[169\]](#)


### 3.1.3.1. Start the Installation

1. Log into your Ambari cluster with your designated user credentials. The main Ambari Dashboard page will be displayed.


Figure 3.1. Installing Ranger - Main Dashboard View




2. In the left navigation menu, click **Actions**, then select **Add Service**.

**Figure 3.2. Installing Ranger - Add Service**

3. On the Choose Services page, select **Ranger**, then click **Next**.

**Figure 3.3. Installing Ranger - Choose Service**

4. The Ranger Requirements page appears. Ensure that you have met all of the installation requirements, then select the "I have met all the requirements above" check box and click **Proceed**.

**Figure 3.4. Installing Ranger - Ranger Requirements**

5. You are then prompted to select the host where Ranger Admin will be installed. This host should have DB admin access to the Ranger DB host and User Sync. Notice in the figure below that both the Ranger Admin and Ranger User Sync services will be installed on the primary node in the cluster (c6401.ambari.apache.org in the example shown below).


Make a note of the Ranger Admin host for use in subsequent installation steps. Click **Next** when finished to continue with the installation.



### Note

The Ranger Admin and Ranger User Sync services must be installed on the same cluster node.

**Figure 3.5. Installing Ranger Assign Masters**



6. The Customize Services page appears. These settings are described in the next section.


### 3.1.3.2. Customize Services

The next step in the installation process is to specify Ranger settings on the Customize Services page.

- [Ranger Admin Settings \[138\]](#)
- [Ranger Audit Settings \[148\]](#)
- [Configure Ranger User Sync \[149\]](#)
- [Configure Ranger Authentication \[156\]](#)

#### 3.1.3.2.1. Ranger Admin Settings

1. On the Customize Services page, select the Ranger Admin tab, then use the **DB Flavor** drop-down to select the database type that you are using with Ranger.



2. Enter the database server address in the **Ranger DB Host** box.

**Table 3.1. Ranger DB Host**

DB Flavor	Host	Example
MySQL	<HOST[:PORT]>	c6401.ambari.apache.org or c6401.ambari.apache.org:3306
Oracle	<HOST:PORT:SID>	c6401.ambari.apache.org:1521:ORCL
	<HOST:PORT/Service>	c6401.ambari.apache.org:1521/XE
PostgreSQL	<HOST[:PORT]>	c6401.ambari.apache.org or c6401.ambari.apache.org:5432
MS SQL	<HOST[:PORT]>	c6401.ambari.apache.org

DB Flavor	Host	Example
		or c6401.ambari.apache.org:1433
SQLA	<HOST[:PORT]>	c6401.ambari.apache.org or c6401.ambari.apache.org:2638

3. **Ranger DB name** – The name of the Ranger Policy database, i.e. ranger\_db. Please note that if you are using Oracle, you must specify the Oracle tablespace name here.
4. Driver class name for a JDBC Ranger database – the driver class name is automatically generated based on the selected DB Flavor. The table below lists the default driver class settings. Currently Ranger does not support any third party JDBC driver.

**Table 3.2. Driver Class Name**

DB Flavor	Driver class name for a JDBC Ranger database
MySQL	com.mysql.jdbc.Driver
Oracle	oracle.jdbc.driver.OracleDriver
PostgreSQL	org.postgresql.Driver
MS SQL	com.microsoft.sqlserver.jdbc.SQLServerDriver
SQLA	sap.jdbc4.sqlanywhere.IDriver

5. **Ranger DB username and Ranger DB Password** – Enter the user name and passwords for your Ranger database server. The following table describes these settings in more detail. You can use the MySQL database that was installed with Ambari, or an external MySQL, Oracle, PostgreSQL, MS SQL or SQL Anywhere database.

**Table 3.3. Ranger DB Username Settings**

Property	Description	Default Value	Example Value	Required?
Ranger DB username	The username for the Policy database.	rangeradmin	rangeradmin	Yes
Ranger DB password	The password for the Ranger Policy database user.		PassWORd	Yes

## 6. JDBC connect string



### Important

Currently the Ambari installer generates the JDBC connect string using the `jdbc:oracle:thin:@//host:port/db_name` format. You must replace the connection string as described in the following table:

**Table 3.4. JDBC Connect String**

DB Flavor	Syntax	Example Value
MySQL	<code>jdbc:mysql://DB_HOST:PORT/db_name</code>	<code>jdbc:mysql://c6401.ambari.apache.org:3306/ranger_db</code>

DB Flavor	Syntax	Example Value
Oracle	<b>For Oracle SID:</b> jdbc:oracle:thin:@DB_HOST:PORT:SID	jdbc:oracle:thin:@c6401.ambari.apache.org:1521:ORCL
	<b>For Oracle Service Name:</b> jdbc:oracle:thin:@//DB_HOST[:PORT] [/ServiceName]	jdbc:oracle:thin:@//c6401.ambari.apache.org:1521/XE
PostgreSQL	jdbc:postgresql://DB_HOST/ db_name	jdbc:postgresql://c6401.ambari.apache.org:5432/ ranger_db
MS SQL	jdbc:sqlserver:// DB_HOST;databaseName=db_name	jdbc:sqlserver://c6401.ambari.apache.org:1433;databaseName=ranger_db
SQLA	jdbc:sqlanywhere:host=DB_HOST;data	jdbc:sqlanywhere:host=c6401.ambari.apache.org:2638;data

## 7. Setup Database and Database User

- If set to **Yes** – The Database Administrator (DBA) user name and password will need to be provided as described in the next step.



### Note

Ranger does not store the DBA user name and password after setup. Therefore, you can clear these values in the Ambari UI after the Ranger setup is complete.

- If set to **No** – A **No** indicates that you do not wish to provide Database Administrator (DBA) account details to the Ambari Ranger installer. Setting this to No continues the Ranger installation process without providing DBA account details. In this case, you must perform the system database user setup as described in [Setting up Database Users Without Sharing DBA Credentials](#), and then proceed with the installation.



### Note

If **No** is selected and the UI still requires you to enter a user name and password in order to proceed, you can enter any value – the values do not need to be the actual DBA user name and password.

## 8. Database Administrator (DBA) username and Database Administrator (DBA) password

The DBA username and password are set when the database server is installed. If you do not have this information, contact the database administrator who installed the database server.

**Table 3.5. DBA Credential Settings**

Property	Description	Default Value	Example Value	Required?
Database Administrator (DBA) username	The Ranger database user that has administrative privileges to create database schemas and users.	root	root	Yes
Database Administrator (DBA) password	The root password for the Ranger database user.		root	Yes

If the Oracle DB root user Role is SYSDBA, you must also specify that in the **Database Administrator (DBA) username** parameter. For example, if the DBA user name is `orcl_root` you must specify `orcl_root AS SYSDBA`.



### Note

As mentioned in the note in the previous step, if **Setup Database and Database User** is set to **No**, a placeholder DBA username and password may still be required in order to continue with the Ranger installation.

The following images show examples of the DB settings for each Ranger database type.



### Note

To test the DB settings, click **Test Connection**. If a Ranger database has not been pre-installed, **Test Connection** will fail even for a valid configuration.

## MySQL

Ranger Admin    Ranger User Info    Ranger Plugin    Ranger Audit    Advanced

## Ranger Admin

DB FLAVOR

MYSQL

Ranger DB name

ranger

Ranger DB username

rangeradmin

JDBC connect string

jdbc:mysql://c6401.ambari.apache.org/ranger

Ranger DB host

c6401.ambari.apache.org

Driver class name for a JDBC Ranger database

com.mysql.jdbc.Driver

Ranger DB password

.....

Setup Database and Database User

Yes

Database Administrator (DBA) username

root

Database Administrator (DBA) password

.....

JDBC connect string for root user

jdbc:mysql://c6401.ambari.apache.org

**Oracle** – if the Oracle instance is running with a Service name.

Ranger Admin    Ranger User Info    Ranger Plugin    Ranger Audit    Advanced

## Ranger Admin

DB FLAVOR	ORACLE	Ranger DB host
Ranger DB name	ranger	Driver class name for a JDBC Ranger database
Ranger DB username	rangeradmin	Ranger DB password
JDBC connect string	:oracle:thin:@//c6401.ambari.apache.org:1521/XE	.....

Setup Database and Database User

Yes

Database Administrator (DBA) username	SYS AS SYSDBA	Database Administrator (DBA) password
JDBC connect string for root user	jdbc:oracle:thin:@//c6401.ambari.apache.org:1521	.....

**Oracle** – if the Oracle instance is running with a SID.

Ranger Admin    Ranger User Info    Ranger Plugin    Ranger Audit    Advanced

## Ranger Admin

DB FLAVOR	ORACLE	Ranger DB host
Ranger DB name	ranger	Driver class name for a JDBC Ranger database
Ranger DB username	rangeradmin	Ranger DB password
JDBC connect string	jdbc:oracle:thin:@c6401.ambari.apache.org:1521:ORCL	.....
Setup Database and Database User		
Database Administrator (DBA) username	SYS AS SYSDBA	Database Administrator (DBA) password
JDBC connect string for root user	jdbc:oracle:thin:@c6401.ambari.apache.org:1521:ORCL	.....

PostgreSQL

Ranger Admin    Ranger User Info    Ranger Plugin    Ranger Audit    Advanced

### Ranger Admin

DB FLAVOR	POSTGRES	Ranger DB host
Ranger DB name	ranger	Driver class name for a JDBC Ranger database
Ranger DB username	rangeradmin	Ranger DB password
JDBC connect string	jdbc:postgresql://c6401.ambari.apache.org:5432/r	..... .....

---

Setup Database and Database User

Yes

Database Administrator (DBA) username	postgres	Database Administrator (DBA) password
JDBC connect string for root user	jdbc:postgresql://c6401.ambari.apache.org:5432	..... .....

**MS SQL**

Ranger Admin    Ranger User Info    Ranger Plugin    Ranger Audit    Advanced

### Ranger Admin

DB FLAVOR

MSSQL

Ranger DB name

ranger

Ranger DB username

rangeradmin

JDBC connect string

jdbc:sqlserver://c6401.ambari.apache.org:1433;databaseName=ranger

Ranger DB host

c6401.ambari.apache.org:1433

Driver class name for a JDBC Ranger database

com.microsoft.sqlserver.jdbc.SQLServerDriver

Ranger DB password

.....

Setup Database and Database User

Yes

Database Administrator (DBA) username

administrator

Database Administrator (DBA) password

.....

JDBC connect string for root user

jdbc:sqlserver://c6401.ambari.apache.org:1433;

### SQL Anywhere

Ranger Admin    Ranger User Info    Ranger Plugin    Ranger Audit    Advanced

## Ranger Admin

DB FLAVOR

SQL Anywhere

Ranger DB name

ranger

Ranger DB username

rangeradmin

JDBC connect string

=c6401.ambari.apache.org:2638;database=ranger

Ranger DB host

c6401.ambari.apache.org:2638

Driver class name for a JDBC Ranger database

sap.jdbc4.sqlanywhere.IDriver

Ranger DB password

.....

Setup Database and Database User

Yes

Database Administrator (DBA) username

dba

Database Administrator (DBA) password

.....


JDBC connect string for root user

jdbc:sqlanywhere:host=c6401.ambari.apache.org::

### 3.1.3.2.2. Ranger Audit Settings

1. On the Customize Services page, select the Ranger Audit tab.

It is recommended that you store audits in Solr and HDFS, and disable Audit to DB.



- Under Audit to Solr, click **OFF** under SolrCloud to enable SolrCloud. The button label will change to **ON**, and the SolrCloud configuration settings will be loaded automatically.



### Note

Audits to Solr requires that you have already [installed Solr](#) and [configured SolrCloud](#).

- Under Audit to DB, enter a password in the **Ranger Audit DB password** boxes. Audit to DB is set to **OFF** by default. (The password must be entered to preserve backward compatibility)

#### 3.1.3.2.3. Configure Ranger User Sync

This section describes how to configure Ranger User Sync for either UNIX or LDAP/AD.

- [Test Run Ranger Usersync \[150\]](#)

- [Configuring Ranger User Sync for UNIX \[150\]](#)
- [Configuring Ranger User Sync for LDAP/AD \[151\]](#)

### 3.1.3.2.3.1. Test Run Ranger Usersync

#### Steps

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended.

To test-run loading User and Group data into Ranger before committing to the changes:

1. Set `ranger.usersync.policymanager.mockrun=true`. This parameter can be found in Ambari > Ranger > Configs > Advanced > Advanced ranger-ugsync-site.
2. View the Users and Groups that will be loaded into Ranger: `tail -f /var/log/ranger/usersync/usersync.log`.
3. After confirming that the users and groups are retrieved as intended, set `ranger.usersync.policymanager.mockrun=false` and restart Ranger Usersync.

This will sync the users shown in the usersync log to the Ranger database.

### 3.1.3.2.3.2. Configuring Ranger User Sync for UNIX

#### Before you begin

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

#### Steps

Use the following steps to configure Ranger User Sync for UNIX.

1. On the Customize Services page, select the Ranger User Info tab.
2. Click **Yes** under Enable User Sync.
3. Use the Sync Source drop-down to select UNIX, then set the following properties.

**Table 3.6. UNIX User Sync Properties**

Property	Description	Default Value
Sync Source	Only sync users above this user ID.	500
Password File	The location of the password file on the Linux server.	/etc/passwd
Group File	The location of the groups file on the Linux server.	/etc/group

The screenshot shows the 'Add Service Wizard' interface. On the left, a sidebar lists steps: 'Assign Masters', 'Assign Slaves and Clients', 'Customize Services' (which is selected), 'Configure Identities', 'Review', 'Install, Start and Test', and 'Summary'. The main panel title is 'Ranger User Info'. It contains fields for 'Enable User Sync' (set to 'Yes'), 'Sync Source' (set to 'UNIX'), 'Minimum User ID' (set to '500'), 'Password File' (set to '/etc/passwd'), and 'Group File' (set to '/etc/group'). A note at the bottom states 'All configurations have been addressed.'.

### 3.1.3.2.3.3. Configuring Ranger User Sync for LDAP/AD

#### Important



To ensure that LDAP/AD group level authorization is enforced in Hadoop, you should [set up Hadoop group mapping for LDAP/AD](#).

#### Note



You can use the [LDAP Connection Check tool](#) to determine User Sync settings for LDAP/AD.

#### Before you begin

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

## Steps

Use the following steps to configure Ranger User Sync for LDAP/AD.

1. On the Customize Services page, select the Ranger User Info tab.
2. Click **Yes** under Enable User Sync.
3. Use the Sync Source drop-down to select LDAP/AD.
4. Set the following properties on the Common Configs tab.

**Table 3.7. LDAP/AD Common Configs**

Property	Description	Default Value	Sample Values
LDAP/AD URL	Add URL depending upon LDAP/AD sync source	ldap:///{host}:{port}	ldap:/// ldap.example.com:389 or ldaps:/// ldap.example.com:636
Bind Anonymous	If Yes is selected, the Bind User and Bind User Password are not required.	NO	
Bind User	The location of the groups file on the Linux server.	The full distinguished name (DN), including common name (CN), of an LDAP/AD user account that has privileges to search for users. The LDAP bind DN is used to connect to LDAP and query for users and groups.	cn=admin,dc=example,dc=com or admin@example.com
Bind User Password	The password of the Bind User.		

The screenshot shows the 'Add Service Wizard' interface for 'Ranger'. The left sidebar lists steps: 'Configure Identities', 'Review', 'Install, Start and Test', and 'Summary'. The main area has tabs at the top: Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger (selected), Slider, SmartSense, Spark, and Misc. A message bar says 'There are 51 configuration changes in 8 services. Show Details'. Below are tabs: Group, Default (1), Manage Config Groups, Filter..., Ranger Admin (selected), Ranger User Info, Ranger Plugin, Ranger Audit, and Advanced. The 'Ranger User Info' tab is active, showing fields for 'Enable User Sync' (Yes), 'Sync Source' (LDAP/AD), and tabs for 'Common Configs' (selected), 'User Configs' (highlighted in blue), and 'Group Configs'. Under 'User Configs', there are fields for 'LDAP/AD URL' (ldap://172.22.126.169:389), 'Bind Anonymous' (No), 'Bind User' (cn=Manager,dc=qe,dc=hortonworks,dc=com), and 'Bind User Password' (two password input fields). The 'Advanced' tab is partially visible at the bottom.

- Set the following properties on the User Configs tab.

**Table 3.8. LDAP/AD User Configs**

Property	Description	Default Value	Sample Values
Group User Map Sync	Sync specific groups for users.	No	Yes
Username Attribute	The LDAP user name attribute.		sAMAccountName for AD, uid or cn for OpenLDAP
User Object Class	Object class to identify user entries.	person	top, person, organizationalPerson, user, or posixAccount
User Search Base	Search base for users.		cn=users,dc=example,dc=com
User Search Filter	Optional additional filter constraining the users selected for syncing.		Sample filter to retrieve all the users: cn=* Sample filter to retrieve all the users who are members

Property	Description	Default Value	Sample Values
			of groupA or groupB: ( (memberof=CN=GroupA,OU=groups,DC=example,DC=com)(memberof=CN=GroupB,OU=groups,DC=example,DC=com))
User Search Scope	This value is used to limit user search to the depth from search base.	sub	base, one, or sub
User Group Name Attribute	Attribute from user entry whose values would be treated as group values to be pushed into the Access Manager database. You can provide multiple attribute names separated by commas.	memberof,ismemberof	memberof, ismemberof, or gidNumber

Add Service Wizard

### Ranger User Info

Enable User Sync:

Sync Source:

Group User Map Sync:

Common Configs    User Configs    **Group Configs**

Username Attribute: uid

User Object Class: person

User Search Base: dc=qe,dc=hortonworks,dc=com

User Search Filter: (uid={0})


User Search Scope: sub

User Group Name Attribute: memberof, ismemberof

6. Set the following properties on the Group Configs tab.

**Table 3.9. LDAP/AD Group Configs**

Property	Description	Default Value	Sample Values
Enable Group Sync	If Enable Group Sync is set to No, the group names the users belong to are derived from "User Group Name Attribute". In this case no additional group filters are applied.  If Enable Group Sync is set to Yes, the groups the users belong to are retrieved from LDAP/AD using the following group-related attributes.	No	Yes
Group Member Attribute	The LDAP group member attribute name.		member
Group Name Attribute	The LDAP group name attribute.		distinguishedName for AD, cn for OpenLdap
Group Object Class	LDAP Group object class.		group, groupofnames, or posixGroup
Group Search Base	Search base for groups.		ou=groups,DC=example,DC=com
Group Search Filter	Optional additional filter constraining the groups selected for syncing.		Sample filter to retrieve all groups: cn=*  Sample filter to retrieve only the groups whose cn is Engineering or Sales: ( (cn=Engineering)(cn=Sales))



### 3.1.3.2.4. Configure Ranger Authentication

This section describes how to configure Ranger authentication for UNIX, LDAP, and AD.

- [Configuring Ranger UNIX Authentication \[156\]](#)
- [Configuring Ranger LDAP Authentication \[158\]](#)
- [Configuring Ranger Active Directory Authentication \[161\]](#)

#### 3.1.3.2.4.1. Configuring Ranger UNIX Authentication

Use the following steps to configure Ranger authentication for UNIX.

1. Select the Advanced tab on the Customize Services page.
2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the **External URL** box in the format `http://<your_ranger_host>:6080`.

3. Under Ranger Settings, select **UNIX**.

HTTP is enabled by default – if you disable HTTP, only HTTPS is allowed.

4. Under UNIX Authentication Settings, set the following properties.

**Table 3.10. UNIX Authentication Settings**

Property	Description	Default Value	Example Value
Allow remote Login	Flag to enable/disable remote login. Only applies to UNIX authentication.	true	true
ranger.unixauth.service.hostname	The address of the host where the UNIX authentication service is running.	<code>{{{ugsync_host}}}</code>	
ranger.unixauth.service.port	The port number on which the UNIX authentication service is running.	5151	5151



### Note

Properties with value `{ {xyz} }` are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

The screenshot shows the 'Add Service Wizard' interface with the 'Ranger Settings' tab selected. Under 'External URL', the value is `http://b6403.ambari.apache.org:8080`. Under 'Authentication method', the 'UNIX' option is selected. Under 'HTTP enabled', the checkbox is checked. Below this, the 'Unix Authentication Settings' tab is selected, showing three properties: 'Allow remote Login' (value: true), 'ranger.unixauth.service.hostname' (value: `{{{ugsync_host}}}`), and 'ranger.unixauth.service.port' (value: 5151). At the bottom of the window, there are tabs for 'Knox SSO Settings' and 'Advanced ranger-admin-site'.

### 3.1.3.2.4.2. Configuring Ranger LDAP Authentication



#### Note

You can use the [LDAP Connection Check tool](#) to determine authentication settings for LDAP.

Use the following steps to configure Ranger authentication for LDAP.

1. Select the Advanced tab on the Customize Services page.
2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the **External URL** box in the format `http://<your_ranger_host>:6080`.
3. Under Ranger Settings, select **LDAP**.
4. Under LDAP Settings, set the following properties.

**Table 3.11. LDAP Authentication Settings**

Property	Description	Default Value	Example Value
ranger.ldap.base_dn	The Distinguished Name (DN) of the starting point for directory server searches.	dc=example,dc=com	dc=example,dc=com
Bind User	The full Distinguished Name (DN), including Common Name (CN) of an LDAP user account that has privileges to search for users. This is a macro variable value that is derived from the <b>Bind User</b> value from <b>Ranger User Info &gt; Common Configs</b> .	{ {ranger_ug_ldap_bind_dn} }{ranger_ug_ldap_bind_dn}}	
Bind User Password	Password for the Bind User. This is a macro variable value that is derived from the <b>Bind User Password</b> value from <b>Ranger User Info &gt; Common Configs</b> .		

Property	Description	Default Value	Example Value
ranger.ldap.group.roleattribute	The LDAP group role attribute.	cn	cn
ranger.ldap.referral	See description below.	ignore	follow   ignore   throw
LDAP URL	The LDAP server URL. This is a macro variable value that is derived from the <b>LDAP/AD URL</b> value from <b>Ranger User Info &gt; Common Configs</b> .	<code>{ {ranger_ug_ldap_url} }</code>	<code>{ {ranger_ug_ldap_url} }</code>
ranger.ldap.user.dnpattern	The user DN pattern is expanded when a user is being logged in. For example, if the user "ldapadmin" attempted to log in, the LDAP Server would attempt to bind against the DN "uid=ldapadmin,ou=users,dc=example,dc=com" using the password the user provided>	<code>uid={0},ou=users,dc=xasecure,dc=net</code>	<code>cn=ldapadmin,ou=Users,dc=example,dc=com</code>
User Search Filter	The search filter used for Bind Authentication. This is a macro variable value that is derived from the <b>User Search Filter</b> value from <b>Ranger User Info &gt; User Configs</b> .	<code>{ {ranger_ug_ldap_user_searchfilter} }</code>	<code>{ {ranger_ug_ldap_user_searchfilter} }</code>




## Note

Properties with value `{ {xyz} }` are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

There are three possible values for `ranger.ldap.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.

- When this property is set to `follow`, the LDAP service provider processes all of the normal entries first, and then follows the continuation references.
- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search.



### 3.1.3.2.4.3. Configuring Ranger Active Directory Authentication



#### Note

You can use the [LDAP Connection Check tool](#) to determine authentication settings for Active Directory.

Use the following steps to configure Ranger authentication for Active Directory.

1. Select the Advanced tab on the Customize Services page.
2. Under Ranger Settings, specify the Ranger Access Manager/Service Manager host address in the **External URL** box in the format `http://<your_ranger_host>:6080`.
3. Under Ranger Settings, select **ACTIVE\_DIRECTORY**.
4. Under AD Settings, set the following properties.

**Table 3.12. AD Settings**

Property	Description	Default Value	Example Value
ranger.ldap.ad.base_dn	The Distinguished Name (DN) of the starting point for directory server searches.	dc=example,dc=com	dc=example,dc=com
ranger.ldap.ad.bind_dn	The full Distinguished Name (DN), including Common Name (CN) of an LDAP user account that has privileges to search for users. This is a macro variable value that is derived from the <b>Bind User</b> value from <b>Ranger User Info &gt; Common Configs</b> .	<code>{ {ranger_ug_ldap_bind_dn} }</code>	
ranger.ldap.ad.bind.password	Password for the bind_dn. This is a macro variable value that is derived from the <b>Bind User Password</b> value from <b>Ranger User Info &gt; Common Configs</b> .		
Domain Name (Only for AD)	The domain name of the AD Authentication service.		dc=example,dc=com
ranger.ldap.ad.referral	See description below.	ignore	follow   ignore   throw
ranger.ldap.ad.url	The AD server URL. This is a macro variable value that is derived from the <b>LDAP/AD URL</b> value from <b>Ranger User Info &gt; Common Configs</b> .	<code>{ {ranger_ug_ldap_url} }</code>	<code>{ {ranger_ug_ldap_url} }</code>
ranger.ldap.ad.user.searchfilter	The search filter used for Bind Authentication. This is a macro variable value that is derived from the <b>User Search Filter</b> value from <b>Ranger User Info &gt; User Configs</b> .	<code>{ {ranger_ug_ldap_user_searchfilter} }</code>	<code>{ {ranger_ug_ldap_user_searchfilter} }</code>



### Note


Properties with value `{ {xyz} }` are macro variables that are derived from other specified values in order to streamline the configuration process. Macro variables can be edited if required – if you need to restore the original value, click the Set Recommended symbol at the right of the property box.

There are three possible values for `ranger.ldap.ad.referral`: `follow`, `throw`, and `ignore`. The recommended setting is `follow`.

When searching a directory, the server might return several search results, along with a few continuation references that show where to obtain further results. These results and references might be interleaved at the protocol level.


- When this property is set to `follow`, the AD service provider processes all of the normal entries first, and then follows the continuation references.

- When this property is set to `throw`, all of the normal entries are returned in the enumeration first, before the `ReferralException` is thrown. By contrast, a "referral" error response is processed immediately when this property is set to `follow` or `throw`.
- When this property is set to `ignore`, it indicates that the server should return referral entries as ordinary entries (or plain text). This might return partial results for the search. In the case of AD, a `PartialResultException` is returned when referrals are encountered while search results are processed.



When you have finished configuring all of the Customize Services Settings, click **Next** at the bottom of the page to continue with the installation.

5. When you save the authentication method as Active Directory, a Dependent Configurations pop-up may appear recommending that you set the authentication method as LDAP. This recommended configuration should not be applied for AD, so you should clear (un-check) the `ranger.authentication.method` check box, then click **OK**.



### 3.1.3.3. Complete the Ranger Installation

1. On the Review page, carefully review all of your settings and configurations. If everything looks good, click **Deploy** to install Ranger on the Ambari server.

**Review**

Please review the configuration before installation

Admin Name : admin  
Cluster Name : Thomas1  
Total Hosts : 3 (0 new)  
Repositories:

- redhat5 (HDP-2.2):  
http://public-repo-1.hortonworks.com/HDP/centos5/2.x/updates/2.2.6.0
- redhat5 (HDP-UTILS-1.1.0.20):  
http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.20/repos/centos5
- redhat6 (HDP-2.2):  
http://public-repo-1.hortonworks.com/HDP/centos6/2.x/updates/2.2.6.0
- redhat6 (HDP-UTILS-1.1.0.20):  
http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.20/repos/centos6
- suse11 (HDP-2.2):  
http://public-repo-1.hortonworks.com/HDP/suse11sp3/2.x/updates/2.2.6.0
- suse11 (HDP-UTILS-1.1.0.20):  
http://public-repo-1.hortonworks.com/HDP-UTILS-1.1.0.20/repos/suse11sp3
- ubuntu12 (HDP-2.2):  
http://public-repo-1.hortonworks.com/HDP/ubuntu12/2.x/updates/2.2.6.3

← Back      Print      Deploy →

2. When you click **Deploy**, Ranger is installed on the specified host on your Ambari server. A progress bar displays the installation progress.

**Install, Start and Test**

Please wait while the selected services are installed and started.

Host	Status	Message
c6401.ambari.apache.org	8%	Installing Ranger Admin
c6402.ambari.apache.org	33%	Install complete (Waiting to start)
c6403.ambari.apache.org	33%	Install complete (Waiting to start)

3 of 3 hosts showing - Show All      Show: All (3) In Progress (3) | Warning (0) | Success (0) | Fail (0)      24 % overall

Next →      Previous ←

3. When the installation is complete, a Summary page displays the installation details. You may need to restart services for cluster components after installing Ranger.



### Note

If the installation fails, you should complete the installation process, then reconfigure and reinstall Ranger.

#### 3.1.3.4. Advanced Usersync Settings

To access Usersync settings, select the Advanced tab on the Customize Service page. Usersync pulls in users from UNIX, LDAP, or AD and populates Ranger's local user tables with these users.



### Important

To ensure that LDAP/AD group level authorization is enforced in Hadoop, you must first [set up Hadoop group mapping](#) for LDAP.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

##### 3.1.3.4.1. UNIX Usersync Settings

If you are using UNIX authentication, the default values for the Advanced ranger-ugsync-site properties are the settings for UNIX authentication.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

Advanced ranger-ugsync-site

ranger.usersync.ldap.bindkeystore		lock	green	blue
ranger.usersync.ldap.ldapbindpassword	Type password	lock	Retype Password	lock
ranger.usersync.group.memberattributename		lock	green	blue
ranger.usersync.group.nameattribute		lock	green	blue
ranger.usersync.group.objectclass		lock	green	blue
ranger.usersync.group.searchbase		lock	green	blue
ranger.usersync.group.searchenabled	false	lock	green	blue
ranger.usersync.group.searchfilter		lock	green	blue
ranger.usersync.group.searchscope		lock	green	blue
ranger.usersync.group.usermodelsyncenabled	false	lock	green	blue
ranger.usersync.ldap.searchBase	dc=hadoop,dc=apache,dc=org	lock	green	blue
ranger.usersync.source.impl.class	org.apache.ranger.unixusersync.process.UnixUserGroupBuilder	lock	green	blue
ranger.usersync.credstore.filename	/usr/hdp/current/ranger-usersync/conf/ugsync.jceks	lock	green	blue
ranger.usersync.enabled	true	lock	green	blue
ranger.usersync.filesource.file	/tmp/usergroup.txt	lock	green	blue
ranger.usersync.filesource.text.delimiter	,	lock	green	blue
ranger.usersync.keystore.file	/usr/hdp/current/ranger-usersync/conf/unixauthservice.jks	lock	green	blue

### 3.1.3.4.2. Required LDAP and AD Usersync Settings

If you are using LDAP authentication, you must update the following Advanced ranger-ugsync-site properties.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

**Table 3.13. LDAP Advanced ranger-ugsync-site Settings**

Property Name	LDAP Value
ranger.usersync.ldap.bindkeystore	Set this to the same value as the <code>ranger.usersync.credstore.filename</code> property, i.e, the default value is <code>/usr/hdp/current/ranger-usersync/conf/ugsync.jceks</code>
ranger.usersync.ldap.bindalias	<code>ranger.usersync.ldap.bindalias</code>
ranger.usersync.source.impl.class	<code>ldap</code>

**Table 3.14. AD Advanced ranger-ugsync-site Settings**

Property Name	LDAP Value
ranger.usersync.source.impl.class	<code>ldap</code>

### 3.1.3.4.3. Additional LDAP and AD Usersync Settings

If you are using LDAP or Active Directory authentication, you may need to update the following properties, depending upon your specific deployment characteristics.

Before committing to usersync changes, it is recommended that you test-run that users and groups are being retrieved as intended: [Test Run Ranger Usersync \[150\]](#).

**Table 3.15. Advanced ranger-ugsync-site Settings for LDAP and AD**

Property Name	LDAP ranger-ugsync-site Value	AD ranger-ugsync-site Value
ranger.usersync.ldap.url	<code>ldap://127.0.0.1:389</code>	<code>ldap://ad-conrowoller-hostname:389</code>
ranger.usersync.ldap.binddn	<code>cn=ldapadmin,ou=users,dc=example,dc=com</code>	<code>cn=adadmin,cn=Users,dc=example,dc=com</code>
ranger.usersync.ldap.ldapbindpassword	<code>secret</code>	<code>secret</code>
ranger.usersync.ldap.searchBase	<code>dc=example,dc=com</code>	<code>dc=example,dc=com</code>
ranger.usersync.source.impl.class	<code>org.apache.ranger.ldapusersync.process.LdapUserGroupBuilder</code>	
ranger.usersync.ldap.user.searchbase	<code>ou=users, dc=example, dc=com</code>	<code>dc=example,dc=com</code>
ranger.usersync.ldap.user.searchscope	<code>sub</code>	<code>sub</code>
ranger.usersync.ldap.user.objectclass	<code>person</code>	<code>person</code>
ranger.usersync.ldap.user.searchfilter	Set to single empty space if no value. Do not leave it as "empty"	<code>(objectcategory=person)</code>
ranger.usersync.ldap.user.nameattribute	<code>uid or cn</code>	<code>sAMAccountName</code>
ranger.usersync.ldap.user.groupnameattribute	<code>memberof,ismemberof</code>	<code>memberof,ismemberof</code>
ranger.usersync.ldap.username.caseconversion	<code>none</code>	<code>none</code>
ranger.usersync.ldap.groupname.caseconversion	<code>none</code>	<code>none</code>

Property Name	LDAP ranger-ugsync-site Value	AD ranger-ugsync-site Value
ranger.usersync.group.searchenabled *	false	false
ranger.usersync.group.usermodelsyncenabled *	false	false
ranger.usersync.group.searchbase *	ou=groups, dc=example, dc=com	dc=example,dc=com
ranger.usersync.group.searchscope *	sub	sub
ranger.usersync.group.objectclass *	groupofnames	groupofnames
ranger.usersync.group.searchfilter *	needed for AD authentication	(member=CN={0}, OU=MyUsers, DC=AD-HDP, DC=COM)
ranger.usersync.group.nameattribute *	cn	cn
ranger.usersync.group.memberattributename *	member	member
ranger.usersync.pagedresultsenabled *	true	true
ranger.usersync.pagedresultssize *	500	500
ranger.usersync.user.searchenabled *	false	false
ranger.usersync.group.search.first.enabled *	false	false

\* Only applies when you want to filter out groups.

After you have finished specifying all of the settings on the Customize Services page, click **Next** at the bottom of the page to continue with the installation.

### 3.1.3.5. Configuring Ranger for LDAP SSL

You can use the following steps to configure LDAP SSL using self-signed certs in the default Ranger User Sync TrustStore.

1. The default location is /usr/hdp/current/ranger-usersync/conf/mytruststore.jks for the ranger.usersync.truststore.file property.
2. Alternatively, copy and edit the self-signed ca certs.
3. Set the ranger.usersync.truststore.file property to that new cacert file.

```
cd /usr/hdp/<version>/ranger-usersync
service ranger-usersync stop
service ranger-usersync start
```

Where cert.pem has the LDAPS cert.

### 3.1.3.6. Setting up Database Users Without Sharing DBA Credentials

If do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the dba\_script.py Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger

installer. You can then run the normal Ambari Ranger installation without specify a DBA user name and password.

To create Ranger DB users using the `dba_script.py` script:

1. Download the Ranger rpm using the `yum install` command.

```
yum install ranger-admin
```

2. You should see one file named `dba_script.py` in the `/usr/hdp/current/ranger-admin` directory.

3. Get the script reviewed internally and verify that your DBA is authorized to run the script.

4. Execute the script by running the following command:

```
python dba_script.py
```

5. Pass all values required in the argument. These should include `db flavor`, `JDBC jar`, `db host`, `db name`, `db user`, and other parameters.

- If you would prefer not to pass runtime arguments via the command prompt, you can update the `/usr/hdp/current/ranger-admin/install.properties` file and then run:

- `python dba_script.py -q`

When you specify the `-q` option, the script will read all required information from the `install.properties` file

- You can use the `-d` option to run the script in "dry" mode. Running the script in dry mode causes the script to generate a database script.

```
python dba_script.py -d /tmp/generated-script.sql
```

Anyone can run the script, but it is recommended that the system DBA run the script in dry mode. In either case, the system DBA should review the generated script, but should only make minor adjustments to the script, for example, change the location of a particular database file. No major changes should be made that substantially alter the script – otherwise the Ranger install may fail.

The system DBA must then run the generated script.

6. Run the Ranger Ambari install procedure, but set **Setup Database and Database User** to **No** in the Ranger Admin section of the Customize Services page.

### 3.1.3.7. Updating Ranger Admin Passwords

For the following users, if you update the passwords on the Ranger Configs page, you must also update the passwords on the Configs page of each Ambari component that has the Ranger plugin enabled. Individual Ambari component configurations are not automatically updated – the service restart will fail if you do not update these passwords on each component.

- Ranger Admin user – The credentials for this user are set in **Configs > Advanced ranger-env** in the fields labeled **admin\_username** (default value: admin) and **admin\_password** (default value: admin).
- Admin user used by Ambari to create repo/policies – The user name for this user is set in **Configs > Admin Settings** in the field labeled **Ranger Admin username for Ambari** (default value: amb\_ranger\_admin). The password for this user is set in the field labeled **Ranger Admin user's password for Ambari**. This password is specified during the Ranger installation.

The following image shows the location of these settings on the Ranger Configs page:

**Admin Settings**

- Ranger Admin user's password for Ambari: [redacted]
- Location of Sqoop Connector Jar: /usr/share/java/mysql-connector-java.jar

**Advanced ranger-env**

Setting	Value	Actions
admin_password	[redacted]	[edit]
Setup DB and DB user	DB: [redacted] DB User: [redacted]	[edit]
admin_username	admin	[edit]
ranger_admin_log_dir	/var/log/ranger/admin	[edit]
ranger_admin_username	amb_ranger_admin	[edit]
ranger_pid_dir	/var/run/ranger	[edit]
ranger_usersync_log_dir	/var/log/ranger/usersync	[edit]
xml_configurations_supported	true	[edit]

### 3.1.4. Enabling Ranger Plugins

Ranger plugins can be enabled for several HDP services. This section describes how to enable each of these plugins. For performance reasons, it is recommended that you store audits in Solr and HDFS, and not in a database.

If you are using a Kerberos-enabled cluster, there are a number of additional steps you must follow to ensure that you can use the Ranger plugins on a Kerberos cluster.

The following Ranger plugins are available:

- [HDFS \[171\]](#)
- [Hive \[175\]](#)

- HBase [178]
- Kafka [181]
- Knox [185]
- YARN [188]
- Storm [192]


### 3.1.4.1. HDFS

Use the following steps to enable the Ranger HDFS plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.

The screenshot shows the Ambari interface for the cluster 'c6401\_TEST'. The top navigation bar includes 'Dashboard', 'Services', 'Hosts 1', 'Alerts', 'Admin', and a user dropdown. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense, and Spark. A red box highlights the 'Ranger' service. The main content area has tabs for 'Summary' and 'Configs', with 'Configs' selected. Below this is a 'Quick Links' section with a 'Manage Config Groups' button and a 'Filter...' dropdown. A central panel displays configuration versions for HDFS, HBase, and YARN, with version V3 selected. A message at the bottom of this panel states 'admin authored on Wed, Feb 03, 2016 11:28'. At the bottom of the main content area is a black menu bar with 'Discard' and 'Save' buttons. Below the main content area is a large box titled 'Ranger Plugin' containing several toggle switches. The 'HDFS Ranger Plugin' switch is set to 'ON'. The 'Hbase Ranger Plugin' and 'Knox Ranger Plugin' switches are also set to 'ON'. The 'YARN Ranger Plugin' switch is set to 'ON'. The 'Storm Ranger Plugin' switch is set to 'OFF'. The 'Kafka Ranger Plugin' switch is set to 'ON'. The bottom of the page features a footer with the number '171'.


2. Under HDFS Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **HDFS** in the navigation menu, then select **Restart > Restart All Affected** to restart the HDFS service and load the new configuration.

The screenshot shows the Ambari UI for a test\_cluster. On the left, a sidebar lists various services: HDFS (green), MapReduce2 (orange), YARN (blue), Tez (grey), Hive (green), HBase (red), Pig (grey), Sqoop (green), Oozie (green), ZooKeeper (green), Falcon (red), Storm (green), Flume (red), Accumulo (red), Ambari Metrics (green), Atlas (green), Kafka (green), Knox (green), Mahout (grey), Ranger (green), Slider (grey), SmartSense (green), and Spark (green). In the center, the 'Configs' tab is selected under 'Summary'. A message at the top says 'Restart Required: 4 Components on 1 Host'. Below it, a 'Manage Config Groups' section shows three configurations: V3 (2 minutes ago), N2 (2 hours ago), and V1 (15 days ago). A red box highlights the 'Restart All Affected' button. At the bottom, there are 'Settings' and 'Advanced' tabs, and a 'Save' button.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the HDFS restart.



8. After HDFS restarts, the Ranger plugin for HDFS will be enabled. Other components may also require a restart.

### 3.1.4.2. Hive

Use the following steps to enable the Ranger Hive plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.

The screenshot shows the Ambari interface for the cluster 'c6401\_TEST'. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive (selected), HBase, Pig, Soop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger (selected), Slider, SmartSense, and Spark. The main area displays configuration groups: V3 (admin, 6 days ago, HDP-2.3), V2 (admin, 7 days ago, HDP-2.3), and V1 (admin, 13 days ago, HDP-2.3). A message at the bottom indicates 'admin authored on Wed, Feb 03, 2016 11:28'. Below the message, tabs include Ranger Admin, Ranger User Info, Ranger Plugin (selected), Ranger Audit, and Advanced. The Ranger Plugin section contains six toggle switches: HDFS Ranger Plugin (ON), Hbase Ranger Plugin (ON), Knox Ranger Plugin (ON), YARN Ranger Plugin (ON), Storm Ranger Plugin (OFF), and Kafka Ranger Plugin (ON). The 'Ranger Plugin' tab is highlighted in blue.


2. Under Hive Ranger Plugin, select **On**, then click **Save** in the black menu bar.

This screenshot shows the 'Ranger Plugin' configuration page. It features six sections: HDFS Ranger Plugin (ON), Hbase Ranger Plugin (ON), Knox Ranger Plugin (ON), YARN Ranger Plugin (ON), Storm Ranger Plugin (OFF), and Kafka Ranger Plugin (ON). The 'Hive Ranger Plugin' section is highlighted with a red box around its 'ON' button. The background of the entire page is light gray, while the configuration sections have a white background.


3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click Save.



4. A Dependent Configuration pop-up appears. Click OK to confirm the configuration updates.




5. Click OK on the Save Configuration Changes pop-up.



6. Select **Hive** in the navigation menu, then select **Restart > Restart All Affected** to restart the Hive service and load the new configuration.

A screenshot of the Ambari interface showing the configuration for the Hive service. On the left, the navigation menu is open, and "Hive" is selected. The main area shows the "Configs" tab for the Hive service. A yellow banner at the top indicates "Restart Required: 6 Components on 1 Host". Below this, there is a "Manage Config Groups" section with three configurations listed: V3 (about a minute ago), V2 (5 hours ago), and V1 (15 days ago). In the top right, there is a "Service Actions" dropdown with a "Restart" option, and a red box highlights the "Restart All Affected" button. At the bottom of the configuration page, there are "Discard" and "Save" buttons.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Hive restart.



8. After Hive restarts, the Ranger plugin for Hive will be enabled.

### 3.1.4.3. HBase



#### Note

When HBase is configured with Ranger, and specifically XASecure Authorizer, you may only grant and revoke privileges.

Use the following steps to enable the Ranger HBase plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.

The screenshot shows the Ambari interface for the c6401\_TEST cluster. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense, and Spark. The 'Ranger' service is selected. The main panel displays the 'Ranger Plugin' configuration. It includes sections for HDFS, Hbase, and Knox Ranger Plugins, and YARN, Storm, and Kafka Ranger Plugins. Under the Hbase Ranger Plugin section, the 'ON' button is highlighted with a red box. Below the configuration, a note says 'admin authored on Wed, Feb 03, 2016 11:28' and there are 'Discard' and 'Save' buttons.


- Under HBase Ranger Plugin, select **On**, then click **Save** in the black menu bar.

This screenshot shows the same 'Ranger Plugin' configuration page as the previous one, but with a red box highlighting the 'ON' button for the Hbase Ranger Plugin. The other buttons (HDFS, YARN, Storm, and Kafka) are also shown in green.


- A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **HBase** in the navigation menu, then select **Restart > Restart All Affected** to restart the HBase service and load the new configuration.

The screenshot shows the Ambari interface for managing HBase configurations. On the left, there's a sidebar with various service icons. The 'HBase' icon is selected. The main panel has tabs for 'Summary', 'Heatmaps', and 'Configs'. Under 'Configs', it says 'Restart Required: 3 Components on 1 Host'. There's a 'Group' dropdown set to 'HBase Default (1)'. A red box highlights the 'Restart All Affected' button. Below this, there are sections for 'HBase Master' and 'RegionServer' with various configuration parameters like 'Maximum Memory' and 'Number of Handlers per RegionServer'. At the bottom right of the main panel are 'Discard' and 'Save' buttons.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the HBase restart.



8. After HBase restarts, the Ranger plugin for HBase will be enabled.

### 3.1.4.4. Kafka

Use the following steps to enable the Ranger Kafka plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.

The screenshot shows the Ambari interface for the c6401\_TEST cluster. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense, and Spark. The 'Ranger' service is selected. The main panel displays the 'Ranger Plugin' configuration. It includes sections for HDFS, Hbase, and Knox Ranger Plugins, all set to 'ON'. Below these are sections for YARN, Storm, and Kafka Ranger Plugins. The 'Kafka Ranger Plugin' button is highlighted with a red box. At the bottom, there is a 'Save' button.

- Under Kafka Ranger Plugin, select **On**, then click **Save** in the black menu bar.

This screenshot shows the same Ranger Plugin configuration page as the previous one, but with a difference. The 'Kafka Ranger Plugin' button has been explicitly set to 'ON' and is highlighted with a red box. All other plugin configurations remain at their previous state: HDFS, Hbase, and Knox are still ON; YARN and Storm are OFF; and Kafka is now ON.

- A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.




4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.

A screenshot of a 'Dependent Configurations' dialog box. It shows a table of configuration changes:

Property	Service	Config Group	File Name	Current Value	Recommended Value
<input checked="" type="checkbox"/> authorizer.class.name	Kafka	Default	kafka-broker		org.apache.ranger.authorization.kafka.authorizer.RangerKafkaAuthorizer
<input checked="" type="checkbox"/> content	Kafka	Default	kafka-log4j	# Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements. See the NOTICE file distributed with this work for additional information regarding copyright ownership. The ASF licenses this file to you under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at <a href="http://www.apache.org/licenses/LICENSE-2.0">http://www.apache.org/licenses/LICENSE-2.0</a> Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.	# Licensed to the Apache Software Foundation (ASF) under one or more contributor license agreements. See the NOTICE file distributed with this work for additional information regarding copyright ownership. The ASF licenses this file to you under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at <a href="http://www.apache.org/licenses/LICENSE-2.0">http://www.apache.org/licenses/LICENSE-2.0</a> Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

At the bottom right of the dialog box, there are 'Cancel' and 'OK' buttons, with 'OK' being highlighted with a red border.


5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Kafka** in the navigation menu, then select **Restart > Restart All Affected** to restart the Kafka service and load the new configuration.

A screenshot of the Ambari web interface. The left sidebar shows various services like HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Fiume, Accumulo, Ambari Metrics, and Atlas. The "Kafka" service is selected and highlighted with a dark gray background. The main content area shows the "Configs" tab for the Kafka Broker. It lists configuration parameters such as "Kafka Broker host" (c6403.ambari.apache.org), "zookeeper.connect" (c6403.ambari.apache.org:2181), "log.dirs" (/kafka-logs), "log.retention.hours" (168), "log.roll.hours" (168), and "listeners" (PLAINTEXT://localhost:6667). Above the configuration table, a yellow banner says "Restart Required: 1 Component on 1 Host". To the right of the banner, there is a "Restart" button with a dropdown arrow, and a larger button labeled "Restart All Affected" which is highlighted with a red box. At the bottom right of the configuration table, there are "Discard" and "Save" buttons.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Kafka restart.



8. After Kafka restarts, the Ranger plugin for Kafka will be enabled.


### 3.1.4.5. Knox

Use the following steps to enable the Ranger Knox plugin.


1. On the Ranger Configs page, select the **Ranger Plugin** tab.

A screenshot of the Ambari interface showing the Ranger Configs page. The left sidebar has "Ranger" selected. The main area shows the "Configs" tab is active. Below it, the "Ranger Plugin" tab is selected. Under "Ranger Plugin", several services are listed with their status: HDFS Ranger Plugin (ON), Hbase Ranger Plugin (ON), Knox Ranger Plugin (ON), YARN Ranger Plugin (ON), Storm Ranger Plugin (OFF), and Hive Ranger Plugin (ON). At the bottom right of the main area, there are "Discard" and "Save" buttons, with "Save" being highlighted by a red rectangle.

2. Under Knox Ranger Plugin, select **On**, then click **Save** in the black menu bar.



3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.

**Dependent Configurations**

Based on your configuration changes, Ambari is recommending the following dependent configuration changes. Ambari will update all checked configuration changes to the Recommended Value. Uncheck any configuration to retain the Current Value.

Property	Service	Config Group	File Name	Current Value	Recommended Value
<input checked="" type="checkbox"/> ranger-knox-plugin-enabled	Knox	Default	ranger-knox-plugin-properties	No	Yes
<input checked="" type="checkbox"/> content	Knox	Default	topology	<topology> <gateway> <provider> <role>authentication</role> <name> eShiroProvider</name> <enable>true</enable> </param> <name> eSessionTimeout</name> <value>30</value> </param> <param> <name>main ldapRealm</name> <value>org.apache.hadoop.gateway.sso.realm.KnoxLdapRealm</value> </param> <param> <name>main_id_apfRealm.userDnTemplate</name> <value>uid={0}.ou=people,dc=hadoop,dc=apache,dc=org</value> </param> <param> <name>main_id_apfRealm.contextFactory.url</name> <value>ldap://{{knox_host_name}}:3389</value> </param> <param> <name>main_id_apfRealm.comsFactory.authMechanism</name> <value>simple</value> </param> <param> <name>urlPattern</name> <value>authBasic</value> </param> <param> <name>urlPattern</name> <value>authBasic</value> </param> <param> <name>urlPattern</name> <value>authBasic</value> </param>	<topology> <gateway> <provider> <role>authentication</role> <name> eShiroProvider</name> <enable>true</enable> </param> <name> eSessionTimeout</name> <value>30</value> </param> <param> <name>main ldapRealm</name> <value>org.apache.hadoop.gateway.sso.realm.KnoxLdapRealm</value> </param> <param> <name>main_id_apfRealm.userDnTemplate</name> <value>uid={0}.ou=people,dc=hadoop,dc=apache,dc=org</value> </param> <param> <name>main_id_apfRealm.contextFactory.url</name> <value>ldap://{{knox_host_name}}:3389</value> </param> <param> <name>main_id_apfRealm.comsFactory.authMechanism</name> <value>simple</value> </param> <param> <name>urlPattern</name> <value>authBasic</value> </param> <param> <name>urlPattern</name> <value>authBasic</value> </param> <param> <name>urlPattern</name> <value>authBasic</value> </param>

**Cancel** **OK**

5. Click **OK** on the Save Configuration Changes pop-up.

**Save Configuration Changes**


Service configuration changes saved successfully.

**OK**

6. Select **Knox** in the navigation menu, then select **Restart > Restart All Affected** to restart the Knox service and load the new configuration.

The screenshot shows the Ambari interface for a 'test\_cluster'. On the left, a sidebar lists various Hadoop services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, and Knox. The 'Knox' service is currently selected. The main panel displays the 'Configs' tab for the Knox Gateway. It shows a summary message: 'Restart Required: 1 Component on 1 Host'. Below this, there's a 'Manage Config Groups' section with three groups: V3, V2, and V1. A red box highlights the 'Restart All Affected' button in the top right of this section. At the bottom, there are 'Discard' and 'Save' buttons.

- Click Confirm Restart All on the confirmation pop-up to confirm the Knox restart.



- After Knox restarts, the Ranger plugin for Knox will be enabled.

### 3.1.4.6. YARN

Use the following steps to enable the Ranger YARN plugin.


- On the Ranger Configs page, select the **Ranger Plugin** tab.

The screenshot shows the Ambari interface for the cluster 'c6401\_TEST'. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense, and Spark. The 'Ranger' service is selected. The main panel displays the 'Ranger Plugin' configuration. It includes sections for HDFS, Hbase, and Knox Ranger Plugins, all set to 'ON'. Under the YARN section, the 'YARN Ranger Plugin' is also set to 'ON'. Below these, the 'Storm Ranger Plugin' is set to 'OFF' and the 'Kafka Ranger Plugin' is set to 'ON'. A black menu bar at the top has tabs for 'Summary', 'Configs', 'Quick Links', and 'Service Actions'. The 'Configs' tab is active. A modal window titled 'V3' shows a note: 'admin authored on Wed, Feb 03, 2016 11:28'. Buttons for 'Discard' and 'Save' are at the bottom of the modal.

2. Under YARN Ranger Plugin, select **On**, then click **Save** in the black menu bar.

This screenshot shows the same 'Ranger Plugin' configuration page as the previous one, but with a red box highlighting the 'ON' button for the 'YARN Ranger Plugin'. The other settings remain the same: HDFS, Hbase, and Knox Ranger Plugins are ON; Storm Ranger Plugin is OFF; and Kafka Ranger Plugin is ON. The overall layout is identical to the first screenshot, with the YARN Ranger Plugin being the focal point due to the red box.

3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.

Property	Service	Config Group	File Name	Current Value	Recommended Value
<input checked="" type="checkbox"/> ranger-knox-plugin-enabled	Knox	Default	ranger-knox-plugin-properties	Yes	No
<input checked="" type="checkbox"/> content	Knox	Default	topology	<pre>&lt;dependency&gt; &lt;gateway&gt; &lt;provider&gt; &lt;role&gt;authentication&lt;/role&gt; &lt;name&gt; so-ldap-provider&lt;/name&gt; &lt;enable&gt; &lt;true&gt;&lt;/enable&gt; &lt;param&gt; &lt;name&gt; sessionTimeout&lt;/name&gt; &lt;value&gt; &lt;30&gt;&lt;/value&gt; &lt;/param&gt; &lt;param&gt; &lt;name&gt; ranger-managedIdpRealm&lt;/name&gt; &lt;value&gt; alur.org.apache.hadoop.gateway.s hirorealm.KnoxIdpRealm&lt;/value&gt; &lt;/param&gt; &lt;param&gt; &lt;name&gt;ranger_id apRealmUserOnTemplate&lt;/name&gt; &lt;value&gt;uid=[0],ou=people,dc=hado op,dc=apache,dc=org&lt;/value&gt; &lt;/pa ram&gt; &lt;param&gt; &lt;name&gt;ranger_idp realm.compositeFactory.uri&lt;/name&gt; &lt;va lue&gt;ldap://[knox_host_name]:3338 &lt;/value&gt; &lt;param&gt; &lt;name&gt;ranger_i dApRealm.contextFactory.a uthenticationMechanism&lt;/name&gt; &lt;va lue&gt;simple&lt;/value&gt; &lt;/param&gt; &lt;par am&gt; &lt;name&gt;ranger_idApRealm.c onfigBasic&lt;/value&gt; &lt;/param&gt; &lt;param&gt; &lt;name&gt;ranger_idApRe alm.providers.&lt;/name&gt;&lt;value&gt;[&lt;/value&gt; </pre>	<pre>&lt;dependency&gt; &lt;gateway&gt; &lt;provider&gt; &lt;role&gt;authentication&lt;/role&gt; &lt;name&gt; so-ldap-provider&lt;/name&gt; &lt;enable&gt; &lt;true&gt;&lt;/enable&gt; &lt;param&gt; &lt;name&gt; sessionTimeout&lt;/name&gt; &lt;value&gt; &lt;30&gt;&lt;/value&gt; &lt;/param&gt; &lt;param&gt; &lt;name&gt; ranger-managedIdpRealm&lt;/name&gt; &lt;value&gt; alur.org.apache.hadoop.gateway.s hironrealm.KnoxIdpRealm&lt;/value&gt; &lt;/param&gt; &lt;param&gt; &lt;name&gt;ranger_id apRealmUserOnTemplate&lt;/name&gt; &lt;value&gt;uid=[0],ou=people,dc=hado op,dc=apache,dc=org&lt;/value&gt; &lt;/pa ram&gt; &lt;param&gt; &lt;name&gt;ranger_idp realm.compositeFactory.uri&lt;/name&gt; &lt;va lue&gt;ldap://[knox_host_name]:3338 &lt;/value&gt; &lt;param&gt; &lt;name&gt;ranger_i dApRealm.contextFactory.a uthenticationMechanism&lt;/name&gt; &lt;va lue&gt;simple&lt;/value&gt; &lt;/param&gt; &lt;par am&gt; &lt;name&gt;ranger_idApRealm.c onfigBasic&lt;/value&gt; &lt;/param&gt; &lt;param&gt; &lt;name&gt;ranger_idApRe alm.providers.&lt;/name&gt;&lt;value&gt;[&lt;/value&gt; </pre>

5. Click **OK** on the Save Configuration Changes pop-up.


## Save Configuration Changes

Service configuration changes saved successfully.

**OK**

6. Select **YARN** in the navigation menu, then select **Restart > Restart All Affected** to restart the YARN service and load the new configuration.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the YARN restart.




8. After YARN restarts, the Ranger plugin for YARN will be enabled. Other components may also require a restart.

### 3.1.4.7. Storm

Before you can use the Storm plugin, you must first enable Kerberos on your cluster. To enable Kerberos on your cluster, see [Enabling Kerberos Authentication Using Ambari](#).


Use the following steps to enable the Ranger Storm plugin.

1. On the Ranger Configs page, select the **Ranger Plugin** tab.




The screenshot shows the Ambari interface for managing Ranger configurations. The top navigation bar includes 'Ambari' and 'c6401\_TEST' (with 0 ops and 15 alerts), 'Dashboard', 'Services', 'Hosts 1', 'Alerts', 'Admin', and a user dropdown for 'admin'. Below the dashboard, a sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Swoop, Oozie, ZooKeeper, Falcon, Storm (selected), Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger (selected), Slider, SmartSense, and Spark. A red box labeled '2' highlights the 'Ranger' service in the sidebar. The main content area has tabs for 'Summary' (selected) and 'Configs'. Under 'Configs', there's a 'Group' dropdown set to 'Default (1)', a 'Manage Config Groups' button, and a 'Filter...' search bar. Below this is a list of configuration versions: V3 (admin, 6 days ago, HDP-2.3, checked), V2 (admin, 7 days ago, HDP-2.3), and V1 (admin, 13 days ago, HDP-2.3). A black menu bar at the bottom contains buttons for 'Discard' and 'Save'. Below the menu bar, tabs include 'Ranger Admin', 'Ranger User Info', 'Ranger Plugin' (selected), 'Ranger Audit', and 'Advanced'. The 'Ranger Plugin' section displays several plugins: HDFS Ranger Plugin (ON), Hbase Ranger Plugin (ON), Knox Ranger Plugin (ON), YARN Ranger Plugin (ON), Storm Ranger Plugin (OFF), and Kafka Ranger Plugin (ON). A red box labeled '3' highlights the 'Storm Ranger Plugin' status.


2. Under Storm Ranger Plugin, select **On**, then click **Save** in the black menu bar.




3. A Save Configuration pop-up appears. Type in a note describing the changes you just made, then click **Save**.



4. A Dependent Configuration pop-up appears. Click **OK** to confirm the configuration updates.




5. Click **OK** on the Save Configuration Changes pop-up.



6. Select **Storm** in the navigation menu, then select **Restart > Restart All Affected** to restart the Storm service and load the new configuration.

A screenshot of the Ambari web interface. The left sidebar shows various services like HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, and Storm. The Storm service is selected. The main panel shows the "Configs" tab for the Storm service. A yellow banner at the top says "Restart Required: 4 Components on 1 Host". Below it is a "Manage Config Groups" section with five configurations (V5, V4, V3, V2, V1) listed. On the far right, there is a "Service Actions" dropdown with a "Restart" option, and a red box highlights the "Restart All Affected" button. At the bottom of the configuration list, there are "Discard" and "Save" buttons. The configuration details for the Nimbus service are shown below, including parameters like nimbus.reassign, nimbus.childopts, and nimbus.cleanup.inbox.freq.secs.

7. Click **Confirm Restart All** on the confirmation pop-up to confirm the Storm restart.



8. After Storm restarts, the Ranger plugin for Storm will be enabled.

### 3.1.5. Ranger Plugins - Kerberos Overview

If you are using a Kerberos-enabled cluster, there are a number of steps you need to follow to ensure you can use the different Ranger plugins on a Kerberos cluster. These plugins are:

1. [HDFS \[195\]](#)
2. [Hive \[196\]](#)
3. [HBase \[197\]](#)
4. [Knox \[197\]](#)



#### Note

These procedures assume that you have already [enabled Ranger plugins](#).

#### 3.1.5.1. HDFS

To enable the Ranger HDFS plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerhdfslookup`. Make sure this user is synced to Ranger Admin (under *Settings>Users/Groups* tab in the Ranger Admin User Interface).
2. Create a Kerberos principal for `rangerhdfslookup` by entering the following command:
  - `kadmin.local -q 'addprinc -pw rangerhdfslookup rangerhdfslookup@example.com'`



#### Note

A single user/principal (e.g., `rangerrepouser`) can also be created and used across services.

3. Navigate to the HDFS service.
4. Click the **Config** tab.
5. Navigate to *advanced ranger-hdfs-plugin-properties* and update the properties listed in the table shown below.

**Table 3.16. HDFS Plugin Properties**

Configuration Property Name	Value
Ranger repository config user	rangerhdfslookup@example.com
Ranger repository config password	rangerhdfslookup
common.name.for.certificate	blank

6. After updating these properties, click **Save** and restart the HDFS service.

### 3.1.5.2. Hive

To enable the Ranger Hive plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerhive lookup`. Make sure this user is synced to Ranger Admin (under *Settings>Users/Groups* tab in the Ranger Admin UI).
2. Create a Kerberos principal for `rangerhive lookup` by entering the following command:
  - `kadmin.local -q 'addprinc -pw rangerhive lookup rangerhive lookup@example.com'`
3. Navigate to the Hive service.
4. Click the **Config** tab and navigate to *advanced ranger-hive-plugin-properties*.
5. Update the following properties with the values listed in the table below.

**Table 3.17. Hive Plugin Properties**

Configuration Property Name	Value
Ranger service config user	rangerhive lookup@example.com
Ranger service config password	rangerhive lookup
common.name.for.certificate	blank

6. After updating these properties, click **Save** and then restart the Hive service.

### 3.1.5.3. HBase

To enable the Ranger HBase plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerhbaselookup`. Make sure this user is synced to Ranger Admin (under `users/groups` tab in the Ranger Admin UI).
2. Create a Kerberos principal for `rangerhbaselookup` by entering the following command:
  - `kadmin.local -q 'addprinc -pw rangerhbaselookup rangerhbaselookup@example.com'`
3. Navigate to the HBase service.
4. Click the **Config** tab and go to *advanced ranger-hbase-plugin-properties*.
5. Update the following properties with the values listed in the table below.

**Table 3.18. HBase Plugin Properties**

Configuration Property Name	Value
Ranger service config user	<code>rangerhbaselookup@example.com</code>
Ranger service config password	<code>rangerhbaselookup</code>
common.name.for.certificate	blank

6. After updating these properties, click **Save** and then restart the HBase service.

### 3.1.5.4. Knox

To enable the Ranger Knox plugin on a Kerberos-enabled cluster, perform the steps described below.

1. Create the system (OS) user `rangerknoxlookup`. Make sure this user is synced to Ranger Admin (under `Settings>Users/Groups` tab in the Ranger Admin UI).
2. Create a Kerberos principal for `rangerknoxlookup` by entering the following command:
  - `kadmin.local -q 'addprinc -pw rangerknoxlookup rangerknoxlookup@example.com'`
3. Navigate to the Knox service.
4. Click the **Config** tab and navigate to *advanced ranger-knox-plugin-properties*.
5. Update the following properties with the values listed in the table below.


**Table 3.19. Knox Plugin Properties**

Configuration Property Name	Value
Ranger service config user	<code>rangerknoxlookup@example.com</code>
Ranger service config password	<code>rangerknoxlookup</code>

Configuration Property Name	Value
common.name.for.certificate	blank

6. After updating these properties, click **Save** and then restart the Knox service.
7. Open the Ranger Admin UI by entering the following information:
  - `http://ranger-host:6080`
  - **username/password** - `admin/admin`. or use `username` as shown in `advanced ranger-env` under the **Config** tab of the Ranger service, and `password` as shown in **Admin Settings**.
8. After you have successfully logged into the system, you will be redirected to the Access Manager page.

**Figure 3.6. Knox Service Manager**



9. Click the repository (`clusterName_hadoop`) **Edit** option under the HDFS box.

**Figure 3.7. Knox Service Edit**

10. Update the following properties listed in the table below under the Config Properties section:

**Table 3.20. Knox Configuration Properties**

Configuration Property Name	Value
fs.default.name	hdfs
hadoop.rpc.protection	blank
common.name.for.certificate	blank

11. Click **Named Test Connection**. You should see a *Connected Successfully* dialog box appear.

12.Click Save.

## 3.2. Using Ranger to Provide Authorization in Hadoop


Once a user has been authenticated, their access rights must be determined. Authorization defines access rights to resources, or privileges of use (permissions) for users. For example, a user may be allowed to create a policy and view reports, but not allowed to edit users and groups. Ranger authorization controls this access rights process for:

- [Configuring Services \[201\]](#)
- [Policy Management \[218\]](#)
- [Users/Groups and Permissions Administration \[236\]](#)
- [Reports Administration \[246\]](#)


For more information on Ranger authorization, see the [Authorization](#) overview.

### 3.2.1. Opening and Closing the Ranger Console

To open the Ranger Console, log in to the Ranger portal at `http://<your_ranger_server_address>:6080`. To log in, enter your username and password, then click **Sign In**.




Ranger Console Home Page




### Ranger Login Console

Once you log in, your user name is also displayed on the Ranger Console home page.




To log out of the Ranger Console, click your user name in the top menu, then select **Log Out**.




## 3.2.2. Console Operations Summary

The Ranger console controls four types of functions:


- **Service Manager** - (displayed when you log in). You can use the Service Manager page to create and administer resource-based services and policies.




The Access Manager menu includes the Resource Based Policies and Reports menu options.




- **Access Manager > Resource Based Policies** - opens the Service Manager page for resource-based policies. You can use the Service Manager page to create and administer resource-based services and policies.



- **The Audit tab** - monitors user activity at the resource level, and conditional auditing based on users, groups, or time. The Audit page includes the Access, Admin, Login Sessions, and Plugins tabs.



- **The Settings tab** - manages users and groups, and assigns policy permissions to users and groups. The dropdown menu includes the Users/Groups and Permissions menu options.




### 3.2.3. Configuring Services

The Ranger Access Manager is open by default in the Ranger Console. To return to the Access Manager from any tab in the Ranger Console, go to the top left corner of the console and click **Ranger**, **Access Manager**, **Service Manager**, or **Access Manager>Resource Based Policies**.



#### Note

The Ambari Ranger installation procedure automatically configures these services, so there should be no need to add a service manually.



- **To add a new service to Resource Based Policies, click the**



**icon in the applicable box on the Service Manager page.**

Enter the required configuration settings, then click **Add**



).

- To edit a service, click



to the right of the entry for that service. Resource Based Policies displays an expanded view of that service, including a list of the policies it contains, their status, and the groups designated to administer those policies.

- To delete a service from Resource Based Policies, click



to the right of the entry for that service. Deleting a service also deletes all the policies within that service.

### Ranger Service Manager Console

This section describes how to configure services in:

- [Configure an HBase Service \[202\]](#)
- [Configure an HDFS Service \[204\]](#)
- [Configure a Hive Service \[207\]](#)
- [Configure a Kafka Service \[208\]](#)
- [Configure a Knox Service \[210\]](#)
- [Configure a Solr Service \[212\]](#)
- [Configure a Storm Service \[214\]](#)
- [Configure a YARN Service \[216\]](#)

#### 3.2.3.1. Configure an HBase Service

Use the following steps to add a service to HBase:

1. On the Service Manager page, click the



icon next to HBase.

The Create Service page appears.

The screenshot shows the 'Create Service' page in the Ranger Service Manager. The top navigation bar includes 'Ranger', 'Access Manager', 'Audit', and 'Settings'. Below the navigation is a breadcrumb trail: 'Service Manager > Create Service'. The main section is titled 'Create Service' and contains two main sections: 'Service Details' and 'Config Properties'. In the 'Service Details' section, there are fields for 'Service Name \*' (a required text input), 'Description' (a text area), and 'Active Status' (radio buttons for 'Enabled' and 'Disabled', with 'Enabled' selected). In the 'Config Properties' section, there are multiple configuration parameters with dropdown menus: 'hadoop.security.authentication \*' (Simple), 'hbase.master.kerberos.principal' (a dropdown menu), 'hbase.security.authentication \*' (Simple), 'hbase.zookeeper.property.clientPort \*' (2181), 'hbase.zookeeper.quorum \*' (a dropdown menu), 'zookeeper.znode.parent \*' (/hbase), and 'Common Name for Certificate' (a text input). Below these is a table for 'Add New Configurations' with columns 'Name' and 'Value', and a delete button. At the bottom are 'Test Connection' and 'Add' (green) and 'Cancel' buttons.

2. Enter the following information on the Create Service page:

**Table 3.21. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.

Field name	Description
Active Status	Enabled or Disabled.

**Table 3.22. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
hadoop.security.authorization	The complete connection URL, including port and database name. (Default port: 10000.) For example, on the sandbox, jdbc:hive2://sandbox:10000/.
hbase.master.kerberos.principal	The Kerberos principal for the HBase Master. (Required only if Kerberos authentication is enabled.)
hbase.security.authentication	As noted in the hadoop configuration file hbase-site.xml.
hbase.zookeeper.property.clientPort	As noted in the hadoop configuration file hbase-site.xml.
hbase.zookeeper.quorum	As noted in the hadoop configuration file hbase-site.xml.
zookeeper.znode.parent	As noted in the hadoop configuration file hbase-site.xml.
Common Name for Certificate	<p>The name of the certificate.</p> <p>This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.</p>
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

4. Click **Add**.

### 3.2.3.2. Configure an HDFS Service

Use the following steps to add a service to HDFS:

1. On the Service Manager page, click the



icon next to HDFS.

The Create Service page appears.

**Service Details :**

Service Name \*

Description

Active Status  Enabled  Disabled

**Config Properties :**

Username \*

Password \*

Namenode URL \*

Authorization Enabled

Authentication Type \*

hadoop.security.auth\_to\_local

dfs.datanode.kerberos.principal

dfs.namenode.kerberos.principal

dfs.secondary.namenode.kerberos.principal

RPC Protection Type

Common Name for Certificate

Add New Configurations 

Name	Value
<input type="text"/>	<input type="text"/> <input type="button" value="x"/>

- Enter the following information on the Create Service page:

**Table 3.23. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.24. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
Namenode URL	<p>hdfs://NAMENODE_FQDN:8020</p> <p>The location of the Hadoop HDFS service, as noted in the hadoop configuration file core-site.xml OR (if this is a HA environment) the path for the primary NameNode.</p> <p>This field was formerly named fs.defaultFS.</p>
Authorization Enabled	Authorization involves restricting access to resources. If enabled, user need authorization credentials.
Authentication Type	<p>The type of authorization in use, as noted in the hadoop configuration file core-site.xml; either simple or Kerberos. (Required only if authorization is enabled).</p> <p>This field was formerly named hadoop.security.authorization.</p>
hadoop.security.auth_to_local	Maps the login credential to a username with Hadoop; use the value noted in the hadoop configuration file, core-site.xml.
dfs.datanode.kerberos.principal	The principal associated with the datanode where the service resides, as noted in the hadoop configuration file hdfs-site.xml. (Required only if Kerberos authentication is enabled).
dfs.namenode.kerberos.principal	The principal associated with the NameNode where the service resides, as noted in the hadoop configuration file hdfs-site.xml. (Required only if Kerberos authentication is enabled).
dfs.secondary.namenode.kerberos.principal	The principal associated with the secondary NameNode where the service resides, as noted in the hadoop configuration file hdfs-site.xml. (Required only if Kerberos authentication is enabled).
RPC Protection Type	Only authorised user can view, use, and contribute to a dataset. A list of protection values for secured SASL connections. Values: Authentication, Integrity, Privacy
Common Name For Certificate	<p>The name of the certificate.</p> <p>This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.</p>
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

 Test Connection

4. Click **Add**.

 Add

### 3.2.3.3. Configure a Hive Service

Use the following steps to add a service to Hive:

1. On the Service Manager page, click the



next to Hive.

The Create Service page appears.

A screenshot of the 'Create Service' page in the Ranger Service Manager. The top navigation bar includes 'Ranger', 'Access Manager', 'Audit', and 'Settings'. Below it, a breadcrumb trail shows 'Service Manager > Create Service'. The main form is titled 'Create Service' and contains two sections: 'Service Details' and 'Config Properties'.

- Service Details:** Contains fields for 'Service Name \*' (a required text input), 'Description' (a text area), and 'Active Status' (radio buttons for 'Enabled' or 'Disabled').
- Config Properties:** Contains fields for 'Username \*', 'Password \*', 'jdbc.driverClassName \*' (set to 'org.apache.hive.jdbc.HiveDriver'), 'jdbc.url \*', and 'Common Name for Certificate'. It also features a table for 'Add New Configurations' with columns 'Name' and 'Value', and a delete button. A '+' button is available to add more configurations. A 'Test Connection' button is located below the table.

At the bottom of the form are 'Add' and 'Cancel' buttons.

2. Enter the following information on the Create Service page:

**Table 3.25. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.26. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
jdbc.driver ClassName	The full classname of the driver used for Hive connections. Default: org.apache.hive.jdbc.HiveDriver
jdbc.url	The complete connection URL, including port and database name. (Default port: 10000.) For example, on the sandbox, jdbc:hive2://sandbox:10000/.
Common Name For Certificate	<p>The name of the certificate.</p> <p>This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.</p>
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

4. Click **Add**.

### 3.2.3.4. Configure a Kafka Service

Use the following steps to add a service to Kafka:

1. On the Service Manager page, click the



next to Kafka.

The Create Service page appears.

2. Enter the following information on the Create Service page:

**Table 3.27. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.28. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
ZooKeeper Connect String	Defaults to localhost:2181 (Provide FQDN of zookeeper host : 2181).
Ranger Plugin SSL CName	Provide common.name.for.certificate which is registered with Ranger (in Wire Encryption environment).

Field name	Description
	This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

A rectangular button with a thin gray border and a white background. Inside, the text "Test Connection" is centered in a small, black, sans-serif font.

4. Click **Add**.

A small, rounded rectangular button with a green background and white text. The word "Add" is written in a white, sans-serif font.

### 3.2.3.5. Configure a Knox Service

Use the following steps to add a service to Knox:

1. On the Service Manager page, click the



next to Knox.

The Create Service page appears.

2. Enter the following information on the Create Service page:

**Table 3.29. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.30. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
knox.url	The Gateway URL for Knox.
Common Name For Certificate	The name of the certificate.

Field name	Description
	This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

 Test Connection

4. Click **Add**.

 Add

### 3.2.3.6. Configure a Solr Service

Use the following steps to add a service to Solr:

1. On the Service Manager page, click the



next to Solr.

The Create Service page appears.

2. Enter the following information on the Create Service page:

**Table 3.31. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.32. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
Solr URL	<code>http://Solr_host:6083</code>
Ranger Plugin SSL CName	Provide common.name.for.certificate which is registered with Ranger (in Wire Encryption environment).

Field name	Description
	This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

A rectangular button with a thin gray border and a white background. Inside, the text "Test Connection" is centered in a small, black, sans-serif font.

4. Click **Add**.

A small, rounded rectangular button with a green background and white text. The word "Add" is written in a white, sans-serif font.

### 3.2.3.7. Configure a Storm Service

Use the following steps to add a service to Storm:

1. On the Service Manager page, click the



next to Storm.

The Create Service page appears.

2. Enter the following information on the Create Service page:

**Table 3.33. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.34. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
Nimbus URL	Hostname of nimbus format, in the form: http:// <i>ipaddress</i> :8080.  This field was formerly named nimbus.url.
Common Name For Certificate	The name of the certificate.

Field name	Description
	This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.

A rectangular button with a thin gray border and a white background. Inside, the text "Test Connection" is centered in a small, black, sans-serif font.

4. Click **Add**.

A small, rounded rectangular button with a green background and white text. The word "Add" is written in a white, sans-serif font.

### 3.2.3.8. Configure a YARN Service

Use the following steps to add a service to YARN:

1. On the Service Manager page, click the



next to YARN.

The Create Service page appears.

2. Enter the following information on the Create Service page:

**Table 3.35. Service Details**

Field name	Description
Service Name	The name of the service; required when configuring agents.
Description	A description of the service.
Active Status	Enabled or Disabled.

**Table 3.36. Config Properties**

Field name	Description
Username	The end system username that can be used for connection.
Password	The password for the username entered above.
YARN REST URL	Http or https://RESOURCEMANAGER_FQDN:8088.
Authentication Type	The type of authorization in use, as noted in the hadoop configuration file core-site.xml; either simple or Kerberos. (Required only if authorization is enabled).

Field name	Description
	This field was formerly named hadoop.security.authorization.
Common Name For Certificate	The name of the certificate. This field is interchangeably named <b>Common Name For Certificate</b> and <b>Ranger Plugin SSL CName</b> in Create Service pages.
Add New Configurations	Add any other new configuration(s).

3. Click **Test Connection**.



4. Click **Add**.



### 3.2.4. Policy Management

To examine the policies associated with each service, go to the service where the service resides and click



The Ranger Service Manager view appears and an expanded view of that service displays, with the policies listed beneath. The policy view includes a search window.

- To add a new policy to the service, click **Add New Policy**



).

The form looks slightly different, depending on the type of service to which you are adding the policy.

- To edit a policy, click



to the right of the entry for that service. Resource Based Policies displays an expanded view of that policy.

- To delete a policy, click



the

Delete icon to the right of the entry for that service.

The screenshot shows the Ranger Service Manager interface. At the top, there's a navigation bar with 'Ranger', 'Access Manager', 'Audit', 'Settings', and a user icon for 'admin'. Below the navigation is a breadcrumb trail: 'Service Manager > c6401\_TEST\_knox Policies'. A modal window titled 'Add new policy' is open on the right, containing a search bar and a green 'Add New Policy' button. In the center, there's a table titled 'List of Policies : c6401\_TEST\_knox' with one row visible. The table columns are: Policy ID (9), Policy Name (c6401\_TEST\_knox-1-20160203193206), Status (Enabled), Audit Logging (Enabled), Groups, Users, and Action. The 'Action' column contains three icons: a pencil for 'Edit policy', a trash can for 'Delete policy', and a refresh symbol. Red arrows point from the text labels 'Edit policy', 'Delete policy', and 'Add New Policy' to their respective icons in the screenshot.

This section describes the requirements for policy creation in

- [Create an HBase Policy \[219\]](#)
- [Create an HDFS Policy \[221\]](#)
- [Create a Hive Policy \[224\]](#)
- [Create a Kafka Policy \[227\]](#)
- [Create a Knox Policy \[228\]](#)
- [Create a Solr Policy \[230\]](#)
- [Create a Storm Policy \[232\]](#)
- [Create a YARN Policy \[234\]](#)

### 3.2.4.1. Create an HBase Policy

To add a new policy to an existing HBase service:

1. On the Service Manager page, select an existing service under HBase.

The screenshot shows a list of services under the 'HBASE' category. There are two entries: 'hbase-test' and 'c6401\_TEST\_hbase'. Each entry has a small icon, an edit button, and a delete button.

The List of Policies page appears.

The screenshot shows the 'List of Policies' page for the 'Example-Service'. The table has the following data:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users	Action
13	Example-Service-1-20160211205602	Enabled	Enabled		admin	

2. Click **Add New Policy**.



The Create Policy console appears.

The screenshot shows the 'Create Policy' interface for HBase. The 'Policy Details' section includes fields for 'Policy Name' (mandatory), 'HBase Table', 'HBase Column-family', 'HBase Column', and 'Description', each with an 'Include' toggle switch. 'Audit Logging' is set to 'YES'. The 'User and Group Permissions' section contains a table with columns: 'Permissions', 'Select Group', 'Select User', 'Permissions', and 'Delegate Admin'. It includes a 'Select Group' button, a 'Select User' button, an 'Add Permissions' button, and a delete icon. At the bottom are 'Add' and 'Cancel' buttons.

3. Complete the Create Policy page as follows:

**Table 3.37. Policy Details**

Label	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
HBase Table	Select the appropriate database. Multiple databases can be selected for a particular policy. This field is mandatory.
HBase Column-family	For the selected table, specify the column families to which the policy applies.
HBase Column	For the selected table and column families, specify the columns to which the policy applies.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.38. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).

Label	Description
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.

 Add

### 3.2.4.2. Provide User Access to HBase Database Tables from the Command Line

HBase provides the means to manage user access to HBase database tables directly from the command line. The most commonly-used commands are:

- GRANT

Syntax: `grant '<user-or-group>', '<permissions>', '<table>'`

For example, to create a policy that grants user1 read/write permission on the table usertable, the command is `grant 'user1', 'RW', 'usertable'`

The syntax is the same for granting CREATE and ADMIN rights.

- REVOKE

Syntax: `revoke '<user-or-group>', '<usertable>'`

For example, to revoke the read/write access of user1 to the table usertable, the command is `revoke 'user1', 'usertable'`



#### Note

Unlike Hive, HBase has no specific revoke commands for each user privilege.

### 3.2.4.3. Create an HDFS Policy

Through configuration, Apache Ranger enables both Ranger policies and HDFS permissions to be checked for a user request. When the NameNode receives a user request, the Ranger

plugin checks for policies set through the Ranger Service Manager. If there are no policies, the Ranger plugin checks for permissions set in HDFS.

We recommend that permissions be created at the Ranger Service Manager, and to have restrictive permissions at the HDFS level.


To add a new policy to an existing HDFS service:

1. On the Service Manager page, select an existing service under HDFS.



The screenshot shows the 'HDFS' service in the Service Manager. It lists two services: 'test-hdfs' and 'c6401\_TEST\_hadoop'. Each service has edit and delete icons next to it.

The List of Policies page appears.



The screenshot shows the 'List of Policies : Example-Service' page. It includes a search bar, an 'Add New Policy' button, and a table with columns: Policy ID, Policy Name, Status, Audit Logging, Groups, Users, and Action. One policy is listed: Policy ID 13, Policy Name 'Example-Service-1-20160211205602', Status 'Enabled', Audit Logging 'Enabled', Groups empty, Users 'admin', and Action buttons.

2. Click **Add New Policy**.



The Create Policy page appears.

The screenshot shows the 'Create Policy' page in the Ranger Access Manager. At the top, there are tabs for 'Access Manager', 'Audit', and 'Settings'. The 'admin' user is logged in. The breadcrumb navigation shows 'Service Manager > test-hdfs Policies > Create Policy'. The main form has sections for 'Policy Details' and 'User and Group Permissions'. In 'Policy Details', fields include 'Policy Name' (disabled), 'Resource Path' (recursive), 'Description', and 'Audit Logging' (YES). In 'User and Group Permissions', there's a table with columns for 'Permissions', 'Select Group', 'Select User', 'Permissions', and 'Delegate Admin'. Buttons at the bottom include 'Add' and 'Cancel'.

- Complete the Create Policy page as follows:

**Table 3.39. Policy Details**

Field	Description
Policy Name	Enter a unique name for this policy. The name cannot be duplicated anywhere in the system.
Resource Path	Define the resource path for the policy folder/file. To avoid the need to supply the full path OR to enable the policy for all subfolders or files, you can either complete this path using wildcards (for example, /home*) or specify that the policy should be recursive. (See below.)
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.40. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.

Label	Description
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.



### 3.2.4.4. Create a Hive Policy

To add a new policy to an existing Hive service:

1. On the Service Manager page, select an existing service under Hive.

A screenshot of the Service Manager interface. At the top, there's a header with a folder icon and the word "HIVE". Below it, a list shows a service named "c6401 TEST hive" with a green link-like style. To the right of this list are two small icons: a pencil for editing and a trash can for deleting. A cursor arrow points at the "c6401 TEST hive" entry.

The List of Policies page appears.

A screenshot of the "List of Policies : Example-Service" page. The top navigation bar includes tabs for "Ranger", "Access Manager", "Audit", and "Settings", with "admin" selected. Below the navigation is a breadcrumb trail: "Service Manager &gt; Example-Service Policies". The main area is titled "List of Policies : Example-Service". It features a search bar with placeholder text "Search for your policy..." and an "Add New Policy" button. A table lists one policy: "Example-Service-1-20160211205602" (Policy ID 13), which is "Enabled" with "Audit Logging" also enabled. The table columns are: Policy ID, Policy Name, Status, Audit Logging, Groups, Users, and Action. The "Action" column contains edit and delete icons.

2. Click **Add New Policy**.



The Create Policy console appears.

The screenshot shows the 'Create Policy' page in the Ranger Access Manager. The 'Policy Details' section includes fields for 'Policy Name' (mandatory), 'Hive Database' (mandatory), 'Table/UDF' (selected), 'Hive Column', 'Description', and 'Audit Logging'. The 'User and Group Permissions' section has tabs for 'Permissions', 'Select Group', and 'Select User'. A modal window titled 'add/edit permissions' lists various database actions: select, update, Create, Drop, Alter, Index, Lock, All, and Select/Deselect All. Buttons for 'Add Group' and 'Add User' are present, along with an 'Add Permissions' button.

3. Complete the Create Policy page as follows:

**Table 3.41. Policy Details**

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Hive Database	Select the appropriate database. Multiple databases can be selected for a particular policy. This field is mandatory.
Table/UDF Drop-down	To continue adding a table-based policy, keep Table selected. To add a User Defined Function (UDF), select UDF.
Hive Column	For the selected database, select table(s) for which the policy will be applicable.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.42. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).

Label	Description
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.



### Note

The Ranger Hive plugin only protects HiveServer2; Hive CLI is not supported by Ranger.

## 3.2.4.5. Provide User Access to Hive Database Tables from the Command Line

Hive provides the means to manage user access to Hive database tables directly from the command line. The most commonly-used commands are:

- GRANT

Syntax: `grant <permissions> on table <table> to user <user or group>;`

For example, to create a policy that grants user1 SELECT permission on the table default-hivesmoke22074, the command is `grant select on table default.hivesmoke22074 to user user1;`

The syntax is the same for granting UPDATE, CREATE, DROP, ALTER, INDEX, LOCK, ALL and ADMIN rights.

- REVOKE

Syntax: `revoke <permissions> on table <table> from user <user or group>;`

For example, to revoke the SELECT rights of user1 to the table default.hivesmoke22074, the command is `revoke select on table default.hivesmoke22074 from user user1;`

The syntax is the same for revoking UPDATE, CREATE, DROP, ALTER, INDEX, LOCK, ALL and ADMIN rights.

### 3.2.4.6. Create a Kafka Policy

To add a new policy to an existing Kafka service:

1. On the Service Manager page, select an existing service under Kafka.

A screenshot of the Service Manager interface. At the top, there's a header with a folder icon and the word 'KAFKA'. Below it, a list contains a single item: 'c6401 TEST kafka'. To the right of this item are two buttons: a pencil icon for editing and a trash can icon for deleting. A cursor arrow points towards the trash can icon.

The List of Policies page appears.

A screenshot of the 'List of Policies' page. The header includes tabs for 'Ranger', 'Access Manager', 'Audit', and 'Settings', with 'admin' selected. Below the header, a breadcrumb navigation shows 'Service Manager > Example-Service Policies'. The main area is titled 'List of Policies : Example-Service'. It features a search bar and a green 'Add New Policy' button. A table lists one policy: 'Policy ID: 13, Policy Name: Example-Service-1-20160211205602, Status: Enabled, Audit Logging: Enabled, Groups: (empty), Users: admin, Action: (edit, delete)'. The 'Edit' and 'Delete' icons are highlighted with a red box.

2. Click Add New Policy.



The Create Policy console appears.

A screenshot of the 'Create Policy' page. The header includes tabs for 'Ranger', 'Access Manager', 'Audit', and 'Settings', with 'admin' selected. Below the header, a breadcrumb navigation shows 'Service Manager > c6401\_TEST\_kafka Policies > Create Policy'. The main area is titled 'Create Policy'. It has two main sections: 'Policy Details:' and 'User and Group Permissions:'. In 'Policy Details:', fields include 'Policy Name \*' (empty), 'Topic \*' (empty), 'Description' (empty), and 'Audit Logging' set to 'YES'. In 'User and Group Permissions:', there are tabs for 'Permissions', 'Select Group' (with a dropdown menu 'Select Group'), 'Select User' (with a dropdown menu 'Select User'), 'Policy Conditions' (with a 'Add Conditions' button), 'Permissions' (with a 'Add Permissions' button), and 'Delegate Admin' (with a checkbox). At the bottom of the page are 'Add' and 'Cancel' buttons.

3. Complete the Create Policy page as follows:

**Table 3.43. Policy Details**

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Topic	A topic is a category or feed name to which messages are published.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.44. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range,
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.



### 3.2.4.7. Create a Knox Policy

To add a new policy to an existing Knox service:

1. On the Service Manager page, select an existing service under Knox.



The List of Policies page appears.

2. Click Add New Policy.

**Add New Policy**

The Create Policy console appears.

3. Complete the Create Policy page as follows:

**Table 3.45. Policy Details**

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Knox Topology	Enter an appropriate Topology Name.

Field	Description
Knox Service	Enter an appropriate Service Name.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.46. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range,
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Since Knox does not provide a command line methodology for assigning privileges or roles to users, the User and Group Permissions portion of the Knox Create Policy form is especially important.

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.



### 3.2.4.8. Create a Solr Policy

To add a new policy to an existing Solr service:

1. On the Service Manager page, select an existing service under Solr.



The List of Policies page appears.

The screenshot shows the Ranger UI with the title 'List of Policies : Example-Service'. At the top right is the user 'admin'. Below the title is a search bar and an 'Add New Policy' button. A table lists policies with columns: Policy ID, Policy Name, Status, Audit Logging, Groups, Users, and Action. One policy is listed: 'Example-Service-1-20160211205602' with status 'Enabled' and audit logging 'Enabled'. The 'Action' column for this row contains two icons: a pencil and a trash can.

2. Click Add New Policy.



The Create Policy console appears.

The screenshot shows the 'Create Policy' page. At the top right is the user 'admin'. The page has sections for 'Policy Details' and 'User and Group Permissions'. In 'Policy Details', fields include 'Policy Name' (mandatory), 'Solr Collection' (mandatory), 'Description' (optional), and 'Audit Logging' (set to 'YES'). In 'User and Group Permissions', there are tabs for 'Permissions', 'Select Group' (with 'Select Group' and '+'), 'Select User' (with 'Select User'), 'Policy Conditions' (with 'Add Conditions' and '+'), 'Permissions' (with 'Add Permissions' and '+'), and 'Delegate Admin' (with a checkbox and a red 'X' icon). At the bottom are 'Add' and 'Cancel' buttons.

3. Complete the Create Policy page as follows:

**Table 3.47. Policy Details**

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Solr Collection	http://host_ip:6083/solr
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.48. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen

Label	Description
	resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Policy Conditions	Specify IP address range,
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character


4. Click **Add**.



### 3.2.4.9. Create a Storm Policy

To add a new policy to an existing Storm service:

1. On the Service Manager page, select an existing service under Storm.



The List of Policies page appears.

Policy ID	Policy Name	Status	Audit Logging	Groups	Users	Action
13	Example-Service-1-20160211205602	Enabled	Enabled		admin	

2. Click **Add New Policy**.



The Create Policy console appears.

The screenshot shows the 'Create Policy' interface in the Ranger Access Manager. At the top, there are tabs for Service Manager, test-storm Policies, and Create Policy. The main area is titled 'Create Policy'. It contains several input fields: 'Policy Name' (mandatory), 'Storm Topology' (mandatory), 'Description', and 'Audit Logging' (set to YES). Below these are sections for 'User and Group Permissions' with tables for 'Select Group', 'Select User', 'Permissions' (with an 'Add Permissions' button), and 'Delegate Admin'. At the bottom are 'Add' and 'Cancel' buttons.

3. Complete the Create Policy page as follows:

**Table 3.49. Policy Details**

Label	Description
Policy Name	Enter an appropriate policy name. This name is cannot be duplicated across the system. This field is mandatory.
Storm Topology	Enter an appropriate Topology Name.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.50. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Since Storm does not provide a command line methodology for assigning privileges or roles to users, the User and Group Permissions portion of the Storm Create Policy form is especially important.

**Table 3.51. Knox User and Group Permissions**

Actions	Description
File upload	Allows a user to upload files.
Get Nimbus Conf	Allows a user to access Nimbus configurations.
Get Cluster Info	Allows a user to get cluster information.
File Download	Allows a user to download files.
Kill Topology	Allows a user to kill the topology.
Rebalance	Allows a user to rebalance topologies.
Activate	Allows a user to activate a topology.
Deactivate	Allows a user to deactivate a topology.
Get Topology Conf	Allows a user to access a topology configuration.
Get Topology	Allows a user to access a topology.
Get User Topology	Allows a user to access a user topology.
Get Topology Info	Allows a user to access topology information.
Upload New Credential	Allows a user to upload a new credential.
Admin	Provides a user with delegated admin access.

Wild cards can be included in the resource path, in the database name, the table name, or column name:

- \* indicates zero or more occurrences of characters
- ? indicates a single character


#### 4. Click **Add**.



#### 3.2.4.10. Create a YARN Policy

To add a new policy to an existing YARN service:

1. On the Service Manager page, select an existing service under YARN.



The List of Policies page appears.

The screenshot shows the Ranger Access Manager interface. The top navigation bar includes 'Ranger', 'Access Manager', 'Audit', 'Settings', and a user icon labeled 'admin'. Below the navigation is a breadcrumb trail: 'Service Manager > Example-Service Policies > List of Policies : Example-Service'. The main area is titled 'List of Policies : Example-Service'. It features a search bar and a table with columns: Policy ID, Policy Name, Status, Audit Logging, Groups, Users, and Action. One row in the table is selected, showing Policy ID 13, Policy Name 'Example-Service-1-20160211205602', Status 'Enabled', Audit Logging 'Enabled', Groups and Users both containing 'admin', and Action buttons. A prominent green 'Add New Policy' button is located at the bottom right of the table.

2. Click Add New Policy.

**Add New Policy**

The Create Policy console appears.

The screenshot shows the 'Create Policy' page. The top navigation bar includes 'Ranger', 'Access Manager', 'Audit', 'Settings', and a user icon labeled 'admin'. Below the navigation is a breadcrumb trail: 'Service Manager > c6401\_TEST\_yarn Policies > Create Policy'. The main area is titled 'Create Policy'. It has two main sections: 'Policy Details:' and 'User and Group Permissions:'. In 'Policy Details:', there are fields for 'Policy Name \*' (with 'enabled' selected), 'Queue \*' (with 'recursive' selected), 'Description', and 'Audit Logging' (with 'YES' selected). In 'User and Group Permissions:', there is a table with columns: 'Permissions', 'Select Group' (with a dropdown for 'Select Group'), 'Select User' (with a dropdown for 'Select User'), 'Permissions' (with a 'Add Permissions' button and a '+' icon), and 'Delegate Admin' (with a checkbox). At the bottom of the page are 'Add' and 'Cancel' buttons.

3. Complete the Create Policy page as follows:

**Table 3.52. Policy Details**

Field	Description
Policy Name	Enter an appropriate policy name. This name cannot be duplicated across the system. This field is mandatory.
Queue	The fundamental unit of scheduling in yarn.
Recursive	You can indicate whether all files or folders within the existing folder comes under the policy. Can be used instead of wildcard characters.
Description	(Optional) Describe the purpose of the policy.
Audit Logging	Specify whether this policy is audited. (De-select to disable auditing).

**Table 3.53. User and Group Permissions**

Label	Description
Select Group	Specify the group to which this policy applies. To designate the group as an Administrator for the chosen resource, specify Admin permissions. (Administrators can create child policies based on existing policies).
Select User	Specify a particular user to which this policy applies (outside of an already-specified group) OR designate a particular user as Admin for this policy. (Administrators can create child policies based on existing policies).
Permissions	Add or edit permissions: Read, Write, Create, Admin, Select/Deselect All.
Delegate Admin	When a policy is assigned to a user or a group of users those users become the delegated admin. The delegated admin can update, delete the policies. It can also create child policies based on the original policy (base policy).

Wild cards can be included in the resource path, in the database name, the table name, or column name:


- \* indicates zero or more occurrences of characters
- ? indicates a single character

4. Click **Add**.



### 3.2.5. Users/Groups and Permissions Administration

To examine the list of users and groups who can access the Ranger portal or its services, click **Settings>Users/Groups** at the top of the Ranger Console.



The User/sGroup view displays:


- Internal users who can log in to the Ranger portal; created by the Ranger console Service Manager
- External users who can access services controlled by the Ranger portal; created at other systems like Active Directory, LDAP or UNIX, and synched with those systems
- Admins who are the only users with permission to create users and create services, run reports, and perform other administrative tasks. Admins can also create child policies based on the original policy (base policy).

	Group Name	Group Source	Visibility	
public	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group01	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group02	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group03	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group04	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group05	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group06	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>
group07	Internal	Visible	<a href="#">Set Visibility</a>	<a href="#">Add New Group</a>

### 3.2.5.1. Add a User

To add a new user to the user list:

1. Click **Settings>Users/Groups**.



The Users/Groups page appears.

	User Name	Email Address	Role	User Source	Groups	Visibility	Status	
admin			Admin	Internal	--	Visible	Enabled	<a href="#">Set Status</a>
rangerusersync			Admin	Internal	--	Visible	Enabled	<a href="#">Set Status</a>
testuser			User	External	--	Visible	Enabled	<a href="#">Set Status</a>
user0001			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0002			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0003			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0004			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0005			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0006			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0007			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0008			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0009			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>
user0010			User	External	group01	Visible	Enabled	<a href="#">Set Status</a>

2. Click **Add New User**.



The Ranger User Detail page appears.

The screenshot shows the 'User Detail' form for creating a new user in Ranger. The form includes fields for User Name, New Password, Password Confirm, First Name, Last Name, Email Address, and Select Role (set to Admin). The Group field is marked with a red asterisk and contains the placeholder text 'Please select'. A green 'Save' button and a black 'Cancel' button are at the bottom.

3. Add the appropriate user details, then click **Save**.


**Save**

The user is immediately added to the list.

### 3.2.5.2. Edit a User

To edit a user:

1. Click **Settings>Users/Groups**.



The Users/Groups page opens to the Users tab.

	Group Name	Group Source	Visibility
public	Internal	Visible	
group01	Internal	Visible	
group02	Internal	Visible	
group03	Internal	Visible	
group04	Internal	Visible	
group05	Internal	Visible	
group06	Internal	Visible	
group07	Internal	Visible	

2. Choose to edit yourself or another user:

User Name	Email Address	Role	User Source	Groups	Visibility	Status
admin		Admin	Internal	--	Visible	Enabled
rangerusersync		Admin	Internal	--	Visible	Enabled
testuser		User	External	--	Visible	Enabled
user0001		User	External	group01	Visible	Enabled
user0002		User	External	group01	Visible	Enabled
user0003		User	External	group01	Visible	Enabled
user0004		User	External	group01	Visible	Enabled
user0005		User	External	group01	Visible	Enabled
user0006		User	External	group01	Visible	Enabled

- To edit another user: in the User Name column, select the user you wish to edit.

The User Detail page appears.



### Note

You can only fully edit internal users. For external users, you can only edit the user role.


The screenshot shows the 'User Detail' form under 'User Edit'. At the top, there are two tabs: 'Basic Info' (selected) and 'Change Password'. The 'Basic Info' tab contains fields for 'User Name \*' (Mal), 'First Name \*' (Mal), 'Last Name' (empty), 'Email Address' (empty), and 'Select Role \*' (User). Below these fields is a 'Group' section with 'Marketing' and 'UX' selected, and a green pencil icon for editing. At the bottom of the form are 'Save' and 'Cancel' buttons.

You can change everything except the User Name when editing an internal user.

The screenshot shows the 'User Detail' form under 'User Edit'. The 'User Name \*' field is pre-filled with 'user0001'. The other fields ('First Name', 'Last Name', 'Email Address', 'Select Role \*') are empty or show their default values. In the 'Group' section, 'group01' is selected. At the bottom of the form are 'Save' and 'Cancel' buttons.

You can only change the user role when editing an external user.

- To edit your user profile, click **Username>Profile**.



The User Profile page appears.

The screenshot shows the 'User Profile' page. At the top, there are two tabs: 'Basic Info' (which is selected) and 'Change Password'. Below the tabs, there are four input fields: 'First Name \*' with the value 'Admin', 'Last Name \*' with the value 'Last Name', 'Email Address' with the value 'Email Address', and a dropdown menu 'Select Role \*' with the value 'Admin'. At the bottom of the page are two buttons: a green 'Save' button and a black 'Cancel' button.


3. Edit the appropriate details and click **Save**.



### 3.2.5.3. Add a Group

To add a group:

1. Click **Settings>Users/Groups**.



The Users/Groups page opens to the Users tab.

User Name	Email Address	Role	User Source	Groups	Visibility	Status
admin		Admin	Internal	--	Visible	Enabled
rangerusersync		Admin	Internal	--	Visible	Enabled
testuser		User	External	--	Visible	Enabled
user0001		User	External	group01	Visible	Enabled
user0002		User	External	group01	Visible	Enabled
user0003		User	External	group01	Visible	Enabled
user0004		User	External	group01	Visible	Enabled
user0005		User	External	group01	Visible	Enabled
user0006		User	External	group01	Visible	Enabled
user0007		User	External	group01	Visible	Enabled
user0008		User	External	group01	Visible	Enabled
user0009		User	External	group01	Visible	Enabled
user0010		User	External	group01	Visible	Enabled

2. Click the **Groups** sub-tab.

The Groups page appears.

Group Name	Group Source	Visibility
public	Internal	Visible
group01	Internal	Visible
group02	Internal	Visible
group03	Internal	Visible
group04	Internal	Visible
group05	Internal	Visible
group06	Internal	Visible
group07	Internal	Visible

3. Click **Add New Group**

The Group Create page appears.

The screenshot shows the Ranger UI interface. At the top, there's a navigation bar with 'Ranger', 'Access Manager', 'Audit', 'Settings', and a user 'admin'. Below it is a sub-navigation bar for 'Users/Groups' with tabs for 'Users' and 'Groups' (which is selected). A search bar says 'Search for your groups...'. To the right of the search bar are 'Set Visibility' and 'Add New Group' buttons. A red arrow points from the 'Set Visibility' button down to a dropdown menu labeled 'Visibility' which has two options: 'Visible' and 'Visible'. The main area shows a 'Group List' table with columns: 'Group Name', 'Group Source', and 'Visibility'. The table contains four rows: 'public' (Group Source: Internal, Visibility: Visible), 'group01' (Group Source: Internal, Visibility: Visible), 'group02' (Group Source: Internal, Visibility: Visible), and 'group03' (Group Source: Internal, Visibility: Visible). Below the table is a 'Group Detail' form with fields for 'Group Name \*' (containing 'Group 04') and 'Description' (empty). At the bottom of the form are 'Save' and 'Cancel' buttons.


4. Enter a unique name for the group, and an optional description, then click **Save**.

**Save**

### 3.2.5.4. Edit a Group

To edit a group:

1. Click **Settings>Users/Groups**.



The Users/Groups page opens to the Users tab.

User Name	Email Address	Role	User Source	Groups	Visibility	Status
admin		Admin	Internal	--	Visible	Enabled
rangerusersync		Admin	Internal	--	Visible	Enabled
testuser		User	External	--	Visible	Enabled
user0001		User	External	group01	Visible	Enabled
user0002		User	External	group01	Visible	Enabled
user0003		User	External	group01	Visible	Enabled
user0004		User	External	group01	Visible	Enabled
user0005		User	External	group01	Visible	Enabled
user0006		User	External	group01	Visible	Enabled
user0007		User	External	group01	Visible	Enabled
user0008		User	External	group01	Visible	Enabled
user0009		User	External	group01	Visible	Enabled
user0010		User	External	group01	Visible	Enabled

2. Click the **Groups** sub-tab.

**Groups**

The Groups page appears.

Group Name	Group Source	Visibility
public	Internal	Visible
group01	Internal	Visible
group02	Internal	Visible
group03	Internal	Visible
group04	Internal	Visible
group05	Internal	Visible
group06	Internal	Visible
group07	Internal	Visible

3. Select the group name you wish to edit.

	Group Name	Group Source	Visibility
<input type="checkbox"/>	public	Internal	Visible
<input type="checkbox"/>	group01	Internal	Visible
<input type="checkbox"/>	group02	Internal	Visible
<input type="checkbox"/>	group03	Internal	Visible

4. The Group Edit page appears.

Group Detail

Group Name \*

Description

**Save** **Cancel**

5. Edit the appropriate details, then click **Save**.



### 3.2.5.5. Add or Edit Permissions

To add or edit user or group:

1. Click **Settings>Permissions**.

Settings

Users/Groups

Permissions

The Users/Groups page opens to the Permissions page.

The screenshot shows a table titled 'Permissions' under the 'Groups' section. The columns are 'Permissions', 'Groups', 'Users', and 'Action'. The 'Permissions' column lists categories like 'Resource Based Policies', 'Users/Groups', 'Reports', 'Audit', and 'Key Manager'. The 'Groups' column lists groups such as 'rangerusersync', 'keyadmin', 'hive', 'knox', 'amb\_ranger\_admin', and 'ams'. The 'Users' column lists individual users corresponding to each group. The 'Action' column contains edit icons.

2. Click



beside the permission you wish to edit.

The Edit Permission page appears.

The screenshot shows the 'Edit Permission' page for the 'Users/Groups' module. It has sections for 'Policy Details' (Module Name: Users/Groups) and 'User and Group Permissions'. Under 'User and Group Permissions', there are dropdown menus for 'Select Group' and 'Select User'. A dropdown menu for 'Select User' is open, showing options like 'keyadmin', 'hive', 'knox', 'amb\_ranger\_admin', 'ams', 'hdfs', and 'ranger'. At the bottom are 'Save' and 'Cancel' buttons.

3. Edit the necessary fields and click **Save**.



You can select multiple users and groups from the dropdown menus.

### 3.2.6. Reports Administration

The Reports module is used to manage the policies more efficiently as the number of policies grow. The page lists all HDFS, HBase, Hive, YARN, Knox, Storm, Solr, and Kafka policies.

You can edit policies from the Reports module by selecting the Policy ID.

The screenshot shows the Ranger Access Manager interface for editing an HDFS policy. The top navigation bar includes 'Ranger', 'Access Manager', 'Audit', 'Settings', 'Service Manager', 'test-hdfs Policies', and 'Edit Policy'. The main area is titled 'Edit Policy' and contains 'Policy Details' and 'User and Group Permissions' sections. A red arrow points to the 'Policy Details' section. The 'Policy ID' is listed as 'test-hdfs-1-20160202213734' with an 'Enabled' status. The 'Resource Path' is set to '/'. The 'Description' is 'Default Policy for Service: test-hdfs'. Under 'Audit Logging', the 'YES' option is selected. In the 'User and Group Permissions' section, there is a table with columns 'Permissions', 'Select Group', 'Select User', 'Permissions', and 'Delegate Admin'. A single row is shown with 'Select Group' and 'Select User' both set to 'admin', and 'Permissions' set to 'Read, Write, Execute'. At the bottom are 'Save', 'Cancel', and 'Delete' buttons.

### 3.2.6.1. View Reports

To view reports on one or more policies, click **Access Manager>Reports**.



The screenshot shows the Ranger User Access Report interface. At the top, there are navigation links: Access Manager, Audit, Settings, and a user icon labeled "admin". Below the header, a "User Access Report" button is highlighted. The main area is titled "Reports" and contains a "Search Criteria" section with fields for Policy Name, Resource, and Search By (Group dropdown with "Select Group"). A "Search" button is also present. Below this, there are two sections: "HDFS" and "HBASE", each displaying a table of policies.

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
1	test-hdfs-1-20160202213734	Enabled	Enabled		admin
4	c6401_TEST_hadoop-1-201602022306...	Enabled	Enabled		

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
2	hbase-test-1-20160202224128	Enabled	Enabled		admin
3	c6401_TEST_hbase-1-20160202225955	Enabled	Enabled		

### 3.2.6.2. Search Reports

You can search:

- **Policy Name** - The policy name assigned to the policy while creating it.
- **Resource** - The resource path used while creating the policy.
- **Group, Username** - The group and the users to which the policy is assigned.

The screenshot shows the Apache Ranger web interface. At the top, there is a green header bar with the 'Ranger' logo, 'Access Manager', 'Audit', 'Settings', and 'admin' user icon. Below the header, a 'User Access Report' button is highlighted in green. The main content area is titled 'Reports'.

**Search Criteria:**

- Policy Name:
- Resource:
- Search By:
- 

**HDFS:**

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
1	test-hdfs-1-20160202213734	Enabled	Enabled		admin
4	c6401_TEST_hadoop-1-201602022306...	Enabled	Enabled		

**HBASE:**

Policy ID	Policy Name	Status	Audit Logging	Groups	Users
2	hbase-test-1-20160202224128	Enabled	Enabled		admin
3	c6401_TEST_hbase-1-20160202225955	Enabled	Enabled		

### 3.2.7. Special Requirements for High Availability Environments

**Special Requirements for High Availability Environments** In a HA environment, primary and secondary NameNodes must be configured as described in the HDP System Administration Guide.

To enable Ranger in the HDFS HA environment, the HDFS plugin must be set up in each NameNode, and then pointed to the same HDFS service set up in the Security Manager. Any policies created within that HDFS service are automatically synchronized to the primary and secondary NameNodes through the installed Apache Ranger plugin. That way, if the primary NameNode fails, the secondary namenode takes over and the Ranger plugin at that NameNode begins to enforce the same policies for access control.

When creating the service, you must include the `fs.default.name` property must be set to the full hostname of the primary NameNode. If the primary NameNode fails during policy creation, you can then temporarily use the `fs.default.name` of the secondary NameNode in the service details to enable directory lookup for policy creation.

If, while the primary node is down, you wish to create new policies, there is a slight difference in user experience when specifying the resource path. If everything is normal, this is a drop-down menu with selectable paths; however, if your cluster is running from the failover node, there will be no drop-down menu, and you will need to manually enter the path.

Primary NameNode failure does not affect the actual policy enforcement. In this setup for HA, access control is enforced during primary NameNode failure, by the Ranger plugs at the secondary NameNodes.

For **Test Connection** to be successful for HBase and HDFS in a Ranger HA environment, complete the following: In `/etc/ranger/admin`, create a symbolic link between `hbase-site.xml` and `hdfs-site.xml`:

```
cd /etc/ranger/admin
ln -s /etc/hadoop/conf/hdfs-site.xml hdfs-site.xml
ln -s /etc/hbase/conf/hbase-site.xml hbase-site.xml
```

### 3.2.8. Adding a New Component to Apache Ranger

This document provides a general description of how to add a new component to Apache Ranger.

Apache Ranger has three main components:

- **Admin Tool** – Provides web interface & REST API for managing security policies
- **Custom Authorization Module for components** – Provides custom authorization within the (Hadoop) component to enforce the policies defined in Admin Tool
- **UserGroup synchronizer** – Enables the user/group information in Apache Ranger to synchronize with the Enterprise user/group information stored in LDAP or Active directory.

For supporting new component authorization using Apache Ranger, the component details needs to be added to Apache Ranger as follows:

- Add component details to the Admin Tool
- Develop a custom authorization module for the new component

#### Adding Component Details to the Admin Tool

The Apache Ranger Admin tool supports policy management via both a web interface (UI) and support for (public) REST API. In order to support a new component in both the UI and the Server, the Admin Tool needs to be modified.

#### Required UI changes to support the new component:

1. Add a new component template to the Access Manager page (console home page):

Show new component on the Access Manager page i.e home page[#!/policymanager]. Apache Ranger needs to add table template to Service Manager page and make changes in corresponding JS files. Ranger also needs to create a new service type enum to distinguish the component for which the service/policy is created/updated.

For example: Add a table template to PolicyManagerLayout\_tmpl.html file to view the new component on the Access Manager page and make changes in the PolicyManagerLayout.js file related to the new component, such as passing knox service collection data to the PolicyManagerLayout\_tmpl template. Also create a new service type enum (for example, ASSET\_KNOX) in the XAEnums.js file.

2. Add new configuration information to the Service Form:

Add new configuration fields to Service Form [AssetForm.js] as per new component configuration information. This will cause the display of new configuration fields in the corresponding service Create/Update page. Please note that the AssetForm.js is a common file for every component to create/update the service.

For example: Add new field(configuration) information to AssetForm.js and AssetForm\_tmpl.js.

3. Add a new Policy Listing page:

Add a new policy listing page for the new component in the View Policy list. For example: Create a new KnoxTableLayout.js file and add JS-related changes as per the old component[HiveTableLayout.js] to the View Policy listing. Also create a template page, KnoxTableLayout\_tmpl.html.

4. Add a new Policy Create/Update page:

Add a Policy Create/Update page for the new component. Also add a policy form JS file and its template to handle all policy form-related actions for the new component. For example: Create a new KnoxPolicyCreate.js file for Create/Update Knox Policy. Create a KnoxPolicyForm.js file to add knox policy fields information. Also create a corresponding KnoxPolicyForm\_tmpl.html template.

5. Other file changes, as needed:

Make changes in existing common files as per our new component like Router.js, Controller.js, XAUtils.js, FormInputList.js, UserPermissionList.js, XAEnums.js, etc.

**Required server changes for the new component:**

Let's assume that Apache Ranger has three components supported in their portal and we want to introduce one new component, Knox:

1. Create New Service Type

If Apache Ranger is introducing new component i.e Knox, then they will add one new service type for knox. i.e serviceType = "Knox". On the basis of service type, while creating/updating service/policy, Apache Ranger will distinguish for which component this service/policy is created/updated.

## 2. Add new required parameters in existig objects and populate objects

For Policy Creation/Update of any component (i.e HDFS, Hive, Hbase), Apache Ranger uses only one common object, `VXPolicy.` The same goes for the Service Creation/Update of any component: Apache Ranger uses only one common object `VXService.` As Apache Ranger has three components, it will have all the required parameters of all of those three components in `VXPolicy/VXService.` But for Knox, Apache Ranger requires some different parameters which are not there in previous components. Thus, it will add only required parameters into `VXPolicy/VXService` object. When a user sends a request to the Knox create/update policy, they will only send the parameters that are required for Knox to create/update the VXPolicy object.

After adding new parameters into VXPolixy/VXService, Apache Ranger populates the newly-added parameters in corresponding services, so that it can map those objects with Entity Object.

## 3. Add newly-added fields (into database table) related parameters into entity object and populate them

As Apache Ranger is using JPA-EclipseLink for database mapping into java, it is necessary to update the Entity object. For example, if for Knox policy Apache Ranger has added two new fields (`topology` and `service`) into db table `x\_resource`, it will also have to update the entity object of table (i.e `XXResource`), since it is altering table structure.

After updating the entity object Apache Ranger will populate newly-added parameters in corresponding services (i.e XResourceService), so that it can communicate with the client using the updated entity object.

## 4. Change middleware code business logic

After adding and populating newly required parameters for new component, Apache Ranger will have to write business logic into file `AssetMgr`, where it may also need to do some minor changes. For example, if it wants to create a default policy while creating the Service, then on the basis of serviceType, Apache Ranger will create one default policy for the given service. Everything else will work fine, as it is common for all components.

### **Required database changes for the new component:**

For service and policy management, Apache Ranger includes the following tables:

- x\_asset (for service)
- x\_resource (for service)

As written above, if Apache Ranger is introducing new component then it is not required to create individual table in database for each component. Apache Ranger has common tables for all components.

If Apache Ranger has three components and wants to introduce a fourth one, then it will add required fields into these two tables and will map accordingly with java object. For example, for Knox, Apache Ranger will add two fields (`topology`, `service`) into `x\_resource`. After this, it will be able to perform CRUD operation of policy and service for our new component, and also for previous components.

### 3.2.9. Developing a Custom Authorization Module

In the Hadoop ecosystem, each component (i.e., Hive, HBase) has its own authorization implementation and ability to plug in a custom authorization module. To implement the centralized authorization and audit feature for a component, the component should support a customizable (or pluggable) authorization module.

The custom component Authorization Plugin should do the following:

- Provide authorization based on Policies defined in Policy Admin Tool
- Provide audit information based on the authorization decisions

#### Implementing Custom Component Authorization

To implement the custom component authorization plugin, the Ranger common agent framework provides the following functionalities:

- Ability to read all policies from Service Manager for a given service-id
- Ability to log audit information

When the custom authorization module is initialized, the module should do the following:

1. Initiate a REST API call to the “Policy Admin Tool” to retrieve all policies associated with the specific component.
2. Once the policies are available, it should:
  - be built into a custom data structure for enabling the authorization module.
  - kick off the policy updater thread to refresh policies from “Policy Admin Tool” at a regular interval.

When the custom authorization module is called to perform authorization of a component action (such as READ action) on a specific component resource (such as /app folder), the authorization module will:

- **Identify authorization decision** - For each policy:policyList:
  - If (resource in policy <match> auth-requested-resource)
  - If (action-in-policy <match>action-requested)
  - If (current-user or current-user-groups or public-group <allowed> for the policy), Return access-allowed
- **Identify auditing needs** - For each policy:policyList
  - If (resource in policy <match> auth-requested-resource), return policy.isAuditEnabled()

### 3.2.10. Apache Ranger Public REST API

- [Service Definition APIs \[254\]](#)

- [Get Service Definition by ID \[255\]](#)
- [Get Service Definition by Name \[258\]](#)
- [Create Service Definition \[261\]](#)
- [Update Service Definition by ID \[264\]](#)
- [Update Service Definition by Name \[268\]](#)
- [Delete Service Definition by ID \[268\]](#)
- [Delete Service Definition by Name \[268\]](#)
- [Search Service Definitions \[268\]](#)
- [Service APIs \[270\]](#)
  - [Get Service by ID \[270\]](#)
  - [Get Service by Name \[270\]](#)
  - [Create Service \[271\]](#)
  - [Update Service by ID \[271\]](#)
  - [Update Service by Name \[272\]](#)
  - [Delete Service by ID \[272\]](#)
  - [Delete Service by Name \[272\]](#)
  - [Search Services \[273\]](#)
- [Policy APIs \[275\]](#)
  - [Get Policy by ID \[275\]](#)
  - [Get Policy by Service Name and Policy Name \[276\]](#)
  - [Create Policy \[277\]](#)
  - [Update Policy by ID \[279\]](#)
  - [Update Policy by Service Name and Policy Name \[281\]](#)
  - [Delete Policy by ID \[284\]](#)
  - [Delete Policy by Service Name and Policy Name \[284\]](#)
  - [Search Policies in a Service \[284\]](#)

### 3.2.10.1. Service Definition APIs

- [Get Service Definition by ID \[255\]](#)

- [Get Service Definition by Name \[258\]](#)
- [Create Service Definition \[261\]](#)
- [Update Service Definition by ID \[264\]](#)
- [Update Service Definition by Name \[268\]](#)
- [Delete Service Definition by ID \[268\]](#)
- [Delete Service Definition by Name \[268\]](#)
- [Search Service Definitions \[268\]](#)

### 3.2.10.1.1. Get Service Definition by ID

<b>API Name</b>	<b>Get Service Definition</b>
<b>Request Type</b>	<b>GET</b>
<b>Request URL</b>	<b>service/public/v2/api/servicedef/{id}</b>
<b>Request Params</b>	
<b>Response</b>	<pre>{   "accessTypes": [     {       "impliedGrants": [],       "itemId": 1,       "label": "Read",       "name": "read"     },     {       "impliedGrants": [],       "itemId": 2,       "label": "Write",       "name": "write"     },     {       "impliedGrants": [],       "itemId": 3,       "label": "Execute",       "name": "execute"     }   ],   "configs": [     {       "itemId": 1,       "label": "Username",       "mandatory": true,       "name": "username",       "subType": "",       "type": "string",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "itemId": 2,       "label": "Password",       "mandatory": true,       "name": "password",       "subType": "",       "type": "password",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "itemId": 3,       "label": "Namenode URL",       "mandatory": true,       "name": "fs.default.name",       "subType": "",       "type": "string",       "uiHint": ""     }   ] }</pre>

API Name	Get Service Definition
	<pre> "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "defaultValue": "false", "itemId": 4, "label": "Authorization Enabled", "mandatory": true, "name": "hadoop.security. authorization", "subType": "YesTrue:NoFalse", "type": "bool", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "defaultValue": "simple", "itemId": 5, "label": "Authentication Type", "mandatory": true, "name": "hadoop.security. authentication", "subType": "authnType", "type": "enum", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "itemId": 6, "mandatory": false, "name": "hadoop.security. auth_to_local", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "itemId": 7, "mandatory": false, "name": "dfs.datanode.kerberos. principal", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "itemId": 8, "mandatory": false, "name": "dfs.namenode.kerberos. principal", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "itemId": 9, "mandatory": false, "name": "dfs.secondary.namenode. kerberos.principal", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "defaultValue": "authentication", "itemId": 10, </pre>

API Name	Get Service Definition
	<pre> "label": "RPC Protection Type", "mandatory": false, "name": "hadoop.rpc.protection", "subType": "rpcProtection", "type": "enum", "uiHint": "", "validationMessage": "", "validationRegEx": ""  }, { "itemId": 11, "label": "Common Name for Certificate", "mandatory": false, "name": "commonNameForCertificate", "subType": "", "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": ""  }, "contextEnrichers": [], "createTime": 1450756476000, "description": "HDFS Repository", "enums": [ { "defaultIndex": 0, "elements": [ { "itemId": 1, "label": "Simple", "name": "simple" }, { "itemId": 2, "label": "Kerberos", "name": "kerberos" } ], "itemId": 1, "name": "authnType" }, { "defaultIndex": 0, "elements": [ { "itemId": 1, "label": "Authentication", "name": "authentication" }, { "itemId": 2, "label": "Integrity", "name": "integrity" }, { "itemId": 3, "label": "Privacy", "name": "privacy" } ], "itemId": 2, "name": "rpcProtection" } ], "guid": "0d047247-bafe-4cf8-8e9b- d5d377284b2d", "id": 1, "implClass": "org.apache.ranger.services.hdfs. RangerServiceHdfs", "isEnabled": true, "label": "HDFS Repository", "name": "hdfs", "options": {}, "policyConditions": [], "resources": [ </pre>

API Name	Get Service Definition
	<pre>{   "description": "HDFS file or directory path",   "excludesSupported": false,   "itemId": 1,   "label": "Resource Path",   "level": 10,   "lookupSupported": true,   "mandatory": true,   "matcher": "org.apache.ranger.plugin.resourcematcher.RangerPathResourceMatcher",   "matcherOptions": {     "ignoreCase": "false",     "wildCard": "true"   },   "name": "path",   "recursiveSupported": true,   "type": "path",   "uiHint": "",   "validationMessage": "",   "validationRegEx": "" }, "updateTime": 1450756477000, "version": 1 }</pre>

### 3.2.10.1.2. Get Service Definition by Name

API Name	Get Service Definition
Request Type	GET
Request URL	service/public/v2/api/servicedef/name/{name}
Request Params	
Response	<pre>{   "accessTypes": [     {       "impliedGrants": [],       "itemId": 1,       "label": "select",       "name": "select"     },     {       "impliedGrants": [],       "itemId": 2,       "label": "update",       "name": "update"     },     {       "impliedGrants": [],       "itemId": 3,       "label": "Create",       "name": "create"     },     {       "impliedGrants": [],       "itemId": 4,       "label": "Drop",       "name": "drop"     },     {       "impliedGrants": [],       "itemId": 5,       "label": "Alter",       "name": "alter"     },     {       "impliedGrants": [],       "itemId": 6,       "label": "Index",       "name": "index"     },     {       "impliedGrants": []     }   ] }</pre>

API Name	Get Service Definition
	<pre>         "itemId": 7,         "label": "Lock",         "name": "lock"       },       "impliedGrants": [         "select",         "update",         "create",         "drop",         "alter",         "index",         "lock"       ],       "itemId": 8,       "label": "All",       "name": "all"     }   ],   "configs": [     {       "itemId": 1,       "label": "Username",       "mandatory": true,       "name": "username",       "type": "string",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "itemId": 2,       "label": "Password",       "mandatory": true,       "name": "password",       "type": "password",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "defaultValue": "org.apache.hive.jdbc.HiveDriver",       "itemId": 3,       "mandatory": true,       "name": "jdbc.driverClassName",       "type": "string",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "defaultValue": "",       "itemId": 4,       "mandatory": true,       "name": "jdbc.url",       "type": "string",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "itemId": 5,       "label": "Common Name for Certificate",       "mandatory": false,       "name": "commonNameForCertificate",       "type": "string",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     }   ],   "contextEnrichers": [],   "createTime": 1450756479000,   "description": "Hive Server2",   "enums": [] </pre>

API Name	Get Service Definition
	<pre> "guid": "3e1aefb5a-184a-4e82-9d9c-87a5cacc243c", "id": 3, "implClass": "org.apache.ranger.services.hive.RangerServiceHive", "isEnabled": true, "label": "Hive Server2", "name": "hive", "options": {}, "policyConditions": [ { "description": "List of Hive resources", "evaluator": "org.apache.ranger.plugin.conditionevaluator.RangerHiveResourcesAccessedTogetherCondition", "evaluatorOptions": {}, "itemId": 1, "label": "Hive Resources Accessed Together?", "name": "resources-accessed-together" }, ], "resources": [ { "description": "Hive Database", "excludesSupported": true, "itemId": 1, "label": "Hive Database", "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "database", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "description": "Hive Table", "excludesSupported": true, "itemId": 2, "label": "Hive Table", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": { "ignoreCase": "true", "wildCard": "true" }, "name": "table", "parent": "database", "recursiveSupported": false, "type": "string", "uiHint": "", "validationMessage": "", "validationRegEx": "" }, { "description": "Hive UDF", "excludesSupported": true, "itemId": 3, "label": "Hive UDF", "level": 20, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher", } ] </pre>

API Name	Get Service Definition
	<pre> "matcherOptions": {   "ignoreCase": "true",   "wildCard": "true" }, {   "name": "udf",   "parent": "database",   "recursiveSupported": false,   "type": "string",   "uiHint": "",   "validationMessage": "",   "validationRegEx": "" }, {   "description": "Hive Column",   "excludesSupported": true,   "itemId": 4,   "label": "Hive Column",   "level": 30,   "lookupSupported": true,   "mandatory": true,   "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",   "matcherOptions": {     "ignoreCase": "true",     "wildCard": "true" }, {   "name": "column",   "parent": "table",   "recursiveSupported": false,   "type": "string",   "uiHint": "",   "validationMessage": "",   "validationRegEx": "" }, ], "updateTime": 1450756479000, "version": 1 } </pre>

### 3.2.10.1.3. Create Service Definition

API Name	Create Service Definition
Request Type	Post
Request URL	service/public/v2/api/servicedef
Request Params	<pre> {   "accessTypes": [     {       "impliedGrants": [],       "itemId": 1,       "label": "select",       "name": "select"     },     {       "impliedGrants": [],       "itemId": 2,       "label": "update",       "name": "update"     },     {       "impliedGrants": [],       "itemId": 3,       "label": "Create",       "name": "create"     },     {       "impliedGrants": [],       "itemId": 4,       "label": "Drop",       "name": "drop"     },     {       "impliedGrants": [         "select",         "update",         "create"       ]     }   ] } </pre>

API Name	Create Service Definition
	<pre>         "create",         "drop"     ],     "itemId": 5,     "label": "All",     "name": "all" } ], "configs": [ {     "itemId": 1,     "label": "Username",     "mandatory": true,     "name": "username",     "type": "string",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, {     "itemId": 2,     "label": "Password",     "mandatory": true,     "name": "password",     "type": "password",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, ], "contextEnrichers": [], "description": "Test Component", "enums": [], "implClass": "org.apache.ranger.services.test.RangerServiceTest", "isEnabled": true, "label": "Test Component", "name": "test", "options": {}, "policyConditions": [], "resources": [ {     "description": "Root Of Resource Hierarchy for Test Component",     "excludesSupported": true,     "itemId": 1,     "label": "Test Root Resource",     "level": 10,     "lookupSupported": true,     "mandatory": true,     "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",     "matcherOptions": {         "ignoreCase": "true",         "wildCard": "true"     },     "name": "root",     "recursiveSupported": false,     "type": "string",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, {     "description": "Sub Resource for Test Component",     "excludesSupported": true,     "itemId": 2,     "label": "Test sub resource",     "level": 20,     "lookupSupported": true,     "mandatory": true,     "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",     "matcherOptions": {         "ignoreCase": "true",         "wildCard": "true"     } } ] } </pre>

API Name	Create Service Definition
	<pre>         },         "name": "sub",         "parent": "root",         "recursiveSupported": false,         "type": "string",         "uiHint": "",         "validationMessage": "",         "validationRegEx": ""       }     ],     "version": 1 } </pre>
<u>Response</u>	
	<pre> {   "accessTypes": [     {       "impliedGrants": [],       "itemId": 1,       "label": "select",       "name": "select"     },     {       "impliedGrants": [],       "itemId": 2,       "label": "update",       "name": "update"     },     {       "impliedGrants": [],       "itemId": 3,       "label": "Create",       "name": "create"     },     {       "impliedGrants": [],       "itemId": 4,       "label": "Drop",       "name": "drop"     },     {       "impliedGrants": [         "select",         "update",         "create",         "drop"       ],       "itemId": 5,       "label": "All",       "name": "all"     }   ],   "configs": [     {       "itemId": 1,       "label": "Username",       "mandatory": true,       "name": "username",       "type": "string",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     },     {       "itemId": 2,       "label": "Password",       "mandatory": true,       "name": "password",       "type": "password",       "uiHint": "",       "validationMessage": "",       "validationRegEx": ""     }   ],   "contextEnrichers": [],   "createTime": 1451347300617,   "createdBy": "Admin",   "description": "Test Component",   "enums": [] } </pre>

API Name	Create Service Definition
	<pre>     "guid": "f889f2d3-920a-4504-9905-809bbc417902",     "id": 101,     "implClass": "org.apache.ranger.services.test.RangerServiceTest",     "isEnabled": true,     "label": "Test Component",     "name": "test",     "options": {},     "policyConditions": [],     "resources": [         {             "description": "Root Of Resource Hierarchy for Test Component",             "excludesSupported": true,             "itemId": 1,             "label": "Test Root Resource",             "level": 10,             "lookupSupported": true,             "mandatory": true,             "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",             "matcherOptions": {                 "ignoreCase": "true",                 "wildCard": "true"             },             "name": "root",             "recursiveSupported": false,             "type": "string",             "uiHint": "",             "validationMessage": "",             "validationRegEx": ""         },         {             "description": "Sub Resource for Test Component",             "excludesSupported": true,             "itemId": 2,             "label": "Test sub resource",             "level": 20,             "lookupSupported": true,             "mandatory": true,             "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",             "matcherOptions": {                 "ignoreCase": "true",                 "wildCard": "true"             },             "name": "sub",             "parent": "root",             "recursiveSupported": false,             "type": "string",             "uiHint": "",             "validationMessage": "",             "validationRegEx": ""         }     ],     "updateTime": 1451347300618,     "updatedBy": "Admin",     "version": 1 } </pre>

### 3.2.10.1.4. Update Service Definition by ID

API Name	Update Service Definition
Request Type	PUT
Request URL	service/public/v2/api/servicedef/{id}
Request Params	<pre>{     "accessTypes": [         {             "impliedGrants": [],             "itemId": 1,             "label": "select",             "name": "select"         }     ] }</pre>

API Name	Update Service Definition
	<pre>         },         {           "impliedGrants": [],           "itemId": 2,           "label": "update",           "name": "update"         },         {           "impliedGrants": [],           "itemId": 3,           "label": "Create",           "name": "create"         },         {           "impliedGrants": [],           "itemId": 4,           "label": "Drop",           "name": "drop"         },         {           "impliedGrants": [],           "itemId": 5,           "label": "Index",           "name": "index"         },         {           "impliedGrants": [             "select",             "update",             "create",             "drop",             "index"           ],           "itemId": 6,           "label": "All",           "name": "all"         }       ],       "configs": [         {           "itemId": 1,           "label": "Username",           "mandatory": true,           "name": "username",           "type": "string",           "uiHint": "",           "validationMessage": "",           "validationRegEx": ""         },         {           "itemId": 2,           "label": "Password",           "mandatory": true,           "name": "password",           "type": "password",           "uiHint": "",           "validationMessage": "",           "validationRegEx": ""         }       ],       "contextEnrichers": [],       "description": "Test Component",       "enums": [],       "implClass": "org.apache.ranger.services.test.RangerServiceTest",       "isEnabled": true,       "label": "Test Component",       "name": "test",       "options": {},       "policyConditions": [],       "resources": [         {           "description": "Root Of Resource Hierarchy for Test Component",           "excludesSupported": true,           "itemId": 1,           "label": "Test Root Resource",         }       ]     }   </pre>

API Name	Update Service Definition
	<pre> "level": 10, "lookupSupported": true, "mandatory": true, "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher", "matcherOptions": {     "ignoreCase": "true",     "wildCard": "true" }, {     "name": "root",     "recursiveSupported": false,     "type": "string",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, {     "description": "Sub Resource for Test Component",     "excludesSupported": true,     "itemId": 2,     "label": "Test sub resource",     "level": 20,     "lookupSupported": true,     "mandatory": true,     "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",     "matcherOptions": {         "ignoreCase": "true",         "wildCard": "true"     },     "name": "sub",     "parent": "root",     "recursiveSupported": false,     "type": "string",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" } ] } </pre>
Response	
	<pre>{     "accessTypes": [         {             "impliedGrants": [],             "itemId": 1,             "label": "select",             "name": "select"         },         {             "impliedGrants": [],             "itemId": 2,             "label": "update",             "name": "update"         },         {             "impliedGrants": [],             "itemId": 3,             "label": "Create",             "name": "create"         },         {             "impliedGrants": [],             "itemId": 4,             "label": "Drop",             "name": "drop"         },         {             "impliedGrants": [],             "itemId": 5,             "label": "Index",             "name": "index"         },         {             "impliedGrants": [                 "select",                 "update"             ]         }     ] }</pre>

API Name	Update Service Definition
	<pre>         "create",         "drop",         "index"     ],     "itemId": 6,     "label": "All",     "name": "all" } ], "configs": [ {     "itemId": 1,     "label": "Username",     "mandatory": true,     "name": "username",     "type": "string",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, {     "itemId": 2,     "label": "Password",     "mandatory": true,     "name": "password",     "type": "password",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, ], "contextEnrichers": [], "createTime": 1451347301000, "createdBy": "Admin", "description": "Test Component", "enums": [], "guid": "f889f2d3-920a-4504-9905-809bbc417902", "id": 101, "implClass": "org.apache.ranger.services.test.RangerServiceTest", "isEnabled": true, "label": "Test Component", "name": "test", "options": {}, "policyConditions": [], "resources": [ {     "description": "Root Of Resource Hierarchy for Test Component",     "excludesSupported": true,     "itemId": 1,     "label": "Test Root Resource",     "level": 10,     "lookupSupported": true,     "mandatory": true,     "matcher": "org.apache.ranger.plugin.resourcematcher.RangerDefaultResourceMatcher",     "matcherOptions": {         "ignoreCase": "true",         "wildCard": "true"     },     "name": "root",     "recursiveSupported": false,     "type": "string",     "uiHint": "",     "validationMessage": "",     "validationRegEx": "" }, {     "description": "Sub Resource for Test Component",     "excludesSupported": true,     "itemId": 2,     "label": "Test sub resource",     "level": 20,     "lookupSupported": true, </pre>

API Name	Update Service Definition
	<pre>         "mandatory": true,         "matcher": "org.apache.ranger.plugin. resource.matcher.RangerDefaultResourceMatcher",         "matcherOptions": {             "ignoreCase": "true",             "wildCard": "true"         },         "name": "sub",         "parent": "root",         "recursiveSupported": false,         "type": "string",         "uiHint": "",         "validationMessage": "",         "validationRegEx": ""     },     "updateTime": 1451351474321,     "updatedBy": "Admin",     "version": 2 } </pre>

### 3.2.10.1.5. Update Service Definition by Name

API Name	Update Service Definition
Request Type	PUT
Request URL	service/public/v2/api/servicedef/{name}
Request Params	Application/json
	<ul style="list-style-type: none"> <li>Example:</li> </ul>
Response	200-Application/json

### 3.2.10.1.6. Delete Service Definition by ID

API Name	Delete Service Definition
Request Type	DELETE
Request URL	service/public/v2/api/servicedef/{id}
Request Param	
Response	204-No Content

### 3.2.10.1.7. Delete Service Definition by Name

API Name	Delete Service Definition
Request Type	DELETE
Request URL	service/public/v2/api/servicedef/name/{name}
Request Param	
Response	204-No Content

### 3.2.10.1.8. Search Service Definitions

API Name	Search Service Definitions
Request Type	GET
Request URL	service/public/v2/api/servicedef
Request Params	<p>Query Params</p> <p>pageSize int <i>The page size required</i></p> <p>startIndex int <i>The startrecord index</i></p>

API Name	Search Service Definitions
	<pre>serviceType string The service definition names("hdfs", "hive", "hbase", "knox", "storm", "solr", "kafka", "yarn")  isEnabled boolean The enabled status : true if enabled; false otherwise  Example :  pageSize=25&amp;startIndex=0</pre>
Response	
	<pre>[   {     "accessTypes": [       {         "impliedGrants": [],         "itemId": 1,         "label": "Read",         "name": "read"       },       {         "impliedGrants": [],         "itemId": 2,         "label": "Write",         "name": "write"       },       {         "impliedGrants": [],         "itemId": 3,         "label": "Execute",         "name": "execute"       }     ],     "configs": [       {         "itemId": 1,         "label": "Username",         "mandatory": true,         "name": "username",         "subType": "",         "type": "string",         "uiHint": "",         "validationMessage": "",         "validationRegEx": ""       },       ...       {         "description": "Sub Resource for Test Component",         "excludesSupported": true,         "itemId": 2,         "label": "Test sub resource",         "level": 20,         "lookupSupported": true,         "mandatory": true,         "matcher": "org. apache.ranger.plugin.resourcematcher. RangerDefaultResourceMatcher",         "matcherOptions": {           "ignoreCase": "true",           "wildCard": "true"         },         "name": "sub",         "parent": "root",         "recursiveSupported": false,         "type": "string",         "uiHint": "",         "validationMessage": "",         "validationRegEx": ""       }     ],     "updateTime": 1451351474000,     "updatedBy": "Admin",     "version": 2   } ]</pre>

### 3.2.10.2. Service APIs

- [Get Service by ID \[270\]](#)
- [Get Service by Name \[270\]](#)
- [Create Service \[271\]](#)
- [Update Service by ID \[271\]](#)
- [Update Service by Name \[272\]](#)
- [Delete Service by ID \[272\]](#)
- [Delete Service by Name \[272\]](#)
- [Search Services \[273\]](#)

#### 3.2.10.2.1. Get Service by ID

<b>API Name</b>	<b>Get Service</b>
<b>Request Type</b>	<b>GET</b>
<b>Request URL</b>	<b>service/public/v2/api/service/{id}</b>
<b>Request Params</b>	
<b>Response</b>	<pre>{     "configs": {         "fs.default.name": "hdfs://akulkarni-otp-real-final-1.novalocal:8020",         "hadoop.security.auth_to_local": "DEFAULT",         "hadoop.security.authentication": "simple",         "hadoop.security.authorization": "false",         "password": "*****",         "username": "hadoop"     },     "createTime": 1450757397000,     "createdBy": "amb_ranger_admin",     "description": "hdfs repo",     "guid": "ec082eea-0c22-43b8-84e0-129422f689b9",     "id": 1,     "isEnabled": true,     "name": "cl1_hadoop",     "policyUpdateTime": 1450757398000,     "policyVersion": 2,     "tagVersion": 1,     "type": "hdfs",     "updateTime": 1450757398000,     "updatedBy": "amb_ranger_admin",     "version": 3 }</pre>

#### 3.2.10.2.2. Get Service by Name

<b>API Name</b>	<b>Get Service</b>
<b>Request Type</b>	<b>GET</b>
<b>Request URL</b>	<b>service/public/v2/api/service/name/{name}</b>
<b>Request Params</b>	
<b>Response</b>	{

API Name	Get Service
	<pre> "configs": {     "jdbc.driverClassName": "org.apache.hive.jdbc.HiveDriver",     "jdbc.url": "jdbc:hive2://akulkarni-otp-real-final-1.novalocal:10000",     "password": "*****",     "username": "hive" }, "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "description": "hive repo", "guid": "2bca8f98-4859-43c3-a8f4-d31a15f28793", "id": 3, "isEnabled": true, "name": "cli_hive", "policyUpdateTime": 1450757995000, "policyVersion": 4, "tagUpdateTime": 1450916660000, "tagVersion": 74, "type": "hive", "updateTime": 1450757995000, "updatedBy": "amb_ranger_admin", "version": 78 } </pre>

### 3.2.10.2.3. Create Service

API Name	Create Service
Request Type	Post
Request URL	service/public/v2/api/service
Request Params	<pre> {     "configs": {         "password": "*****",         "username": "hadoop"     },     "description": "test service",     "isEnabled": true,     "name": "cli_test",     "type": "test",     "version": 1 } </pre>
Response	<pre> {     "configs": {         "password": "*****",         "username": "hadoop"     },     "createTime": 1451348710255,     "createdBy": "Admin",     "description": "test service",     "guid": "e72cb64d-66d7-4632-b5ae-c6966cb52105",     "id": 6,     "isEnabled": true,     "name": "cli_test",     "tagVersion": 1,     "type": "test",     "updateTime": 1451348710256,     "updatedBy": "Admin",     "version": 1 } </pre>

### 3.2.10.2.4. Update Service by ID

API Name	Update Service
Request Type	PUT

<b>API Name</b>	<b>Update Service</b>
<b>Request URL</b>	service/public/v2/api/service/{id}
<b>Request Params</b>	Application/json
	<ul style="list-style-type: none"> <li>• Example:</li> </ul>
<b>Response</b>	200-Application/json

### 3.2.10.2.5. Update Service by Name

<b>API Name</b>	<b>Update Service</b>
<b>Request Type</b>	PUT
<b>Request URL</b>	service/public/v2/api/service/name/{name}
<b>Request Params</b>	<pre>{   "configs": {     "password": "*****",     "username": "admin"   },   "description": "test service",   "isEnabled": true,   "name": "cli_test",   "type": "test" }</pre>
<b>Response</b>	<pre>{   "configs": {     "password": "*****",     "username": "admin"   },   "createTime": 1451348710000,   "createdBy": "Admin",   "description": "test service",   "guid": "e72cb64d-66d7-4632-b5ae-c6966cb52105",   "id": 6,   "isEnabled": true,   "name": "cli_test",   "policyUpdateTime": 1451351474000,   "policyVersion": 3,   "tagVersion": 1,   "type": "test",   "updateTime": 1451352016713,   "updatedBy": "Admin",   "version": 5 }</pre>

### 3.2.10.2.6. Delete Service by ID

<b>API Name</b>	<b>Delete Service</b>
<b>Request Type</b>	DELETE
<b>Request URL</b>	service/public/v2/api/service/{id}
<b>Request Param</b>	
<b>Response</b>	204-No Content

### 3.2.10.2.7. Delete Service by Name

<b>API Name</b>	<b>Delete Service</b>
<b>Request Type</b>	DELETE
<b>Request URL</b>	service/public/v2/api/service/name/{name}
<b>Request Param</b>	
<b>Response</b>	204-No Content

### 3.2.10.2.8. Search Services

<b>API Name</b>	<b>Search Services</b>
<b>Request Type</b>	GET
<b>Request URL</b>	service/public/v2/api/service
<b>Request Params</b>	<p><b>Query Parameters:</b></p> <p>pageSize int <i>The page size required</i></p> <p>startIndex int <i>The startrecord index</i></p> <p>serviceName string <i>The service name</i></p> <p>serviceNamePartial string <i>Partial service name</i></p> <p>serviceType string <i>The service types(such as "hdfs", "hive", "hbase", "knox", "storm")</i></p> <p>isEnabled boolean <i>The enabled status (true/false): true is enabled, false otherwise</i></p> <p>Example :</p> <p>pageSize=25&amp;startIndex=0</p>
<b>Response</b>	<pre>[     {         "configs": {             "fs.default.name": "hdfs://akulkarni-etc-real-final-1.novalocal:8020",             "hadoop.security.auth_to_local": "DEFAULT",             "hadoop.security.authentication": "simple",             "hadoop.security.authorization": "false",             "password": "*****",             "username": "hadoop"         },         "createTime": 1450757397000,         "createdBy": "amb_ranger_admin",         "description": "hdfs repo",         "guid": "ec082eea-0c22-43b8-84e0-129422f689b9",         "id": 1,         "isEnabled": true,         "name": "cll_hadoop",         "policyUpdateTime": 1450757398000,         "policyVersion": 2,         "tagVersion": 1,         "type": "hdfs",         "updateTime": 1450757398000,         "updatedBy": "amb_ranger_admin",         "version": 3     },     {         "configs": {             "password": "*****",             "username": "yarn",             "yarn.url": "http://akulkarni-etc-real-final-1.novalocal:8088"         },         "createTime": 1450757747000,         "createdBy": "amb_ranger_admin",         "description": "yarn repo",         "guid": "080970a9-2216-4660-962e-2b48046bf87e",         "id": 2,         "isEnabled": true,         "name": "cll_yarn",         "policyUpdateTime": 1450757747000,         "policyVersion": 1,         "tagVersion": 1,         "type": "yarn",         "updateTime": 1450757747000,     } ]</pre>

API Name	Search Services
	<pre> "updatedBy": "amb_ranger_admin", "version": 2 }, {   "configs": {     "jdbc.driverClassName": "org.apache. hive.jdbc.HiveDriver",     "jdbc.url": "jdbc:hive2://akulkarni- etp-real-final-1.novalocal:10000",     "password": "*****",     "username": "hive"   },   "createTime": 1450757992000,   "createdBy": "amb_ranger_admin",   "description": "hive repo",   "guid": "2bca8f98-4859-43c3-a8f4- d31a15f28793",   "id": 3,   "isEnabled": true,   "name": "cli_hive",   "policyUpdateTime": 1450757995000,   "policyVersion": 4,   "tagUpdateTime": 1450916660000,   "tagVersion": 74,   "type": "hive",   "updateTime": 1450757995000,   "updatedBy": "amb_ranger_admin",   "version": 78 }, {   "configs": {     "hadoop.security.authentication": "simple",     "hbase.security.authentication": "simple",     "hbase.zookeeper.property.clientPort": "2181",     "hbase.zookeeper.quorum": "akulkarni- etp-real-final-1.novalocal",     "password": "*****",     "username": "hbase",     "zookeeper.znode.parent": "/hbase- unsecure"   },   "createTime": 1450758200000,   "createdBy": "amb_ranger_admin",   "description": "hbase repo",   "guid": "6495d4c9-cd1b-4bdf-a023- bdc82806186f",   "id": 4,   "isEnabled": true,   "name": "cli_hbase",   "policyUpdateTime": 1450758202000,   "policyVersion": 2,   "tagVersion": 1,   "type": "hbase",   "updateTime": 1450758202000,   "updatedBy": "amb_ranger_admin",   "version": 3 }, {   "configs": {     "password": "*****",     "username": "kafka",     "zookeeper.connect": "akulkarni-etp- real-final-1.novalocal:2181"   },   "createTime": 1450758481000,   "createdBy": "amb_ranger_admin",   "description": "kafka repo",   "guid": "bd25a697-7c45-4c75-b23d- bb02071c98c2",   "id": 5,   "isEnabled": true,   "name": "cli_kafka",   "policyUpdateTime": 1450805416000,   "policyVersion": 2 } </pre>

API Name	Search Services
	<pre>         "tagVersion": 1,         "type": "kafka",         "updateTime": 1450805416000,         "updatedBy": "amb_ranger_admin",         "version": 3     },     {         "configs": {             "password": "*****",             "username": "admin"         },         "createTime": 1451348710000,         "createdBy": "Admin",         "description": "test service",         "guid": "e72cb64d-66d7-4632-b5ae-c6966cb52105",         "id": 6,         "isEnabled": true,         "name": "cl1_test",         "policyUpdateTime": 1451352708000,         "policyVersion": 4,         "tagVersion": 1,         "type": "test",         "updateTime": 1451352708000,         "updatedBy": "Admin",         "version": 6     } ]</pre>

### 3.2.10.3. Policy APIs

- [Get Policy by ID \[275\]](#)
- [Get Policy by Service Name and Policy Name \[276\]](#)
- [Create Policy \[277\]](#)
- [Update Policy by ID \[279\]](#)
- [Update Policy by Service Name and Policy Name \[281\]](#)
- [Delete Policy by ID \[284\]](#)
- [Delete Policy by Service Name and Policy Name \[284\]](#)
- [Search Policies in a Service \[284\]](#)

#### 3.2.10.3.1. Get Policy by ID

API Name	Get Policy
Request Type	Get
Request URL	service/public/v2/api/policy/{id}
Request Params	
Response	<pre> {     "allowExceptions": [],     "createTime": 1450757397000,     "createdBy": "amb_ranger_admin",     "denyExceptions": [],     "denyPolicyItems": [],     "description": "Default Policy for Service: cl1_hadoop",     "guid": "4c2f7afb-23fa-45e9-9b41-29bdc7423b65",     "id": 1,     "isAuditEnabled": true,     "isEnabled": true,     "name": "cl1_hadoop-1-20151222040957",     "policyItems": [ </pre>

API Name	Get Policy
	<pre>{   "accesses": [     {       "isAllowed": true,       "type": "read"     },     {       "isAllowed": true,       "type": "write"     },     {       "isAllowed": true,       "type": "execute"     }   ],   "conditions": [],   "delegateAdmin": true,   "groups": [],   "users": [     "ambari-qa"   ] }, {   "resourceSignature": "6f956063401eda656f1eae8870clfafac",   "resources": {     "path": {       "isExcludes": false,       "isRecursive": true,       "values": [         "/*"       ]     }   },   "service": "cl1_hadoop",   "updateTime": 1450757398000,   "updatedBy": "amb_ranger_admin",   "version": 2 }</pre>

### 3.2.10.3.2. Get Policy by Service Name and Policy Name

API Name	Get Policy
Request Type	Get
Request URL	service/public/v2/api/service/{service-name}/policy/{policy-name}
Request Params	
Response	<pre>{   "allowExceptions": [],   "createTime": 1450757992000,   "createdBy": "amb_ranger_admin",   "denyExceptions": [],   "denyPolicyItems": [],   "description": "Default Policy for Service: cl1_hive",   "guid": "d6218120-1b66-43e6-9fef-9c917a8e9e25",   "id": 4,   "isAuditEnabled": true,   "isEnabled": true,   "name": "cl1_hive-2-20151222041952",   "policyItems": [     {       "accesses": [         {           "isAllowed": true,           "type": "select"         },         {           "isAllowed": true,           "type": "update"         }       ]     }   ] }</pre>

API Name	Get Policy
	<pre>{     "isAllowed": true,     "type": "create" }, {     "isAllowed": true,     "type": "drop" }, {     "isAllowed": true,     "type": "alter" }, {     "isAllowed": true,     "type": "index" }, {     "isAllowed": true,     "type": "lock" }, {     "isAllowed": true,     "type": "all" } ], "conditions": [], "delegateAdmin": true, "groups": [], "users": [     "ambari-qa" ] }, ], "resourceSignature": "c834ed2b8c7462d2aa8bbffdb05226c8", "resources": {     "database": {         "isExcludes": false,         "isRecursive": false,         "values": [             "*"         ]     },     "udf": {         "isExcludes": false,         "isRecursive": false,         "values": [             "*"         ]     } }, "service": "cl1_hive", "updateTime": 1450757995000, "updatedBy": "amb_ranger_admin", "version": 2 }</pre>

### 3.2.10.3.3. Create Policy

API name	Create Policy
Request Type	POST
Request URL	service/public/v2/api/policy
Request Params	<pre>{     "allowExceptions": [],     "denyExceptions": [],     "denyPolicyItems": [         {             "accesses": [                 {                     "isAllowed": true,                     "type": "drop"                 }             ],             "conditions": []         }     ],     "groups": [] }</pre>

API name	Create Policy
	<pre> "conditions": [], "delegateAdmin": true, "groups": [], "users": [   "hadoop" ] }, "description": "Policy for Service: cl1_test", "isAuditEnabled": true, "isEnabled": true, "name": "cl1_test-1", "policyItems": [   {     "accesses": [       {         "isAllowed": true,         "type": "select"       },       {         "isAllowed": true,         "type": "update"       },       {         "isAllowed": true,         "type": "create"       },       {         "isAllowed": true,         "type": "drop"       }     ],     "conditions": [],     "delegateAdmin": true,     "groups": ["public"],     "users": [     ]   } ], "resources": {   "root": {     "isExcludes": false,     "isRecursive": false,     "values": [       "abc"     ]   },   "sub": {     "isExcludes": false,     "isRecursive": false,     "values": [       "**"     ]   } }, "service": "cl1_test", "version": 1 } </pre>
Response	
	<pre> {   "allowExceptions": [],   "createTime": 1451350456093,   "createdBy": "Admin",   "denyExceptions": [],   "denyPolicyItems": [     {       "accesses": [         {           "isAllowed": true,           "type": "drop"         }       ],       "conditions": [],       "delegateAdmin": true,       "groups": [],       "users": [         "hadoop"       ]     }   ] } </pre>

API name	Create Policy
	<pre>         },         "description": "Policy for Service: cl1_test",         "guid": "ff0b3c4a-6aa0-4803-9314-17f3b8950482",         "id": 8,         "isAuditEnabled": true,         "isEnabled": true,         "name": "cl1_test-1",         "policyItems": [           {             "accesses": [               {                 "isAllowed": true,                 "type": "select"               },               {                 "isAllowed": true,                 "type": "update"               },               {                 "isAllowed": true,                 "type": "create"               },               {                 "isAllowed": true,                 "type": "drop"               }             ],             "conditions": [],             "delegateAdmin": true,             "groups": [               "public"             ],             "users": []           }         ],         "resourceSignature": "8a2fac99ba72c687defacff39d6354fb",         "resources": {           "root": {             "isExcludes": false,             "isRecursive": false,             "values": [               "abc"             ]           },           "sub": {             "isExcludes": false,             "isRecursive": false,             "values": [               "*"             ]           }         },         "service": "cl1_test",         "updateTime": 1451350456094,         "updatedBy": "Admin",         "version": 1       }     }   </pre>

### 3.2.10.3.4. Update Policy by ID

API Name	<b>update policy</b>
Request Type	<b>PUT</b>
Request URL	<b>service/public/v2/api/policy/{id}</b>
Request Params	<pre> {   "id": 8,   "allowExceptions": [],   "denyExceptions": [],   "denyPolicyItems": [     {       "accesses": [         ...       ]     }   ] }   </pre>

<b>API Name</b>	<pre> <b>update policy</b>          {             "isAllowed": true,             "type": "drop"         },         "conditions": [],         "delegateAdmin": true,         "groups": [],         "users": [             "admin"         ]     } ], "description": "Policy for Service: cll_test", "isAuditEnabled": true, "isEnabled": true, "name": "cll_test-1", "policyItems": [     {         "accesses": [             {                 "isAllowed": true,                 "type": "select"             },             {                 "isAllowed": true,                 "type": "update"             },             {                 "isAllowed": true,                 "type": "create"             },             {                 "isAllowed": true,                 "type": "drop"             }         ],         "conditions": [],         "delegateAdmin": true,         "groups": ["public"],         "users": [         ]     } ], "resources": {     "root": {         "isExcludes": false,         "isRecursive": false,         "values": [             "abc"         ]     },     "sub": {         "isExcludes": false,         "isRecursive": false,         "values": [             "*"         ]     } }, "service": "cll_test", "version": 1 } </pre>
<b>Response</b>	<pre>{     "allowExceptions": [],     "createTime": 1451350456000,     "createdBy": "Admin",     "denyExceptions": [],     "denyPolicyItems": [         {             "accesses": [                 {                     "isAllowed": true,                     "type": "drop"                 }             ],             "conditions": []         }     ] }</pre>

API Name	update policy
	<pre> "delegateAdmin": true, "groups": [], "users": [     "admin" ] ], "description": "Policy for Service: cli_test", "guid": "ff0b3c4a-6aa0-4803-9314-17f3b8950482", "id": 8, "isAuditEnabled": true, isEnabled": true, "name": "cli_test-1", "policyItems": [ {     "accesses": [         {             "isAllowed": true,             "type": "select"         },         {             "isAllowed": true,             "type": "update"         },         {             "isAllowed": true,             "type": "create"         },         {             "isAllowed": true,             "type": "drop"         }     ],     "conditions": [],     "delegateAdmin": true,     "groups": [         "public"     ],     "users": [] } ], "resourceSignature": "8a2fac99ba72c687defacff39d6354fb", "resources": {     "root": {         "isExcludes": false,         "isRecursive": false,         "values": [             "abc"         ]     },     "sub": {         "isExcludes": false,         "isRecursive": false,         "values": [             "*"         ]     } }, "service": "cli_test", "updateTime": 1451955041580, "updatedBy": "Admin", "version": 3 } </pre>

### 3.2.10.3.5. Update Policy by Service Name and Policy Name

API Name	update policy
Request Type	PUT
Request URL	service/public/v2/api/service/{service-name}/policy/{policy-name}
Request Params	{

<b>API Name</b>	<b>update policy</b>
	<pre> "allowExceptions": [], "denyExceptions": [], "denyPolicyItems": [ {     "accesses": [         {             "isAllowed": true,             "type": "drop"         }     ],     "conditions": [],     "delegateAdmin": true,     "groups": [],     "users": [         "hadoop",         "admin"     ] }, ], "description": "Policy for Service: cl1_test", "isAuditEnabled": true, "isEnabled": true, "name": "cl1_test-1", "policyItems": [ {     "accesses": [         {             "isAllowed": true,             "type": "select"         },         {             "isAllowed": true,             "type": "update"         },         {             "isAllowed": true,             "type": "create"         },         {             "isAllowed": true,             "type": "drop"         }     ],     "conditions": [],     "delegateAdmin": true,     "groups": ["public"],     "users": [     ] } ], "resources": {     "root": {         "isExcludes": false,         "isRecursive": false,         "values": [             "abc"         ]     },     "sub": {         "isExcludes": false,         "isRecursive": false,         "values": [             "*"         ]     } }, "service": "cl1_test", "version": 1 } ] </pre>
	200 - Application/json
<b>Response</b>	{ "allowExceptions": [], "createTime": 1451350456000, "createdBy": "Admin", "denyExceptions": [], "denyPolicyItems": [ 

API Name	update policy
	<pre>{     "accesses": [         {             "isAllowed": true,             "type": "drop"         }     ],     "conditions": [],     "delegateAdmin": true,     "groups": [],     "users": [         "hadoop",         "admin"     ] }, {     "description": "Policy for Service: cl1_test",     "guid": "ff0b3c4a-6aa0-4803-9314-17f3b8950482",     "id": 8,     "isAuditEnabled": true,     "isEnabled": true,     "name": "cl1_test-1",     "policyItems": [         {             "accesses": [                 {                     "isAllowed": true,                     "type": "select"                 },                 {                     "isAllowed": true,                     "type": "update"                 },                 {                     "isAllowed": true,                     "type": "create"                 },                 {                     "isAllowed": true,                     "type": "drop"                 }             ],             "conditions": [],             "delegateAdmin": true,             "groups": [                 "public"             ],             "users": []         }     ],     "resourceSignature": "8a2fac99ba72c687defacff39d6354fb",     "resources": {         "root": {             "isExcludes": false,             "isRecursive": false,             "values": [                 "abc"             ]         },         "sub": {             "isExcludes": false,             "isRecursive": false,             "values": [                 "***"             ]         }     },     "service": "cl1_test",     "updateTime": 1451352707567,     "updatedBy": "Admin",     "version": 2 }</pre>

### 3.2.10.3.6. Delete Policy by ID

<b>API Name</b>	Delete Policy
<b>Request Type</b>	DELETE
<b>Request URL</b>	service/public/v2/api/policy/{id}
<b>Request Params</b>	
<b>Response</b>	204 - No Content

### 3.2.10.3.7. Delete Policy by Service Name and Policy Name

<b>API Name</b>	Delete Policy
<b>Request Type</b>	DELETE
<b>Request URL</b>	service/public/v2/api/policy
<b>Request Params</b>	<u>Query Parameters:</u> servicename string The name of service policyname string The name of policy Example: servicename=service-name&policyname=policy-name
<b>Response</b>	204 - No Content

### 3.2.10.3.8. Search Policies in a Service

<b>API Name</b>	Search Policies in a Service
<b>API Name</b>	Search Policies in a Service
<b>Request Type</b>	GET
<b>Request URL</b>	service/public/v2/api/service/{service-name}/policy
<b>Request Params</b>	<u>Query Parameters:</u> pageSize int <i>The page size required</i> startIndex int <i>The start record index</i> policyName string <i>The Exact Name of the policy</i> policyNamePartial string <i>The Partial Name of the policy</i> policyId string <i>The policy ID</i> polResource string <i>The policy resource value</i> resource:resource-type string <i>The policy resource value for given resource-type</i> user string <i>The user name</i> group string <i>The group name</i> isRecursive boolean <i>The <u>isRecursive</u> property ("true" or "false")</i> isEnabled boolean <i>The enable/disabled property ("true" or "false")</i> Example = pageSize=25&startIndex=0&resource:database=finance
<b>Response</b>	[

API Name	Search Policies in a Service
	<pre>{   "allowExceptions": [],   "createTime": 1450757992000,   "createdBy": "amb_ranger_admin",   "denyExceptions": [],   "denyPolicyItems": [],   "description": "Default Policy for Service: cli_hive",   "guid": "4a322a05-c17f-4d6c-b291-94cae3e6c353",   "id": 3,   "isAuditEnabled": true,   "isEnabled": true,   "name": "cli_hive-1-20151222041951",   "policyItems": [     {       "accesses": [         {           "isAllowed": true,           "type": "select"         },         {           "isAllowed": true,           "type": "update"         },         {           "isAllowed": true,           "type": "create"         },         {           "isAllowed": true,           "type": "drop"         },         {           "isAllowed": true,           "type": "alter"         },         {           "isAllowed": true,           "type": "index"         },         {           "isAllowed": true,           "type": "lock"         },         {           "isAllowed": true,           "type": "all"         }       ],       "conditions": [],       "delegateAdmin": true,       "groups": [],       "users": [         "ambari-qa"       ]     }   ],   "resourceSignature": "6e79c1c989c79b7e53af663d3bdc2de6",   "resources": {     "column": {       "isExcludes": false,       "isRecursive": false,       "values": [         "*"       ]     },     "database": {       "isExcludes": false,       "isRecursive": false,       "values": [         "*"       ]     }   } }</pre>

API Name	Search Policies in a Service
	<pre> "table": {     "isExcludes": false,     "isRecursive": false,     "values": [         "*"     ] }, "service": "cll_hive", "updateTime": 1450757994000, "updatedBy": "amb_ranger_admin", "version": 2 }, { "allowExceptions": [], "createTime": 1450757992000, "createdBy": "amb_ranger_admin", "denyExceptions": [], "denyPolicyItems": [], "description": "Default Policy for Service: cll_hive", "guid": "d6218120-1b66-43e6-9fef-9c917a8e9e25", "id": 4, "isAuditEnabled": true, "isEnabled": true, "name": "cll_hive-2-20151222041952", "policyItems": [ {     "accesses": [         {             "isAllowed": true,             "type": "select"         },         {             "isAllowed": true,             "type": "update"         },         {             "isAllowed": true,             "type": "create"         },         {             "isAllowed": true,             "type": "drop"         },         {             "isAllowed": true,             "type": "alter"         },         {             "isAllowed": true,             "type": "index"         },         {             "isAllowed": true,             "type": "lock"         },         {             "isAllowed": true,             "type": "all"         }     ],     "conditions": [],     "delegateAdmin": true,     "groups": [],     "users": [         "ambari-qa"     ] }, {     "resourceSignature": "c834ed2b8c7462d2aa8bbffdb05226c8",     "resources": {         "database": { </pre>

API Name	Search Policies in a Service
API Name	Search Policies in a Service
	<pre>        "isExcludes": false,         "isRecursive": false,         "values": [           "*"         ],       },       "udf": {         "isExcludes": false,         "isRecursive": false,         "values": [           "*"         ]       },       "service": "cl1_hive",       "updateTime": 1450757995000,       "updatedBy": "amb_ranger_admin",       "version": 2     } ]</pre>

## 4. Data Protection: Wire Encryption

Encryption is applied to electronic information to ensure its privacy and confidentiality. Wire encryption protects data as it moves into, through, and out of an Hadoop cluster over RPC, HTTP, Data Transfer Protocol (DTP), and JDBC:

- *Clients* typically communicate directly with the Hadoop cluster. Data can be protected using RPC encryption or Data Transfer Protocol:
  - **RPC encryption:** Clients interacting directly with the Hadoop cluster through RPC. A client uses RPC to connect to the NameNode (NN) to initiate file read and write operations. RPC connections in Hadoop use Java's Simple Authentication & Security Layer (SASL), which supports encryption.
  - **Data Transfer Protocol:** The NN gives the client the address of the first DataNode (DN) to read or write the block. The actual data transfer between the client and a DN uses Data Transfer Protocol.
- *Users* typically communicate with the Hadoop cluster using a Browser or a command line tools, data can be protected as follows:
  - **HTTPS encryption:** Users typically interact with Hadoop using a browser or component CLI, while applications use REST APIs or Thrift. Encryption over the HTTP protocol is implemented with the support for SSL across a Hadoop cluster and for the individual components such as Ambari.
  - **JDBC:** HiveServer2 implements encryption with Java SASL protocol's quality of protection (QOP) setting. With this the data moving between a HiveServer2 over JDBC and a JDBC client can be encrypted.
- Additionally, within-cluster communication between processes can be protected using HTTPS encryption during MapReduce shuffle:
  - **HTTPS encryption during shuffle:** When data moves between the Mappers and the Reducers over the HTTP protocol, this step is called shuffle. Reducer initiates the connection to the Mapper to ask for data; it acts as an SSL client.

This chapter provides information about configuring and connecting to wire-encrypted components.

For information about configuring HDFS data-at-rest encryption, see [HDFS "Data at Rest" Encryption](#).

### 4.1. Enabling RPC Encryption

The most common way for a client to interact with a Hadoop cluster is through RPC. A client connects to a NameNode over RPC protocol to read or write a file. RPC connections in Hadoop use the Java Simple Authentication and Security Layer (SASL) which supports encryption. When the `hadoop.rpc.protection` property is set to `privacy`, the data over RPC is encrypted with symmetric keys.



### Note

RPC encryption covers not only the channel between a client and a Hadoop cluster but also the inter-cluster communication among Hadoop services.

Enable Encrypted RPC by setting the following properties in `core-site.xml`:

```
hadoop.rpc.protection=privacy
```

(Also supported are the 'authentication' and 'integrity' settings.)

## 4.2. Enabling Data Transfer Protocol

The NameNode gives the client the address of the first DataNode to read or write the block. The actual data transfer between the client and the DataNode is over Hadoop's Data Transfer Protocol. To encrypt this protocol you must set `dfs.encrypt.data.transfer=true` on the NameNode and all DataNodes. The actual algorithm used for encryption can be customized with `dfs.encrypt.data.transfer.algorithm` set to either "3des" or "rc4". If nothing is set, then the default on the system is used (usually 3DES.) While 3DES is more cryptographically secure, RC4 is substantially faster.

Enable Encrypted DTP by setting the following properties in `hdfs-site.xml`:

```
dfs.encrypt.data.transfer=true
dfs.encrypt.data.transfer.algorithm=3des
```

`rc4` is also supported.



### Note

Secondary NameNode is not supported with the HTTPS port. It can only be accessed via `http://<SNN>:50090`.

## 4.3. Enabling SSL: Understanding the Hadoop SSL Keystore Factory

The Hadoop SSL Keystore Factory manages SSL for core services that communicate with other cluster services over HTTP, such as MapReduce, YARN, and HDFS. Other components that have services that are typically not distributed, or only receive HTTP connections directly from clients, use built-in Java JDK SSL tools. Examples include HBase and Oozie.

The following table shows HDP cluster services that use HTTP and support SSL for wire encryption.

**Table 4.1. Components that Support SSL**

Component	Service	SSL Management
HDFS	WebHDFS	Hadoop SSL Keystore Factory
MapReduce	Shuffle	Hadoop SSL Keystore Factory
	TaskTracker	Hadoop SSL Keystore Factory
Yarn	Resource Manager	Hadoop SSL Keystore Factory

Component	Service	SSL Management
	JobHistory	Hadoop SSL Keystore Factory
Oozie		Configured in oozie-site.xml
HBase	REST API	Configured in hbase-site.xml
Hive	HiveServer2	Configured in hive-site.xml
Kafka		JDK: User and default
Solr		JDK: User and default
Accumulo		JDK: User and default
Falcon	REST API	JDK: User and default
Knox	Hadoop cluster (REST client)	JDK: default only
	Knox Gateway server	JDK: User and default
HDP Security Administration	Server/Agent	JDK: User and default

When enabling support for SSL, it is important to know which SSL Management method is being used by the Hadoop service. Services that are co-located on a host must configure the server certificate and keys, and in some cases the client truststore, in the Hadoop SSL Keystore Factory and JDK locations. When using CA signed certificates, configure the Hadoop SSL Keystore Factory to use the Java keystore and truststore locations.

The following list describes major differences between certificates managed by the Hadoop SSL Keystore Management Factory and certificates managed by JDK:

- Hadoop SSL Keystore Management Factory:
  - Supports only JKS formatted keys.
  - Supports toggling the shuffle between HTTP and HTTPS.
  - Supports two way certificate and name validation.
  - Uses a common location for both the keystore and truststore that is available to other Hadoop core services.
  - Allows you to manage SSL in a central location and propagate changes to all cluster nodes.
  - Automatically reloads the keystore and truststore without restarting services.
- SSL Management with JDK:
  - Allows either HTTP or HTTPS.
  - Uses hard-coded locations for truststores and keystores that may vary between hosts. Typically, this requires you to generate key pairs and import certificates on each host.
  - Requires the service to be restarted to reload the keystores and truststores.
  - Requires certificates to be installed in the client CA truststore.



## Note

For more information on JDK SSL Management, see "Using SSL" in [Monitoring and Managing Using JMX Technology](#).

## 4.4. Creating and Managing SSL Certificates

This section contains the following topics:

- Obtaining a certificate from a third-party Certificate Authority (CA)
- Creating an internal CA (OpenSSL)
- Installing Certificates in the Hadoop SSL Keystore Factory (HDFS, MapReduce, and YARN)
- Using an internal CA (OpenSSL)



### Note

For more information about the `keytool` utility, see the Oracle keytool reference: [keytool - Key and Certificate Management Tool](#).

For more information about OpenSSL, see [OpenSSL Documentation](#).



### Note

Java-based Hadoop components such as HDFS, MapReduce, and YARN support JKS format, while Python based services such as Hue use PEM format.

### 4.4.1. Obtain a Certificate from a Trusted Third-Party Certification Authority (CA)

A third-party Certification Authority (CA) accepts certificate requests from entities, authenticates applications, issues certificates, and maintains status information about certificates. Associated cryptography guarantees that a signed certificate is computationally difficult to forge. Thus, as long as the CA is a genuine and trusted authority, clients have high assurance that they are connecting to the machines that they are attempting to connect with.

To obtain a certificate signed by a third-party CA, generate and submit a Certificate Signing Request (CSR) for each cluster node:

1. From the service user account associated with the component (such as `hive`, `hbase`, `oozie`, or `hdfs`, shown below as `<service_user>`), generate the host key:

```
su -l <service_user> -C "keytool -keystore <client-keystore> -genkey -alias <host>"
```

2. At the prompts, enter the information required by the CSR.



### Note

Request generation information and requirements vary depending on the certificate authority. Check with your CA for details.

Example using default keystore `keystore.jks`:

```
su -l hdfs -c "keytool -keystore keystore.jks -genkey -alias n3"
```

```
Enter keystore password: *****
What is your first and last name?
[Unknown]: hortonworks.com
What is the name of your organizational unit?
[Unknown]: Development
What is the name of your organization?
[Unknown]: Hortonworks
What is the name of your City or Locality?
[Unknown]: SantaClara
What is the name of your State or Province?
[Unknown]: CA
What is the two-letter country code for this unit?
[Unknown]: US
Is <CN=hortonworks.com, OU=Development, O=Hortonworks, L=SantaClara, ST=CA, C=US correct?
[no]: yes

Enter key password for <host>
(RTURN if same as keystore password):
```

By default, keystore uses JKS format for the keystore and truststore. The keystore file is created in the user's home directory. Access to the keystore requires the password and alias.

3. Verify that the key was generated; for example:

```
su -l hdfs -c "keytool -list -v -keystore keystore.jks"
```

4. Create the CSR file:

```
su -l hdfs -c "keytool -keystore <keystorename> -certreq -alias <host> -keyalg rsa -file <host>.csr"
```

This command generates a certificate signing request that can be sent to a CA. The file <host>.csr contains the CSR.

The CSR is created in the user's home directory.

5. Confirm that the keystore.jks and <host>.csr files exist by running the following command and making sure that the files are listed in the output:

```
su -l hdfs -c "ls ~/"
```

6. Submit the CSR to your Certificate Authority.

7. To import and install keys and certificates, follow the instructions sent to you by the CA.

## 4.4.2. Create and Set Up an Internal CA (OpenSSL)

OpenSSL provides tools to allow you to create your own private certificate authority.

Considerations:

- The encryption algorithms may be less secure than a well-known, trusted third-party.
- Unknown CAs require that the certificate be installed in corresponding client truststores.



## Note

When accessing the service from a client application such as HiveCLI or cURL, the CA must resolve on the client side or the connection attempt may fail. Users accessing the service through a browser will be able to add an exception if the certificate cannot be verified in their local truststore.

Prerequisite: Install openssl. For example, on CentOS run `yum install openssl`.

To create and set up a CA:

1. Generate the key and certificate for a component process.

The first step in deploying HTTPS for a component process (for example, Kafka broker) is to generate the key and certificate for each node in the cluster. You can use the Java keytool utility to accomplish this task. Start with a temporary keystore, so that you can export and sign it later with the CA.

Use the following keytool command to create the key and certificate:

```
$ keytool -keystore <keystore-file> -alias localhost -validity <validity> -genkey
```

where:

<keystore-file> is the keystore file that stores the certificate. The keystore file contains the private key of the certificate; therefore, it needs to be kept safely.

<validity> is the length of time (in days) that the certificate will be valid.

Make sure that the common name (CN) matches the fully qualified domain name (FQDN) of the server. The client compares the CN with the DNS domain name to ensure that it is indeed connecting to the desired server, not a malicious server.

2. Create the Certificate Authority (CA)

After step 1, each machine in the cluster has a public-private key pair and a certificate that identifies the machine. The certificate is unsigned, however, which means that an attacker can create such a certificate to pretend to be any machine.

To prevent forged certificates, it is very important to sign the certificates for each machine in the cluster.

A CA is responsible for signing certificates, and associated cryptography guarantees that a signed certificate is computationally difficult to forge. Thus, as long as the CA is a genuine and trusted authority, the clients have high assurance that they are connecting to the machines that they are attempting to connect with.

Here is a sample openssl command to generate a CA:

```
openssl req -new -x509 -keyout ca-key -out ca-cert -days 365
```

The generated CA is simply a public-private key pair and certificate, intended to sign other certificates.

3. Add the generated CA to the *server's* truststore:

```
keytool -keystore server.truststore.jks -alias CARoot -import -file ca-cert
```

4. Add the generated CA to the *client's* truststore, so that clients know that they can trust this CA:

```
keytool -keystore client.truststore.jks -alias CARoot -import -file ca-cert
```

In contrast to the keystore in step 1 that stores each machine's own identity, the truststore of a client stores all of the certificates that the client should trust. Importing a certificate into one's truststore also means trusting all certificates that are signed by that certificate.

Trusting the CA means trusting all certificates that it has issued. This attribute is called a "chain of trust," and is particularly useful when deploying SSL on a large cluster. You can sign all certificates in the cluster with a single CA, and have all machines share the same truststore that trusts the CA. That way all machines can authenticate all other machines.

5. Sign all certificates generated in Step 1 with the CA generated in Step 2:

a. Export the certificate from the keystore:

```
keytool -keystore server.keystore.jks -alias localhost -certreq -file cert-file
```

b. Sign the certificate with the CA:

```
openssl x509 -req -CA ca-cert -CAkey ca-key -in cert-file -out cert-signed -days <validity> -CAcreateserial -passin pass:<ca-password>
```

6. Import the CA certificate and the signed certificate into the keystore. For example:

```
$ keytool -keystore server.keystore.jks -alias CARoot -import -file ca-cert
$ keytool -keystore server.keystore.jks -alias localhost -import -file cert-signed
```

The parameters are defined as follows:

Parameter	Description
keystore	The location of the keystore
ca-cert	The certificate of the CA
ca-key	The private key of the CA
ca-password	The passphrase of the CA
cert-file	The exported, unsigned certificate of the server
cert-signed	The signed certificate of the server

All of the preceding steps can be placed into a bash script.

In the following example, note that one of the commands assumes a password of test1234. Specify your own password before running the script.

```
#!/bin/bash

#Step 1
keytool -keystore server.keystore.jks -alias localhost -validity 365 -genkey
```

```
#Step 2
openssl req -new -x509 -keyout ca-key -out ca-cert -days 365
keytool -keystore server.truststore.jks -alias CARoot -import -file ca-cert
keytool -keystore client.truststore.jks -alias CARoot -import -file ca-cert

#Step 3
keytool -keystore server.keystore.jks -alias localhost -certreq -file cert-
file
openssl x509 -req -CA ca-cert -CAkey ca-key -in cert-file -out cert-signed -
days 365 -CAcreateserial -passin pass:test1234
keytool -keystore server.keystore.jks -alias CARoot -import -file ca-cert
keytool -keystore server.keystore.jks -alias localhost -import -file cert-
signed
```

To finish the setup process:

1. Set up the CA directory structure:

```
mkdir -m 0700 /root/CA /root/CA/certs /root/CA/crl /root/CA/newcerts /root/
CA/private
```

2. Move the CA key to /root/CA/private and the CA certificate to /root/CA/certs.

```
mv ca.key /root/CA/private;mv ca.crt /root/CA/certs
```

3. Add required files:

```
touch /root/CA/index.txt; echo 1000 >> /root/CA/serial
```

4. Set permissions on the ca.key:

```
chmod 0400 /root/ca/private/ca.key
```

5. Open the OpenSSL configuration file:

```
vi /etc/pki/tls/openssl.cnf
```

6. Change the directory paths to match your environment:

```
[CA_default]

dir = /root/CA # Where everything is kept
certs = /root/CA/certs # Where the issued certs are
kept
crl_dir = /root/CA/crl # Where the issued crl are kept
database = /root/CA/index.txt # database index file.
#unique_subject = no # Set to 'no' to allow creation
of
several certificates with same
subject.
new_certs_dir = /root/CA/newcerts # default place for new certs.

certificate = /root/CA/cacert.pem # The CA certificate
serial = /root/CA/serial # The current serial number
crlnumber = /root/CA/crlnumber # the current crl number
must be commented out to leave
a V1 CRL
crl = $dir/crl.pem # The current CRL
private_key = /root/CA/private/cakey.pem # The private key
```

```
RANDFILE = /root/CA/private/.rand # private random number file
x509_extensions = usr_cert # The extensions to add to the cert
```

## 7. Save the changes and restart OpenSSL.

Example of setting up an OpenSSL internal CA:

```
openssl genrsa -out ca.key 8192; openssl req -new -x509 -extensions v3_ca -key ca.key -out ca.crt -days 365

Generating RSA private key, 8192 bit long modulus
..
e is 65537 (0x10001)
You are about to be asked to enter information that will be incorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.

Country Name (2 letter code) [XX]:US
State or Province Name (full name) []:California
Locality Name (eg, city) [Default City]:SantaClara
Organization Name (eg, company) [Default Company Ltd]:Hortonworks
Organizational Unit Name (eg, section) []:
Common Name (eg, your name or your server's hostname) []:nn
Email Address []:it@hortonworks.com

mkdir -m 0700 /root/CA /root/CA/certs /root/CA/crl /root/CA/newcerts /root/CA/
private
ls /root/CA
certs crl newcerts private
```

### 4.4.3. Installing Certificates in the Hadoop SSL Keystore Factory (HDFS, MapReduce, and YARN)

HDFS, MapReduce, and YARN use the Hadoop SSL Keystore Factory to manage SSL Certificates. This factory uses a common directory for server keystore and client truststore. The Hadoop SSL Keystore Factory allows you to use CA certificates managed in their own stores.

#### 1. Create a directory for the server and client stores.

```
mkdir -p <SERVER_KEY_LOCATION> ; mkdir -p <CLIENT_KEY_LOCATION>
```

#### 2. Import the server certificate from each node into the HTTP Factory truststore.

```
cd <SERVER_KEY_LOCATION> ; keytool -import -noprompt -alias <remote-
hostname> -file <remote-hostname>.jks -keystore <TRUSTSTORE_FILE> -storepass
<SERVER_TRUSTSTORE_PASSWORD>
```

#### 3. Create a single truststore file containing the public key from all certificates, by importing the public key for each CA or from each self-signed certificate pair:

```
keytool -import -noprompt -alias <host> -file $CERTIFICATE_NAME -keystore
<ALL_JKS> -storepass <CLIENT_TRUSTSTORE_PASSWORD>
```

4. Copy the keystore and truststores to every node in the cluster.
5. Validate the common truststore file on all hosts.

```
keytool -list -v -keystore <ALL_JKS> -storepass <CLIENT_TRUSTSTORE_PASSWORD>
```

6. Set permissions and ownership on the keys:

```
chgrp -R <YARN_USER>:hadoop <SERVER_KEY_LOCATION>
chgrp -R <YARN_USER>:hadoop <CLIENT_KEY_LOCATION>
chmod 755 <SERVER_KEY_LOCATION>
chmod 755 <CLIENT_KEY_LOCATION>
chmod 440 <KEYSTORE_FILE>
chmod 440 <TRUSTSTORE_FILE>
chmod 440 <CERTIFICATE_NAME>
chmod 444 <ALL_JKS>
```



#### Note

The complete path of the <SERVER\_KEY\_LOCATION> and the <CLIENT\_KEY\_LOCATION> from the root directory /etc must be owned by the yarn user and the hadoop group.

### 4.4.4. Using a CA-Signed Certificate

To use a CA-signed certificate:

1. Run the following command to create a self-signing rootCA and import the rootCA into the client truststore. This is a private key; it should be kept private. The following command creates a 2048-bit key:

```
openssl genrsa -out <clusterCA>.key 2048
```

2. Self-sign the rootCA. The following command signs for 300 days. It will start an interactive script that requests name and location information.

```
openssl req -x509 -new -key <clusterCA>.key -days 300 -out <clusterCA>
```

3. Import the rootCA into the client truststore:

```
keytool -importcert -alias <clusterCA> -file $clusterCA -keystore
<clustertruststore> -storepass <clustertruststorekey>
```



#### Note

Make sure that the `ssl-client.xml` file on every host is configured to use this `$clustertrust` store.

When configuring with Hive point to this file; when configuring other services install the certificate in the Java truststore.

4. For each host, sign the certreq file with the rootCA:

```
openssl x509 -req -CA $clusterCA.pem -CAkey <clusterCA>.key -in <host>.cert
-out $host.signed -days 300 -CAcreateserial
```

5. On each host, import the rootCA and the signed cert back in:

```
keytool -keystore <hostkeystore> -storepass <hoststorekey> -alias
<clusterCA> -import -file cluster1CA.pem
keytool -keystore <hostkeystore> -storepass <hoststorekey> -alias `hostname
-s` -import -file <host>.signed -keypass <hostkey>
```

## 4.5. Enabling SSL for HDP Components

The following table contains links to instructions for enabling SSL on specific HDP components.



### Note

These instructions assume that you have already created keys and signed certificates for each component of interest, across your cluster. (See [Section 4.3, "Enabling SSL: Understanding the Hadoop SSL Keystore Factory" \[289\]](#) for more information.)

**Table 4.2. Configure SSL Data Protection for HDP Components**

HDP Component	Notes/Link
Hadoop, MapReduce, YARN	<a href="#">Section 4.1, "Enabling RPC Encryption" [288]</a> ; <a href="#">Section 4.6, "Enable SSL for WebHDFS, MapReduce Shuffle, and YARN" [298]</a>
Oozie	<a href="#">Section 4.8, "Enable SSL on Oozie" [302]</a>
HBase	<a href="#">Section 4.9, "Enable SSL on the HBase REST Server" [303]</a>
Hive (HiveServer2)	<a href="#">Section 4.11, "Enable SSL on HiveServer2" [306]</a>
Kafka	<a href="#">Section 4.12, "Enable SSL for Kafka Clients" [307]</a>
Ambari Server	<a href="#">Set Up SSL for Ambari</a>
Falcon	Enabled by default (see <a href="#">Installing the Falcon Package</a> )
Sqoop	Clients of Hive and HBase, see <a href="#">Data Integration Services with HDP, Apache Sqoop Connectors</a>
Knox Gateway	<a href="#">Knox Administrator Guide</a> , <a href="#">Gateway Security</a> , <a href="#">Configure Wire Encryption</a>
Flume	<a href="#">Apache Flume User Guide</a> , <a href="#">Flume Sources</a>
Accumulo	<a href="#">Apache Foundation Blog</a> , <a href="#">Apache Accumulo: Generating Keystores for configuring Accumulo with SSL</a>
Phoenix	<a href="#">Non-Ambari Cluster Installation</a> , <a href="#">Installing Apache Phoenix: Configuring Phoenix for Security</a> and <a href="#">Apache Phoenix, Flume Plug-in</a>
HUE	<a href="#">Non-Ambari Cluster Installation</a> , <a href="#">Installing Hue</a> , <a href="#">Configure Hue</a>

## 4.6. Enable SSL for WebHDFS, MapReduce Shuffle, and YARN

This section explains how to set up SSL for WebHDFS, YARN and MapReduce. Before you begin, make sure that the SSL certificate is properly configured, including the keystore and truststore that will be used by WebHDFS, MapReduce, and YARN.

HDP supports the following SSL modes:

- One-way SSL: SSL client validates the server identity only.
- Mutual authentication (2WAY SSL): The server and clients validate each others' identities. 2WAY SSL can cause performance delays and is difficult to set up and maintain.



### Note

In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide](#), [Gateway Security](#), [Configure Wire Encryption](#).

To enable one-way SSL set the following properties and restart all services:

1. Set the following property values (or add the properties if required) in `core-site.xml`:

```
hadoop.ssl.require.client.cert=false
hadoop.ssl.hostname.verifier=DEFAULT
hadoop.ssl.keystores.factory.class=org.apache.hadoop.security.ssl.FileBasedK
hadoop.ssl.server.conf=ssl-server.xml
hadoop.ssl.client.conf=ssl-client.xml
```



### Note

Specify the `hadoop.ssl.server.conf` and `hadoop.ssl.client.conf` values as the relative or absolute path to Hadoop SSL Keystore Factory configuration files. If you specify only the file name, put the files in the same directory as the `core-site.xml`.

2. Set the following properties (or add the properties if required) in `hdfs-site.xml`:

- `dfs.http.policy=<Policy>`
- `dfs.client.https.need-auth=true` (optional for mutual client/server certificate validation)
- `dfs.datanode.https.address=<hostname>:50475`
- `dfs.namenode.https-address=<hostname>:50470`

where `<Policy>` is either:

- `HTTP_ONLY`: service is provided only on HTTP
- `HTTPS_ONLY`: service is provided only on HTTPS
- `HTTP_AND_HTTPS`: service is provided both on HTTP and HTTPS

3. Set the following properties in `mapred-site.xml`:

```
mapreduce.jobhistory.http.policy=HTTPS_ONLY
```

```
mapreduce.jobhistory.webapp.https.address=<JHS>:<JHS_HTTPS_PORT>
```

4. Set the following properties in `yarn-site.xml`:

```
yarn.http.policy=HTTPS_ONLY
yarn.log.server.url=https://<JHS>:<JHS_HTTPS_PORT>/jobhistory/logs
yarn.resourcemanager.webapp.https.address=<RM>:<RM_HTTPS_PORT>
yarn.nodemanager.webapp.https.address=0.0.0.0:<NM_HTTPS_PORT>
```

5. Create an `ssl-server.xml` file for the Hadoop SSL Keystore Factory:

- a. Copy the example SSL Server configuration file and modify the settings for your environment:

```
cp /etc/hadoop/conf/ssl-server.xml.example /etc/hadoop/conf/ssl-server.xml
```

- b. Configure the server SSL properties:

**Table 4.3. Configuration Properties in `ssl-server.xml`**

Property	Default Value	Description
<code>ssl.server.keystore.type</code>	JKS	The type of the keystore, JKS = Java Keystore, the de-facto standard in Java
<code>ssl.server.keystore.location</code>	None	The location of the keystore file
<code>ssl.server.keystore.password</code>	None	The password to open the keystore file
<code>ssl.server.truststore.type</code>	JKS	The type of the trust store
<code>ssl.server.truststore.location</code>	None	The location of the truststore file
<code>ssl.server.truststore.password</code>	None	The password to open the truststore

For example:

```
<property>
 <name>ssl.server.truststore.location</name>
 <value>/etc/security/serverKeys/truststore.jks</value>
 <description>Truststore to be used by NN and DN. Must be specified.</description>
</property>

<property>
 <name>ssl.server.truststore.password</name>
 <value>changeit</value>
 <description>Optional. Default value is "".
 </description>
</property>

<property>
 <name>ssl.server.truststore.type</name>
 <value>jks</value>
 <description>Optional. The keystore file format, default value is "jks".</description>
</property>

<property>
 <name>ssl.server.truststore.reload.interval</name>
```

```
<value>10000</value>
<description>Truststore reload check interval, in milliseconds.
Default value is 10000 (10 seconds).</description>
</property>

<property>
<name>ssl.server.keystore.location</name>
<value>/etc/security/serverKeys/keystore.jks</value>
<description>Keystore to be used by NN and DN. Must be specified.</description>
</property>

<property>
<name>ssl.server.keystore.password</name>
<value>changeit</value>
<description>Must be specified.</description>
</property>

<property>
<name>ssl.server.keystore.keypassword</name>
<value>changeit</value>
<description>Must be specified.</description>
</property>

<property>
<name>ssl.server.keystore.type</name>
<value>jks</value>
<description>Optional. The keystore file format, default value is
"jks".</description>
</property>
```

6. Create an `ssl-client.xml` file for the Hadoop SSL Keystore Factory:

a. Copy the client truststore example file:

```
cp /etc/hadoop/conf/ssl-server.xml.example /etc/hadoop/conf/ssl-server.xml
```

b. Configure the client trust store values:

```
ssl.client.truststore.location=/etc/security/clientKeys/all.jks
ssl.client.truststore.password=clientTrustStorePassword
ssl.client.truststore.type=jks
```

7. Copy the configuration files (`core-site.xml`, `hdfs-site.xml`, `mapred-site.xml`, `yarn-site.xml`, `ssl-server.xml`, and `ssl-client.xml`), including the `ssl-server` and `ssl-client` store files if the Hadoop SSL Keystore Factory uses its own keystore and truststore files, to all nodes in the cluster.

8. Restart services on all nodes in the cluster.

## 4.7. Enable SSL for HttpFS

Use the following steps to configure [HttpFS](#) to work over SSL.

1. Edit the `httpfs-env.sh` script in the configuration directory and set `HTTPFS_SSL_ENABLED` to true.

In addition, the following 2 properties can be defined (shown here with default values):

- `HTTPFS_SSL_KEYSTORE_FILE=$HOME/.keystore`
- `HTTPFS_SSL_KEYSTORE_PASS=password`

2. In the `HttpFS tomcat/conf` directory, replace the `server.xml` file with the `ssl-server.xml` file.
3. Create an SSL certificate for the HttpFS server. As the `httpfs` Unix user, use the Java keytool command to create the SSL certificate:

```
$ keytool -genkey -alias tomcat -keyalg RSA
```

You will be asked a series of questions in an interactive prompt. It will create the keystore file, which will be named `.keystore` and located in the `httpfs` user home directory.

The password you enter for "keystore password" must match the value of the `HTTPFS_SSL_KEYSTORE_PASS` environment variable set in the `httpfs-env.sh` script in the configuration directory.

The answer to "What is your first and last name?" (i.e. "CN") must be the host name of the machine where the HttpFS Server will be running.

4. Start HttpFS. It should work over HTTPS.
5. Utilizing the Hadoop FileSystem API or the Hadoop FS shell, use the `swebhdfs://` scheme. Make sure the JVM is picking up the truststore containing the public key of the SSL certificate if you are using a self-signed certificate.

## 4.8. Enable SSL on Oozie

The default SSL configuration makes all Oozie URLs use HTTPS except for the JobTracker callback URLs. This simplifies the configuration because no changes are required outside of Oozie. Oozie inherently does not trust the callbacks, they are used as hints.



### Note

Before you begin ensure that the SSL certificate has been generated and properly configured. By default Oozie uses the user default keystore. In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide](#), [Gateway Security](#), [Configure Wire Encryption](#).

1. If Oozie server is running, stop Oozie.
2. Change the Oozie environment variables for HTTPS if required:
  - `OOZIE_HTTPS_PORT` set to Oozie HTTPS port. The default value is 11443.
  - `OOZIE_HTTPS_KEYSTORE_FILE` set to the keystore file that contains the certificate information. Default value `$<HOME>/.keystore`, that is the home directory of the Oozie user.

- OOZIE\_HTTPS\_KEYSTORE\_PASS set to the password of the keystore file. Default value password.



### Note

See [Oozie Environment Setup](#) for more details.

3. Run the following command to enable SSL on Oozie:

```
su -l oozie -c "/usr/hdp/current/oozie-server/bin/oozie-setup.sh prepare-war-secure"
```

4. Start the Oozie server.



### Note

To revert back to unsecured HTTP, run the following command:

```
su -l oozie -c "/usr/hdp/current/oozie-server/bin/oozie-setup.sh prepare-war"
```

## 4.8.1. Configure Oozie HCatalogJob Properties

Integrate Oozie HCatalog by adding following property to `oozie-hcatalog.job.properties`. For example if you are using Ambari, set the properties as:

```
hadoop.rpc.protection=privacy
```



### Note

This property is in addition to any properties you must set for secure clusters.

## 4.9. Enable SSL on the HBase REST Server

Perform the following task to enable SSL on an HBase REST API.



### Note

In order to access SSL-enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Configure SSL for Knox](#).

1. Create and install an SSL certificate for HBase, for example to use a self-signed certificate:

- a. Create an HBase keystore:

```
su -l hbase -c "keytool -genkey -alias hbase -keyalg RSA -keysize 1024 -keystore hbase.jks"
```

At the keytool command prompt:

- Enter the key password
- Enter the keystore password



### Note

Add these two specified values to the corresponding properties in hbase-site.xml in step 2.

b. Export the certificate:

```
su -l hbase -c "keytool -exportcert -alias hbase -file certificate.cert -keystore hbase.jks"
```

c. (Optional) Add certificate to the Java keystore:

- If you are not root run:

```
sudo keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

- If you are root:

```
keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

2. Add the following properties to the hbase-site.xml configuration file on each node in your HBase cluster:

```
<property>
<name>hbase.rest.ssl.enabled</name>
<value>true</value>
</property>

<property>
<name>hbase.rest.ssl.keystore.store</name>
<value>/path/to/keystore</value>
</property>

<property>
<name>hbase.rest.ssl.keystore.password</name>
<value>keystore-password</value>
</property>

<property>
<name>hbase.rest.ssl.keystore.keypassword</name>
<value>key-password</value>
</property>
```

3. Restart all HBase nodes in the cluster.



### Note

**For clusters using self-signed certificates:** Define the truststore as a custom property on the JVM. If the self-signed certificate is not added to the system truststore (cacerts), specify the Java KeyStore (.jks) file containing the certificate

in applications by invoking the `javax.net.ssl.trustStore` system property. Run the following command argument in the application client container to use a self-signed certificate in a `.jks` file:

```
-Djavax.net.ssl.trustStore=/path/to/keystore
```

## 4.10. Enable SSL on the HBase Web UI

Perform the following task to enable SSL and TLS on an HBase Web UI.



### Note

In order to access SSL-enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Configure SSL for Knox](#).

1. Create and install an SSL certificate for HBase, for example to use a self-signed certificate:

- a. Create an HBase keystore:

```
su -l hbase -c "keytool -genkey -alias hbase -keyalg RSA -keysize 1024 -keystore hbase.jks"
```

At the keytool command prompt:

- Enter the key password
- Enter the keystore password



### Note

Add these two specified values to the corresponding properties in `hbase-site.xml` in step 2.

- b. Export the certificate:

```
su -l hbase -c "keytool -exportcert -alias hbase -file certificate.cert -keystore hbase.jks"
```

- c. (Optional) Add certificate to the Java keystore:

- If you are not root run:

```
sudo keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

- If you are root:

```
keytool -import -alias hbase -file certificate.cert -keystore /usr/jdk64/jdk1.7.0_45/jre/lib/security/cacerts
```

2. Add the following properties to the `hbase-site.xml` configuration file on each node in your HBase cluster:

```
<property>
<name>hbase.ssl.enabled</name>
<value>true</value>
</property>

<property>
<name>hadoop.ssl.enabled</name>
<value>true</value>
</property>

<property>
<name>ssl.server.keystore.keypassword</name>
<value>key-password</value>
</property>

<property>
<name><ssl.server.keystore.password</name>
<value>keystore-password</value>
</property>

<property>
<name>ssl.server.keystore.location</name>
<value>/tmp/server-keystore.jks</value>
</property>
```

3. Restart all HBase nodes in the cluster.



### Note

**For clusters using self-signed certificates:** Define the truststore as a custom property on the JVM. If the self-signed certificate is not added to the system truststore (cacerts), specify the Java KeyStore (.jks) file containing the certificate in applications by invoking the javax.net.ssl.trustStore system property. Run the following command argument in the application client container to use a self-signed certificate in a .jks file:

```
-Djavax.net.ssl.trustStore=/path/to/keystore
```

## 4.11. Enable SSL on HiveServer2

When using HiveServer2 without Kerberos authentication, you can enable SSL.



### Note

In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide](#), [Gateway Security](#), [Configure Wire Encryption](#).

Perform the following steps on the HiveServer2:

1. Run the following command to create a keystore for hiveserver2::

```
keytool -genkey -alias hbase -keyalg RSA -keysize 1024 -keystore hbase.jks
```

2. Edit the `hive-site.xml`, set the following properties to enable SSL:

```
<property>
```

```
<name>hive.server2.use.SSL</name>
<value>true</value>
<description></description>
</property>

<property>
<name>hive.server2.keystore.path</name>
<value>keystore-file-path</value>
<description></description>
</property>

<property>
<name>hive.server2.keystore.password</name>
<value>keystore-file-password</value>
<description></description>
</property>
```

3. On the client-side, specify SSL settings for Beeline or JDBC client as follows:

```
jdbc:hive2://<host>:<port>/<database>;ssl=true;sslTrustStore=<path-to-
truststore>;trustStorePassword=<password>
```

## 4.12. Enable SSL for Kafka Clients

Kafka allows clients to connect over SSL. By default SSL is disabled, but it can be enabled as needed.

Before you begin, be sure to generate the key, SSL certificate, keystore, and truststore that will be used by Kafka.

### 4.12.1. Configuring the Kafka Broker

The Kafka Broker supports listening on multiple ports and IP addresses. To enable this feature, specify one or more comma-separated values in the `listeners` property in `server.properties`.

Both PLAINTEXT and SSL ports are required if SSL is not enabled for inter-broker communication (see the following subsection for information about enabling inter-broker communication):

```
listeners=PLAINTEXT://host.name:port,SSL://host.name:port
```

The following SSL configuration settings are needed on the broker side:

```
ssl.keystore.location = /var/private/ssl/kafka.server.keystore.jks
ssl.keystore.password = test1234
ssl.key.password = test1234
ssl.truststore.location = /var/private/ssl/kafka.server.truststore.jks
ssl.truststore.password = test1234
```

The following optional settings are available:

Property	Description	Value(s)
<code>ssl.client.auth</code>	Specify whether client authentication is required, requested, or not required.	none

Property	Description	Value(s)
	<p>none: no client authentication.</p> <p>required: client authentication is required.</p> <p>requested: client authentication is requested, but a client without certs can still connect.</p> <p><b>Note:</b> If you set <code>ssl.client.auth</code> to <code>requested</code> or <code>required</code>, then you must provide a truststore for the Kafka broker. The truststore should contain all CA certificates that are used to sign clients' keys.</p>	
<code>ssl.cipher.suites</code>	Specify one or more cipher suites: named combinations of authentication, encryption, MAC and key exchange algorithms used to negotiate the security settings for a network connection using the TLS or SSL network protocol.	
<code>ssl.enabled.protocols</code>	Specify the SSL protocols that you will accept from clients. Note: SSL is deprecated; its use in production is not recommended.	TLSv1.2, TLSv1.1, TLSv1
<code>ssl.keystore.type</code>	Specify the SSL keystore type.	JKS
<code>ssl.truststore.type</code>	Specify the SSL truststore type.	JKS

## Enabling SSL for Inter-Broker Communication

To enable SSL for inter-broker communication, add the following setting to the broker properties file (default is PLAINTEXT):

```
security.inter.broker.protocol = SSL
```

## Enabling Additional Cipher Suites

To enable any cipher suites other than the defaults that come with JVM (see [Java Cryptography documentation](#)), you will need to install JCE Unlimited Strength Policy files ([download link](#)).

## Validating the Configuration

After you start the broker, you should see the following information in the `server.log` file:

```
with addresses: PLAINTEXT -> EndPoint(192.168.64.1,9092,PLAINTEXT),SSL ->
EndPoint(192.168.64.1,9093,SSL)
```

To make sure that the server keystore and truststore are set up properly, run the following command:

```
openssl s_client -debug -connect localhost:9093 -tls1
```

(Note: TLSv1 should be listed under `ssl.enabled.protocols`)

In the `openssl` output you should see the server certificate; for example:

```
Server certificate
```

```
-----BEGIN CERTIFICATE-----
MIID+DCCAuACCQCx2Rz1tXx3NTANBgkqhkiG9w0BAQsFADB6MQswCQYDVQQGEwJV
UzELMAkGA1UECAwCQ0ExFDASBgNVBAcMC1NhbnRhIENsYXJhMQwwCgYDVQQKDANv
cmcxDDAKBgNVBAsMA29yZzEOMAwGA1UEAwxFa2FmYWsxHDAaBgkqhkiG9w0BCQEW
DXRlc3RADgVzdC5jb20wHhcNMTUwNzMwMDQyOTMwWhcNMTYwNzI5MDQyOTMwWjBt
MQswCQYDVQQGEwJVUzELMAkGA1UECBMCQ0ExFDASBgNVBAcTC1NhbnRhIENsYXJh
MQwwCgYDVQQKEwNvcmcxDDAKBgNVBAsTA29yZzEfMB0GA1UEAxMWU3JpaGFyc2hh
IENoAW50YWxhcGFuatCCAbcwggEsBgcqhkjOOAQBMIIBHwKBgQD9f1OBHXUSKVLf
Spwu7OTn9hG3UjzvRADDHj+At1EmaUVdQCJR+1k9jVj6v8X1ujD2y5tVbNeBO4Ad
NG/yZmC3a5lQpaSfn+gEexAiwk+7qdf+t8Yb+DtX58aophUPBPuD9tPFHsMCNVQT
WhaRMvZ1864rYdcq7/IiAxmd0UgBxwIVAjdgu18VIwvMspK5ggLrhAvvWBz1AoGB
APfhIXWmz3ey7yrXDa4V7151K+7+jrqgv1XTAs9B4JnUV1XjrrUWU/mcQcQgYCO
SRZxI+hMKBYTt88JMoziPue8FnqLVHyNKOCjrh4rs6z1kW6jfWv6ITVi8ftiegEk
O8yk8b6oUZCJqIPf4VrlnwaSi2ZegHtVJWQBDv+z0kqA4GEAAKBgB+Pdz0306bq
TpUAdb2FERMPLFsx06H0x+TULivcp7HbS5yrvkV9bxZmv/FD98x76QxXrOq1WpQhY
YDeGDjH+XQkJ6ZxBVBNJDIpCnfQpfzXAvryQ+cm8oXUsKidtHf4pLMYViXX6BWX
Oc2hX4rG+1C8/NXW+1zVvCr9To9fnqzjMA0GCSqGS1b3DQEBCwUAA4IBAQBfyVse
RJ+ugiNlWg5trZscqH0tlccbne4UuV/xis2eAu914EFOM5kRt5GmkGZRcM/zHF8
BRJwXbf0ftyTMQKSPFk8R4/NGD01zoK+F7uXeJ0S2u/T29xk0u2i4tjvleq6OCphE
i9vdjm0E0Whf9SHRHoxirOYFX3cL775XwKdzKKRkk+AszFR+mRu90rdoaepQtgGh
9Kfwr4+6AU/dPtGuomtBQqMxCz1rLd8EYhVVQ97wHZ3sPv1M5PIhOJ/YHSBJIC
75eo/4acDxZ+j3sR5kcFulzYwFLgDYBaKH/w3mYCgTALeB1zUkX53NVizIvhUd69
XJO41DSDtgolfort
-----END CERTIFICATE-----
subject=/C=US/ST=CA/L=Santa Clara/O=org/OU=org/CN=JBrown
issuer=/C=US/ST=CA/L=Santa Clara/O=org/OU=org/CN=kafak/emailAddress=test@test.com
```

If the certificate does not display, or if there are any other error messages, then your keystore is not set up properly.

## 4.12.2. Configuring Kafka Producer and Kafka Consumer

SSL is supported for new Kafka Producers and Consumer processes; the older API is not supported. Configuration settings for SSL are the same for producers and consumers.

If client authentication is not needed in the broker, then the following is a minimal configuration example:

```
security.protocol = SSL
ssl.truststore.location = /var/private/ssl/kafka.client.truststore.jks
ssl.truststore.password = test1234
```

If client authentication is required, first create a keystore (described earlier in this chapter). Next, specify the following settings:

```
ssl.keystore.location = /var/private/ssl/kafka.client.keystore.jks
ssl.keystore.password = test1234
ssl.key.password = test1234
```

One or more of the following optional settings might also be needed, depending on your requirements and the broker configuration:

Property	Description	Value(s)
ssl.provider	The name of the security provider used for SSL connections. Default value is the default security provider of the JVM.	

Property	Description	Value(s)
ssl.cipher.suites	Specify one or more cipher suites: named combinations of authentication, encryption, MAC and key exchange algorithms used to negotiate the security settings for a network connection using the TLS or SSL network protocol.	
ssl.enabled.protocols	List at least one of the protocols configured on the broker side.	TLSv1.2, TLSv1.1, TLSv1
ssl.keystore.type	Specify the SSL keystore type.	JKS
ssl.truststore.type	Specify the SSL truststore type.	JKS

The following two examples launch console-producer and console-consumer processes:

```
kafka-console-producer.sh --broker-list localhost:9093 --topic test --producer.config client-ssl.properties

kafka-console-consumer.sh --bootstrap-server localhost:9093 --topic test --new-consumer --consumer.config client-ssl.properties
```

## 4.13. Enable SSL for Accumulo

One of the major features added in Accumulo 1.6.0 was the ability to configure Accumulo so that the Thrift communications will run over SSL. [Apache Thrift](#) is the remote procedure call library that is leveraged for both intra-server and client communication with Accumulo. Issuing these calls over a secure socket ensures that unwanted actors cannot inspect the traffic sent across the wire. Given the sometimes sensitive nature of data stored in Accumulo and the authentication details for users, secure communications are critical.

Due to the complex and deployment-specific nature of the security model for some systems, Accumulo expects users to provide their own certificates, guaranteeing that they are, in fact, secure. However, for those who require security but do not already operate within the confines of an established security infrastructure, OpenSSL and the Java keytool command can be used to generate the necessary components to enable wire encryption.

To enable SSL with Accumulo, it is necessary to generate a certificate authority and certificates that are signed by that authority. Typically, each client and server has its own certificate, which provides the finest level of control over a secure cluster when the certificates are properly secured.

### 4.13.1. Generate a Certificate Authority

The certificate authority (CA) controls what certificates can be used to authenticate with each other. To create a secure connection with two certificates, each certificate must be signed by a certificate authority in the "truststore" (A Java KeyStore which contains at least one Certificate Authority's public key). When creating your own certificate authority, a single CA is typically sufficient (and would result in a single public key in the truststore). Alternatively, a third party can also act as a certificate authority (to add an additional layer of security); however, these are typically not a free service.

The following is an example of creating a certificate authority and adding its public key to a Java KeyStore to provide to Accumulo.

```
Create a private key
openssl genrsa -des3 -out root.key 4096

Create a certificate request using the private key
openssl req -x509 -new -key root.key -days 365 -out root.pem

Generate a Base64-encoded version of the PEM just created
openssl x509 -outform der -in root.pem -out root.der

Import the key into a Java KeyStore
keytool -import -alias root-key -keystore truststore.jks -file root.der

Remove the DER formatted key file (as we don't need it anymore)
rm root.der
```

Remember to protect `root.key` and never distribute it, as the private key is the basis for your circle of trust. The `keytool` command will prompt you about whether or not the certificate should be trusted: enter "yes". The `truststore.jks` file, a "truststore", is meant to be shared with all parties communicating with one another. The password provided to the truststore verifies that the contents of the truststore have not been tampered with.

## 4.13.2. Generate a Certificate/Keystore Per Host

It is desirable to generate a certificate for each host in the system. Additionally, each client connecting to the Accumulo instance running with SSL should be issued its own certificate. Issuing individual certificates to each entity provides proper control to revoke/reissue certificates to clients as necessary, without widespread interruption.

The following commands create a private key for the server, generate a certificate signing request created from that private key, use the certificate authority to generate the certificate using the signing request, and then create a Java KeyStore with the certificate and the private key for our server.

```
Create the private key for our server
openssl genrsa -out server.key 4096

Generate a certificate signing request (CSR) with our private key
openssl req -new -key server.key -out server.csr

Use the CSR and the CA to create a certificate for the server (a reply to
the CSR)
openssl x509 -req -in server.csr -CA root.pem -CAkey root.key -CAcreateserial
-out server.crt -days 365

Use the certificate and the private key for our server to create PKCS12
file
openssl pkcs12 -export -in server.crt -inkey server.key -certfile server.crt -
name 'server-key' -out server.p12

Create a Java KeyStore for the server using the PKCS12 file (private key)
keytool -importkeystore -srckeystore server.p12 -srcstoretype pkcs12 -
destkeystore server.jks -deststoretype JKS

Remove the PKCS12 file as we don't need it
rm server.p12

Import the CA-signed certificate to the keystore
```

```
keytool -import -trustcacerts -alias server-crt -file server.crt -keystore server.jks
```

This, combined with the truststore, provides what is needed to configure Accumulo servers to run over SSL. The private key (`server.key`), the certificate signed by the CA (`server.pem`), and the keystore (`server.jks`) should be restricted to only be accessed by the user running Accumulo on the host it was generated for. Use `chown` and `chmod` to protect the files, and do not distribute them over non-secure networks.

### 4.13.3. Configure Accumulo Servers

Now that the Java KeyStores have been created with the necessary information, the Accumulo configuration must be updated so that Accumulo creates the Thrift server over SSL instead of a normal socket. Configure the following properties in `accumulo-site.xml`:

```
<property>
 <name>rpc(javax.net.ssl.KeyStore)</name>
 <value>/path/to/server.jks</value>
</property>
<property>
 <name>rpc(javax.net.ssl.KeyStorePassword)</name>
 <value>server_password</value>
</property>
<property>
 <name>rpc(javax.net.ssl.TrustStore)</name>
 <value>/path/to/truststore.jks</value>
</property>
<property>
 <name>rpc(javax.net.ssl.TrustStorePassword)</name>
 <value>truststore_password</value>
</property>
<property>
 <name>instance.rpc.ssl.enabled</name>
 <value>true</value>
</property>
```

The keystore and truststore paths are both absolute paths on the local file system (not HDFS). Remember that the server keystore should only be readable by the user running Accumulo and, if you place plain-text passwords in `accumulo-site.xml`, make sure that `accumulo-site.xml` is also not globally readable. To keep these passwords out of `accumulo-site.xml`, consider configuring your system with the new Hadoop CredentialProvider class. See [ACCUMULO-2464](#) for more information on what will be available in Accumulo-1.6.1.

Also, be aware that if unique passwords are used for each server when generating the certificate, this will result in different `accumulo-site.xml` files for each host. Unique configuration files for each host will add complexity to the configuration management of your instance. The use of a CredentialProvider (a feature from Hadoop which allows for acquisitions of passwords from alternate systems) can help alleviate the issues with unique `accumulo-site.xml` files on each host. A Java KeyStore can be created using the CredentialProvider tools, which eliminates the need for passwords to be stored in `accumulo-site.xml`, and can instead point to the CredentialProvider URI which is consistent across hosts.

## 4.13.4. Configure Accumulo Clients

To configure Accumulo clients, use \$HOME/.accumulo/config. This is a simple [Java properties file](#): each line is a configuration, key, and value separated by a space, and lines beginning with a # symbol are ignored. For example, if we generated a certificate and placed it in a keystore (as described above), we would generate the following file for the Accumulo client.

```
instance.rpc.ssl.enabled true
rpc(javax.net.ssl.keyStore /path/to/client-keystore.jks
rpc(javax.net.ssl.keyStorePassword client-password
rpc(javax.net.ssl.trustStore /path/to/truststore.jks
rpc(javax.net.ssl.trustStorePassword truststore-password
```

When creating a ZooKeeperInstance, the implementation will automatically look for this configuration file and set up a connection with the methods defined in this file. The ClientConfiguration class also contains methods that can be used instead of a configuration file on the file system. Again, the paths to the keystore and truststore are on the local file system, not HDFS.

## 4.14. SPNEGO setup for WebHCat

To set up secure WebHCat, set the following properties in the /etc/hcatalog/conf/webhcatt-site.xml file:

```
</property>
<name>templeton.kerberos.principal</name>
<value>HTTP/host1234.example.com@EXAMPLE.COM</value>
<description/>
<property>
```

The templeton.kerberos.principal property must use the host name of the WebHCat Server.

```
<property>
<name>templeton.kerberos.keytab</name>
<value>/etc/security/keytabs/spnego.service.keytab</value>
<description/>
</property>

<property>
<name>templeton.kerberos.secret</name>
<value>secret</value>
<description/>
</property>

<property>
<name>templeton.hive.properties</name>
<value>hive.metastore.local=false,hive.metastore.uris=thrift://host1234.
example.com:9083,
hive.metastore.sasl.enabled=true,hive.metastore.execute.
setugi=true,
hive.exec.mode.local.auto=false,
hive.metastore.kerberos.principal=hive/_HOST@EXAMPLE.COM</
value>
<description>Properties to set when running hive.</description>
</property>
```

Be sure to set the `templeton.hive.properties` property with the host name for your Thrift server.

## 4.15. Configure SSL for Hue

HTTPS is a simple HTTP in conjunction with SSL (Secure Sockets Layer) and used for establishing an encrypted link between the web browser and the web server. Using HTTPS enables you to prevent collection of sensitive information between your web browser and a web server.

### 4.15.1. Enabling SSL on Hue by Using a Private Key

If you have a private key, follow these steps to enable SSL on Hue:

1. Configure Hue to use your private key by adding the following syntax to the `/etc/hue/conf/hue.ini` file:

```
ssl_certificate=$PATH_TO_CERTIFICATE
ssl_private_key=$PATH_TO_KEY
ssl_cipher_list="DEFAULT:!aNULL:!eNULL:!LOW:!EXPORT:!SSLv2" (default)
```

2. Restart Hue:

```
/etc/init.d/hue restart
```

### 4.15.2. Enabling SSL on Hue Without Using a Private Key

If you do not have a private key and want to run tests, you can enable SSL on Hue by creating a self-signed certificate:

1. Create a key:

```
openssl genrsa 1024 > host.key
```

2. Create a self-signed certificate:

```
openssl req -new -x509 -nodes -sha1 -key host.key > host.cert
```

3. Move the `host.key` and `host.cert` files to the `ssl` directory:

```
mv host.key /etc/ssl
mv host.cert /etc/ssl
```

4. Configure Hue to use your private key by adding the following syntax to the `/etc/hue/conf/hue.ini` file:

```
ssl_certificate=$PATH_TO_CERTIFICATE
ssl_private_key=$PATH_TO_KEY
ssl_cipher_list="DEFAULT:!aNULL:!eNULL:!LOW:!EXPORT:!SSLv2" (default)
```

5. Restart Hue:

```
/etc/init.d/hue restart
```

## 4.16. Configure SSL for Knox

For the simplest of evaluation deployments, the initial startup of the Knox Gateway will generate a self-signed cert for use on the same machine as the gateway instance. These certificates are issued for "localhost" and will require specifically disabling hostname verification on client machines other than where the gateway is running.

### 4.16.1. Self-Signed Certificate with Specific Hostname for Evaluations

In order to continue to use self-signed certificates for larger evaluation deployments, a certificate can be generated for a specific hostname. This will allow clients to properly verify the hostname presented in the certificate as the host that they requested in the request URL.

To create a self-signed certificate:

1. Create a certificate: where \$gateway-hostname is the FQDN of the Knox Gateway.

```
cd $gateway bin/knoxcli.cmd create-cert --hostname $gateway-hostname
```

2. Export the certificate in PEM format:

```
keytool -export -alias gateway-identity -rfc -file $certificate_path -keystore $gateway /data/security/keystores/gateway.jks
```



#### Note

cURL option accepts certificates in PEM format only.

3. Restart the gateway:

```
cd $gateway bin/gateway.sh stop bin/gateway.sh start
```

4. After copying the certificate to a client, use the following command to verify:

```
curl --cacert $certificate_path -u $username : $password https://$gateway-hostname : $gateway_port /gateway/ $cluster_name /webhdfs/v1?op=GETHOMEDIRECTORY
```

### 4.16.2. CA-Signed Certificates for Production

For production deployments or any deployment in which a certificate authority issued certificate is needed, the following steps are required.

1. Import the desired certificate/key pair into a java keystore using keytool and ensure the following:
  - The certificate alias is gateway-identity.
  - The store password matches the master secret created earlier.
  - Note the key password used - as we need to create an alias for this password.

2. Add a password alias for the key password:

```
cd $gateway bin/knoxcli.cmd create-cert create-alias gateway-identity-passphrase --value $actualpassphrase
```



#### Note

The password alias must be `gateway-identity-passphrase`.

### 4.16.3. Setting Up Trust for the Knox Gateway Clients

In order for clients to trust the certificates presented to them by the gateway, they will need to be present in the client's truststore as follows:

1. Export the gateway-identity cert from the `$gateway /data/security/keystores/gateway.jks` using java keytool or another key management tool.
2. Add the exported certificate to the cacerts or other client specific truststore or the `gateway.jks` file can be copied to the clients to be used as the truststore.



#### Note

If taking this approach be sure to change the password of the copy so that it no longer matches the master secret used to protect server side artifacts.

## 4.17. Securing Phoenix

To configure Phoenix to run in a secure Hadoop cluster, use the instructions on [this page](#).

### 4.18. Set Up SSL for Ambari

If you want to limit access to the Ambari Server to HTTPS connections, you need to provide a certificate. While it is possible to use a self-signed certificate for initial trials, they are not suitable for production environments. After your certificate is in place, you must run a special setup command.

Ambari Server should not be running when you do this. Either make these changes before you start Ambari the first time, or bring the server down before running the setup command.

1. Log into the Ambari Server host.
2. Locate your certificate. If you want to create a temporary self-signed certificate, use this as an example:

```
openssl genrsa -out $wserver.key 2048
```

```
openssl req -new -key $wserver.key -out $wserver.csr
```

```
openssl x509 -req -days 365 -in $wserver.csr -signkey
$wserver.key -out $wserver.crt
```

Where \$wserver is the Ambari Server host name.

The certificate you use must be PEM-encoded, not DER-encoded. If you attempt to use a DER-encoded certificate, you see the following error:

```
unable to load certificate 140109766494024:error:0906D06C:PEM
routines:PEM_read_bio:no start line:pem_lib.c :698:Expecting:
TRUSTED CERTIFICATE
```

You can convert a DER-encoded certificate to a PEM-encoded certificate using the following command:

```
openssl x509 -in cert.crt -inform der -outform pem -out cert.pem
```

where cert.crt is the DER-encoded certificate and cert.pem is the resulting PEM-encoded certificate.

### 3. Run the special setup command and answer the prompts.

```
ambari-server setup-security
```

- Select 1 for Enable HTTPS for Ambari server.
- Respond y to Do you want to configure HTTPS ?
- Select the port you want to use for SSL. The default port number is 8443.
- Provide the complete path to your certificate file (\$wserver.crt from above) and private key file (\$wserver.key from above).
- Provide the password for the private key.
- Start or restart the Server

```
ambari-server restart
```

### 4. Trust Store Setup - If you plan to use Ambari Views with your Ambari Server, after enabling SSL for Ambari using the instructions below, you must also [set up a truststore for the Ambari server](#).

## 4.18.1. Set Up Truststore for Ambari Server

If you plan to [set up SSL for Ambari](#) or to enable wire encryption for HDP, you must configure the Truststore for Ambari and add certificates.

Ambari Server should not be running when you do this. Either make these changes before you start Ambari the first time, or bring the server down before running the setup command .

1. On the Ambari Server, create a new keystore that will contain the Ambari Server's HTTPS certificate.

```
keytool -import -file <path_to_the_Ambari_Server's_SSL_Certificate> -alias
ambari-server -keystore ambari-server-truststore
```

When prompted to 'Trust this certificate?' type "yes".

2. Configure the ambari-server to use this new trust store:

```
ambari-server setup-security
Using python /usr/bin/python2.6
Security setup options...
=====
Choose one of the following options:
[1] Enable HTTPS for Ambari server.
[2] Encrypt passwords stored in ambari.properties file.
[3] Setup Ambari kerberos JAAS configuration.
[4] Setup truststore.
[5] Import certificate to truststore.
=====
Enter choice, (1-5): *4*
Do you want to configure a truststore [y/n] (y)? *y*
TrustStore type [jks/jceks/pkcs12] (jks): *jks*
Path to TrustStore file : *<path to the ambari-server-truststore keystore>*
Password for TrustStore:
Re-enter password:
Ambari Server 'setup-security' completed successfully.
```

3. Once configured, the Ambari Server must be restarted for the change to take effect.

```
ambari-server restart
```

## 4.19. Configure Ambari Ranger SSL

### 4.19.1. Configuring Ambari Ranger SSL Using Public CA Certificates

If you have access to Public CA issued certificates, use the following steps to configure Ambari Ranger SSL.

#### 4.19.1.1. Prerequisites

- Copy the keystore/truststore files into a different location (e.g. /etc/security/serverKeys) than the /etc/<component>/conf folder.
- Make sure that the JKS file names are unique.
- Make sure that the correct permissions are applied.
- Make sure that passwords are secured.

#### 4.19.1.2. Configuring Ranger Admin

1. Stop Ranger by selecting **Service Actions > Stop**.

The screenshot shows the Ambari interface for a cluster named 'test\_cluster'. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense, and Spark. The 'Ranger' service is currently selected. The main panel displays the 'Summary' tab for the Ranger service, which shows the status of Ranger Admin (Started) and Ranger UserSync (Started). Below this, it lists several Ranger plugin statuses: Ranger HDFS plugin (Disabled), Ranger YARN plugin (Disabled), Ranger Hive plugin (Disabled), Ranger HBase plugin (Disabled), Ranger Storm plugin (Disabled), Ranger Knox plugin (Disabled), and Ranger Kafka plugin (Disabled). To the right of the summary, there is a 'Service Actions' dropdown menu with options: Start, Stop (which is highlighted with a red box), Restart All, Enable Ranger Admin HA, Run Service Check, and Turn On Maintenance Mode.

2. Use the following steps to disable the HTTP port and enable the HTTPS port with the required keystore information.
  - a. Select **Configs > Advanced**. Under Ranger Settings, clear the **HTTP enabled** check box (this blocks all agent calls to the HTTP port even if the port is up and working).

The screenshot shows the Ambari interface for managing a test cluster. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, and Ranger. The 'Ranger' service is currently selected. The main panel displays the 'Manage Config Groups' screen for Ranger, showing four configuration versions (V4, V3, V2, V1) with their respective authors (admin) and last updated dates (15 days ago or 2 months ago). A message indicates there is 1 configuration change in 1 service. Below this, under 'Ranger Admin', are fields for Ranger Admin host (c6403.ambari.apache.org), Ranger Admin username (amb\_ranger\_admin), Ranger Admin user's password (two masked fields), and Location of Sql Connector Jar (/usr/share/java/mysql-connector-java.jar). The 'Ranger Settings' section includes fields for External URL (https://c6403.ambari.apache.org:6182) and Authentication method (LDAP selected). The 'HTTP enabled' section at the bottom is also highlighted with a red box.

- b. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.

This is a detailed view of the 'Ranger Settings' section from the Ambari UI. It shows the 'External URL' field set to `https://c6403.ambari.apache.org:6182`, which is highlighted with a red box. Below this, the 'Authentication method' section has 'LDAP' selected. At the bottom, the 'HTTP enabled' section is also highlighted with a red box.

- c. Under Advanced ranger-admin-site, set the following properties:

- `ranger.https.attrib.keystore.file` – Provide the location of the Public CA issued keystore file.
- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore.
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key.
- `ranger.service.https.attrib.clientAuth` – Enter want as the value. This validates the client cert from all agents, but not the requests from web applications. Setting this value to want requires the client to have a certificate to use to sign traffic. If you do not want to put certificates on the client machines to do two-way SSL, this parameter can be set to false to enable one-way SSL.
- `ranger.service.https.attrib.ssl.enabled` – set this property to true.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.

Advanced ranger-admin-site

ranger.audit.source.type	solr			
ranger.credential.provider.path	/etc/ranger/admin/rangeradmin.jceks			
ranger.https.attrib.keystore.file	/etc/ranger/admin/conf/ranger-admin-keystore.jks			
ranger.jpa.audit.jdbc.credential.alias	rangeraudit			
ranger.jpa.audit.jdbc.dialect	<code>{{{jdbc_dialect}}}</code>			
ranger.jpa.audit.jdbc.driver	<code>{{{ranger_jdbc_driver}}}</code>			
ranger.jpa.audit.jdbc.password	.....	.....		
ranger.jpa.audit.jdbc.url	<code>{{{audit_jdbc_url}}}</code>			
ranger.jpa.audit.jdbc.user	<code>{{{ranger_audit_db_user}}}</code>			
ranger.jpa.jdbc.credential.alias	rangeradmin			
ranger.jpa.jdbc.dialect	<code>{{{jdbc_dialect}}}</code>			
ranger.jpa.jdbc.password	.....	.....		
ranger.jpa.jdbc.user	<code>{{{ranger_db_user}}}</code>			
Group Search Base	<code>{{{ranger_ug_ldap_group_searchbase}}}</code>			
Group Search Filter	<code>{{{ranger_ug_ldap_group_searchfilter}}}</code>			
ranger.service.host	<code>{{{ranger_host}}}</code>			
ranger.service.http.port	6080			
ranger.service.https.attrib.clientAuth	want			
ranger.service.https.attrib.keystore.keyalias	rangeradmin			
ranger.service.https.attrib.keystore.pass	.....	.....		
ranger.service.https.attrib.ssl.enabled	true			
ranger.service.https.port	6182			


3. Under Custom ranger-admin-site, add the following properties:

- `ranger.service.https.attrib.keystore.file` – Specify the same value provided for the `ranger.https.attrib.keystore.file` property.

- ranger.service.https.attrib.client.auth – Specify the same value provided for the ranger.service.https.attrib.clientAuth property.

To add a Custom ranger-admin-site property:

- a. Select **Custom ranger-admin-site**, then click **Add Property**.



- b. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.

**Add Property**

Type	ranger-admin-site.xml	 
Key	ranger.service.https.attrib.keystore.file	
Value	/etc/ranger/admin/conf/ranger-admin-keystore.jks	

4. Save your changes and start Ranger Admin.

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

#### 4.19.1.3. Configuring Ranger Usersync

1. Stop Ranger Usersync by selecting the **Ranger Usersync** link, then select **Started > Stop** next to Ranger Usersync.

Ambari test\_cluster 0 ops 16 alerts

Dashboard Services Hosts 1 Alerts Admin admin

**c6403.ambari.apache.org**

[Back](#)

Summary Configs Alerts 16 Versions Host Actions ▾

Components


Component	Status
Accumulo GC / Accumulo	Stopped
Accumulo Master / Accumulo	Stopped
Accumulo Monitor / Accumulo	Stopped
Accumulo Tracer / Accumulo	Stopped
App Timeline Server / YARN	Started
Atlas Metadata Server / Atlas	Started
DRPC Server / Storm	Started
Falcon Server / Falcon	Stopped
HBase Master / HBase	Stopped
History Server / MapReduce2	Started
Hive Metastore / Hive	Started
HiveServer2 / Hive	Started
SmartSense HST Server / SmartSense	Stopped
Kafka Broker / Kafka	Started
Knox Gateway / Knox	Started
Metrics Collector / Ambari Metrics	Stopped
MySQL Server / Hive	Started
NameNode / HDFS	Started
Nimbus / Storm	Started
Oozie Server / Oozie	Started
Ranger Admin / Ranger	Started
Ranger Usersync / Ranger	Started
ResourceManager / YARN	Restart
SNameNode / HDFS	Stop
Spark History Server / Spark	Started
Storm UI Server / Storm	Started

Host Metrics Last 1 hour

Metric	Value
CPU Usage	No Data Available
Disk Usage	No Data Available
Load	No Data Available
Memory Usage	No Data Available
Network Usage	No Data Available
Processes	No Data Available

2. Navigate back to Ranger and select **Configs > Advanced**, then click **Advanced ranger-usersync-site**. Set the following properties:

- `ranger.usersync.truststore.file` – Enter the path to the truststore file.
- `ranger.usersync.truststore.password` – Enter the truststore password.



3. Start Ranger Usersync by selecting the **Ranger Usersync** link on the Summary tab, then select **Stopped > Start** next to Ranger Usersync.

#### 4.19.1.4. Configuring Ranger Plugins for SSL

The following section shows how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components. Additional steps required to configure the Ranger KMS plugin and server are provided in subsequent sections.

##### 4.19.1.4.1. Configuring the Ranger HDFS Plugin for SSL

The following steps show how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components.

1. Stop HDFS by selecting **Service Actions > Stop**.

The screenshot shows the Ambari interface for a cluster named 'test\_cluster'. On the left, a sidebar lists various services: HDFS (green), MapReduce2 (green), YARN (green), Tez (grey), Hive (green), HBase (green), Pig (grey), Sqoop (grey), Oozie (green), ZooKeeper (green), Falcon (red), Storm (green), Flume (green), Accumulo (red), Ambari Metrics (red), Atlas (green), Kafka (green), Knox (green), Mahout (grey), Ranger (green), Slider (grey), SmartSense (red), and Spark (green). The 'Actions' button is highlighted with a red box.

**Summary**

Name	Status	Details
NameNode	Started	Disk Health
SNameNode	Started	Block Health
DataNodes	1/1 Started	Block Health
DataNodes Status	1 live / 0 dead / 0 decommissioning	Total Files + Dir
NFSGateways	0/0 Started	Upgrades
NameNode Uptime	21.82 days	Safe Mode
NameNode Heap	159.3 MB / 1011.3 MB (15.8% used)	
Disk Usage (DFS Used)	869.6 MB / 488.2 GB (0.17%)	
Disk Usage (Non DFS Used)	38.3 GB / 488.2 GB (7.84%)	

**Metrics**

Metric	Value	Actions	Last 1 hour
NameNode GC count	No Data Available		
NameNode GC time	No Data Available		
NN Connection Load	No Data Available		
NameNode Heap	No Data Available		
NameNode Host Load	No Data Available		
NameNode RPC	No Data Available		
Failed disk volumes	n/a		
Corrupted Blocks	0		
Under Replicated Blocks	481		
HDFS Space Utilization	n/a		

2. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.

3. Select **Advanced ranger-hdfs-policymgr-ssl** and set the following properties:

- `xasecure.policymgr.clientssl.keystore` – Enter the public CA signed keystore for the machine that is running the HDFS agent.
- `xasecure.policymgr.clientssl.keystore.password` – Enter the keystore password.

▼ Advanced ranger-hdfs-policymgr-ssl

xasecure.policymgr. clientssl.keystore	/usr/hdp/current/hadoop-client/conf/ranger-plugin-keystore.jks	⊕ C
xasecure.policymgr. clientssl.keystore. credential.file	jceks://file{{credential_file}}	⊕ C
xasecure.policymgr. clientssl.keystore. password	.....	.....
xasecure.policymgr. clientssl.truststore	/usr/hdp/current/hadoop-client/conf/ranger-plugin-truststore.jks	⊕ C
xasecure.policymgr. clientssl.truststore. credential.file	jceks://file{{credential_file}}	⊕ C
xasecure.policymgr. clientssl.truststore. password	.....	.....

4. Select Advanced ranger-hdfs-plugin-properties, then select the Enable Ranger for HDFS check box.

▼ Advanced ranger-hdfs-plugin-properties

Enable Ranger for HDFS	<input checked="" type="checkbox"/>	⊕ C
Ranger repository config password	.....	.....
Ranger repository config user	hadoop	⊕ + C
common.name.for. certificate		⊕ +
hadoop.rpc.protection		⊕ +
Policy user for HDFS	ambari-qa	⊕ + C

5. Click **Save** to save your changes.
  6. Start HDFS by selecting **Service Actions > Start**.
  7. Restart Ranger Admin.
  8. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of the HDFS repository and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.
  9. Start the HDFS service.
- 10 Select **Audit > Agents**. You should see an entry for your repo name with HTTP Response Code 200.



### Note

This procedure assumes that the keystores provided for the Admin and agent are signed by a public CA.

Provide an identifiable string as the value for Common Name when generating certificates. Important note: In the case where multiple servers talking to ranger admin for downloading policies for the same service/repository (e.g. HBase Master and Region servers, multiple NameNodes or Hive servers in an HA environment, be sure to use the repo name or a common string across all of the nodes (such as HbasePlugin, HdfsPlugin etc). (Note this and enter the same value in Common Name For Certificate field in the edit repository page in the Policy Manager UI).



### Note

Ranger Admin will use the JAVA truststore, so you need to add your plugin certificate inside the Java truststore. Alternatively, you can specify a custom truststore by editing `/usr/hdp/2.3.2.0-2950/ranger-admin/ews/ranger-admin-services.sh`. You will need to add the following after the `JAVA_OPTS` line:

```
-Djavax.net.ssl.trustStore=/etc/security/ssl/truststore.jks
-Djavax.net.ssl.trustStorePassword=hadoop
```

For example:

```
JAVA_OPTS=" ${JAVA_OPTS} -XX:MaxPermSize=256m -Xmx1024m -Xms1024m
-Djavax.net.ssl.trustStore=/etc/security/ssl/truststore.jks
-Djavax.net.ssl.trustStorePassword=hadoop"
```

#### 4.19.1.4.2. Configuring the Ranger KMS Plugin for SSL

To configure the Ranger KMS (Key Management Service) plugin for SSL, use the procedure described in the previous section for HDFS, then perform the following additional step.

Log into the Policy Manager UI (as the keyadmin user) and click the **Edit** button of your KMS repository. Provide the CN name of the keystore as the value for Common Name For Certificate and save your changes. This property is not provided by default, so it must be added.

The screenshot shows the Ranger UI for creating a new service. The top navigation bar has tabs for 'Ranger' (selected), 'Access Manager', and 'Encryption'. Below the tabs, there are links for 'Service Manager' and 'Edit Service', and a 'Create Service' button. The main area is titled 'Service Details:' and contains fields for 'Service Name' (cl1\_kms) and 'Description' (kms repo). An 'Active Status' section shows 'Enabled' selected. The next section is 'Config Properties:', which includes fields for 'KMS URL' (kms://https@ip-172-31-26-219.ec2), 'Username' (keyadmin), and 'Password' (redacted). A table for 'Add New Configurations' shows a single entry: 'commonNameForCertificate' with value 'ip-172-31-26-219.ec2.internal'. There is a '+' button to add more configurations and a 'Test Connection' button. At the bottom are 'Save', 'Cancel', and 'Delete' buttons.

#### 4.19.1.4.3. Configuring the Ranger KMS Server for SSL

Use the following steps to configure Ranger KMS (Key Management Service) Server for SSL.

1. Stop Ranger KMS by selecting **Service Actions > Stop**.
2. Select **Custom ranger-kms-site**, then add the following properties as shown below:

ranger.https.attrib.keystore.file

ranger.service.https.attrib.keystore.file (duplicate of above – workaround for now)

ranger.service.https.attrib.clientAuth

ranger.service.https.attrib.client.auth (duplicate of above – workaround for now)

ranger.service.https.attrib.keystore.keyalias

ranger.service.https.attrib.keystore.pass

ranger.service.https.attrib.ssl.enabled

ranger.service.https.port

Custom ranger-kms-site

ranger.https.attrib.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	green	red
ranger.service.https.attrib.client.auth	want	green	red
ranger.service.https.attrib.clientAuth	false	green	red
ranger.service.https.attrib.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	green	red
ranger.service.https.attrib.keystore.keyalias	rangerkms	green	red
ranger.service.https.attrib.keystore.pass	rangerkms	green	red
ranger.service.https.attrib.ssl.enabled	true	green	red
ranger.service.https.port	9393	green	red

Add Property ...

3. Under Advanced kms\_env, update the value of **kms\_port** to match the value of **ranger.service.https.port**.

4. Save your changes and restart Ranger KMS.

When you attempt to access the Ranger KMS UI with the HTTPS protocol on the port specified by the **ranger.service.https.port** property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

## 4.19.2. Configuring Ambari Ranger SSL Using a Self-Signed Certificate

If you do not have access to Public CA issued certificates, use the following steps to create a self-signed certificate and configure Ambari Ranger SSL.

### 4.19.2.1. Prerequisites

- Copy the keystore/truststore files into a different location (e.g. /etc/security/serverKeys) than the /etc/<component>/conf folder.
- Make sure that the JKS file names are unique.

- Make sure that the correct permissions are applied.
- Make sure that passwords are secured.

## 4.19.2.2. Configuring Ranger Admin

1. Stop Ranger by selecting **Service Actions > Stop**.

The screenshot shows the Ambari interface for a 'test\_cluster'. The left sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense, and Spark. The 'Ranger' service is currently selected. The main panel displays the 'Summary' for the Ranger service, which includes a table of Ranger components and their status (Started or Disabled). To the right of the summary, there is a 'Service Actions' dropdown menu with several options: Start, Stop (which is highlighted with a red box), Restart All, Enable Ranger Admin HA, Run Service Check, and Turn On Maintenance Mode.

2. Use the following CLI commands to change to the Ranger Admin directory and create a self-signed certificate.

```
cd /etc/ranger/admin/conf
keytool -genkey -keyalg RSA -alias rangeradmin -keystore ranger-admin-keystore.jks -storepass xasecure -validity 360 -keysize 2048
chown ranger:ranger ranger-admin-keystore.jks
chmod 400 ranger-admin-keystore.jks
```

When prompted, provide the host name as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore.



### Note


When prompted for your password, press the Enter key. This will not work for Java keytool version 1.5.

3. Use the following steps to disable the HTTP port and enable the HTTPS port with the required keystore information.

- a. Select **Configs > Advanced**. Under Ranger Settings, clear the **HTTP enabled** check box (this blocks all agent calls to the HTTP port even if the port is up and working).

The screenshot shows the Ambari interface for a 'test\_cluster'. On the left sidebar, 'Ranger' is selected. In the main content area, the 'Configs' tab is active under the 'Advanced' section. The 'Ranger Settings' group is expanded, showing the 'External URL' field set to 'https://c6403.ambari.apache.org:8182' and the 'Authentication method' dropdown set to 'LDAP'. At the bottom of this group, there is a checkbox labeled 'HTTP enabled' which is currently checked (indicated by a green checkmark). This checkbox is highlighted with a red rectangular box.

- b. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.



c. Under Advanced ranger-admin-site, set the following properties:

- **ranger.https.attrib.keystore.file** – Provide the location of the keystore file created previously: /etc/ranger/admin/conf/ranger-admin-keystore.jks.
- **ranger.service.https.attrib.keystore.pass** – Enter the password for the keystore (in this case, xasecure).
- **ranger.service.https.attrib.keystore.keyalias** – Enter the alias name for the keystore private key (in this case, rangeradmin).
- **ranger.service.https.attrib.clientAuth** – Enter want as the value. This validates the client cert from all agents, but not the requests from web applications. Setting this value to want requires the client to have a certificate to use to sign traffic. If you do not want to put certificates on the client machines to do two-way SSL, this parameter can be set to false to enable one-way SSL.
- **ranger.service.https.attrib.ssl.enabled** – set this property to true.
- **ranger.service.https.port** – Make sure that this port is available, or change the value to an available port number.

Advanced ranger-admin-site

ranger.audit.source.type	solr		
ranger.credential.provider.path	/etc/ranger/admin/rangeradmin.jceks		
ranger.https.attrib.keystore.file	/etc/ranger/admin/conf/ranger-admin-keystore.jks		
ranger.jpa.audit.jdbc.credential.alias	rangeraudit		
ranger.jpa.audit.jdbc.dialect	<code>{{{jdbc_dialect}}}</code>		
ranger.jpa.audit.jdbc.driver	<code>{{{ranger_jdbc_driver}}}</code>		
ranger.jpa.audit.jdbc.password	.....	.....	
ranger.jpa.audit.jdbc.url	<code>{{{audit_jdbc_url}}}</code>		
ranger.jpa.audit.jdbc.user	<code>{{{ranger_audit_db_user}}}</code>		
ranger.jpa.jdbc.credential.alias	rangeradmin		
ranger.jpa.jdbc.dialect	<code>{{{jdbc_dialect}}}</code>		
ranger.jpa.jdbc.password	.....	.....	
ranger.jpa.jdbc.user	<code>{{{ranger_db_user}}}</code>		
Group Search Base	<code>{{{ranger_ug_ldap_group_searchbase}}}</code>		
Group Search Filter	<code>{{{ranger_ug_ldap_group_searchfilter}}}</code>		
ranger.service.host	<code>{{{ranger_host}}}</code>		
ranger.service.http.port	6080		
ranger.service.https.attrib.clientAuth	want		
ranger.service.https.attrib.keystore.keyalias	rangeradmin		
ranger.service.https.attrib.keystore.pass	.....	.....	
ranger.service.https.attrib.ssl.enabled	true		
ranger.service.https.port	6182		

4. Under Custom ranger-admin-site, add the following properties:

- `ranger.service.https.attrib.keystore.file` – Specify the same value provided for the `ranger.https.attrib.keystore.file` property.

- ranger.service.https.attrib.client.auth – Specify the same value provided for the ranger.service.https.attrib.clientAuth property.

To add a Custom ranger-admin-site property:

- a. Select **Custom ranger-admin-site**, then click **Add Property**.

The screenshot shows a hierarchical menu structure for configuration. At the top level, 'AD Settings' is expanded, showing 'ranger.ldap.ad.domain' set to 'localhost' and 'ranger.ldap.ad.url' set to 'ldap://ad.xasecure.net:389'. Below this, several collapsed sections are listed: 'LDAP Settings', 'Advanced ranger-admin-site' (which is currently selected), 'Advanced ranger-env', 'Advanced ranger-ugsync-site', 'Custom admin-properties', and 'Custom ranger-admin-site'. The 'Custom ranger-admin-site' section is expanded, revealing an 'Add Property ...' button which is highlighted with a red box. Underneath this, three more collapsed sections are shown: 'Custom ranger-site', 'Custom ranger-ugsync-site', and 'Custom usersync-properties'.

- b. On the Add Property pop-up, type the property name in the **Key** box, type the property value in the **Value** box, then click **Add**.

The screenshot shows a 'Add Property' dialog box. The 'Type' field contains 'ranger-admin-site.xml'. The 'Key' field contains 'ranger.service.https.attrib.keystore.file'. The 'Value' field contains '/etc/ranger/admin/conf/ranger-admin-keystore.jks'. At the bottom right of the dialog, there are two buttons: 'Cancel' and a green 'Add' button, which is highlighted with a red box.

5. Save your changes and start Ranger Admin.

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the ranger.service.https.port property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

#### 4.19.2.3. Configuring Ranger Usersync

1. Stop Ranger Usersync by selecting the **Ranger Usersync** link, then select **Started > Stop** next to Ranger Usersync.

Ambari test\_cluster 0 ops 16 alerts

Dashboard Services Hosts 1 Alerts Admin admin

c6403.ambari.apache.org

Back

Summary Configs Alerts 15 Versions Host Actions

Components

Component	Status
Accumulo GC / Accumulo	Stopped
Accumulo Master / Accumulo	Stopped
Accumulo Monitor / Accumulo	Stopped
Accumulo Tracer / Accumulo	Stopped
App Timeline Server / YARN	Started
Atlas Metadata Server / Atlas	Started
DRPC Server / Storm	Started
Falcon Server / Falcon	Stopped
HBase Master / HBase	Stopped
History Server / MapReduce2	Started
Hive Metastore / Hive	Started
HiveServer2 / Hive	Started
SmartSense HST Server / SmartSense	Stopped
Kafka Broker / Kafka	Started
Knox Gateway / Knox	Started
Metrics Collector / Ambari Metrics	Stopped
MySQL Server / Hive	Started
NameNode / HDFS	Started
Nimbus / Storm	Started
Oozie Server / Oozie	Started
Ranger Admin / Ranger	Started
Ranger Usersync / Ranger	Started
ResourceManager / YARN	Restart
SNameNode / HDFS	Stop
Spark History Server / Spark	Started
Storm UI Server / Storm	Started

Host Metrics Last 1 hour

Metric	Value
CPU Usage	No Data Available
Disk Usage	No Data Available
Load	No Data Available
Memory Usage	No Data Available
Network Usage	No Data Available
Processes	No Data Available

2. Check to see if `unixauthservice.jks` is in the `/etc/ranger/usersync/conf/` directory. If not, run the following commands in the CLI:

```
cd /etc/ranger/usersync/conf/
mkdir cert
keytool -genkeypair -keyalg RSA -alias selfsigned -keystore /etc/ranger/
usersync/conf/cert/unixauthservice.jks -keypass Unix529p -storepass Unix529p
-validity 3600 -keysize 2048 -dname 'cn=unixauthservice,ou=authenticator,o=
mycompany,c=US'
chown -R ranger:ranger /etc/ranger/usersync/conf/cert
chmod -R 400 /etc/ranger/usersync/conf/cert
```

3. Use the following CLI commands to create a truststore for the Ranger Admin's self-signed keystore. When prompted for a password, press the Enter key.

```
cd /etc/ranger/usersync/conf/
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cer
chown -R ranger:ranger /etc/ranger/usersync/conf/cert
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore mytruststore.jks -storepass changeit
chown ranger:ranger mytruststore.jks
```

4. Navigate back to Ranger and select **Configs > Advanced**, then click **Advanced ranger-usersync-site**. Set the following properties:

- `ranger.usersync.truststore.file` – Enter the path to the truststore file.
- `ranger.usersync.truststore.password` – Enter the truststore password.



5. Start Ranger Usersync by selecting the **Ranger Usersync** link on the Summary tab, then select **Stopped > Start** next to Ranger Usersync.

#### 4.19.2.4. Configuring Ranger Plugins

The following section shows how to configure the Ranger HDFS plugin for SSL with a self-signed certificate. You can use the same procedure for other Ranger components. Additional steps required to configure the Ranger KMS plugin and server are provided in subsequent sections.



##### Note

- To ensure a successful connection after SSL is enabled, self-signed certificates should be imported to the Ranger Admin's trust store (typically JDK cacerts).
- The `ranger.plugin.<service>.policy.rest.ssl.config.file` property should be verified, for example:

```
ranger.plugin.hive.policy.rest.ssl.config.file ==> /etc/
hive/conf/conf.server/ranger-policymgr-ssl.xml
```

#### 4.19.2.4.1. Configuring the Ranger HDFS Plugin for SSL

The following steps show how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components.

1. Stop HDFS by selecting **Service Actions > Stop**.

The screenshot shows the Ambari interface for a 'test\_cluster'. On the left, a sidebar lists various services: HDFS (selected), MapReduce2, YARN, Tez, Hive, HBase, Pig, Sqoop, Oozie, ZooKeeper, Falcon, Storm, Flume, Accumulo, Ambari Metrics, Atlas, Kafka, Knox, Mahout, Ranger, Slider, SmartSense (with 1 alert), and Spark. The main area displays the 'Summary' tab for the HDFS service. It shows the following metrics:

- NameNode**: Started
- SNameNode**: Started
- DataNodes**: 1/1 Started
- DataNodes Status**: 1 live / 0 dead / 0 decommissioning
- NFSGateways**: 0/0 Started
- NameNode Uptime**: 21.82 days
- NameNode Heap**: 159.3 MB / 1011.3 MB (15.8% used)
- Disk Usage (DFS Used)**: 869.6 MB / 488.2 GB (0.17%)
- Disk Usage (Non DFS Used)**: 38.3 GB / 488.2 GB (7.84%)

Below this is a 'Metrics' section with several counters, all showing 'No Data Available':

NameNode GC count	NameNode GC time	NN Connection Load	NameNode Heap	NameNode Host Load
No Data Available	No Data Available	No Data Available	No Data Available	No Data Available

NameNode RPC	Failed disk volumes	Corrupted Blocks	Under Replicated Blocks	HDFS Space Utilization
No Data Available	n/a	0	481	n/a

A context menu is open over the 'Stop' button in the 'Actions' dropdown. The 'Stop' option is highlighted with a red box. Other options in the menu include: Start, Restart All, Restart DataNodes, Move NameNode, Move SNameNode, Enable NameNode HA, Run Service Check, Turn On Maintenance Mode, Rebalance HDFS, and Download Client Configs.

2. Use the following CLI commands to change to the Ranger HDFS plugin directory and create a self-signed certificate.

```
cd /etc/hadoop/conf
keytool -genkey -keyalg RSA -alias rangerHdfsAgent -keystore ranger-plugin-
keystore.jks -storepass myKeyFilePassword -validity 360 -keysize 2048
chown hdfs:hdfs ranger-plugin-keystore.jks
chmod 400 ranger-plugin-keystore.jks
```

When prompted, provide an identifiable string as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore. When prompted for a password, press the Enter key.



### Note

**Important note:** In the case where multiple servers talking to ranger admin for downloading policies for the same service/repository (e.g. HBase Master and Region servers, multiple NameNodes or Hive servers in an HA environment, be sure to use the repo name or a common string across all of the nodes (such as HbasePlugin, HdfsPlugin etc). (Note this and enter the same value in Common Name For Certificate field in the edit repository page in the Policy Manager UI).

3. Use the following CLI commands to create a truststore for the agent and add the Admin public key as a trusted entry. When prompted for a password, press the Enter key.

```
cd /etc/hadoop/conf
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cer
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore ranger-plugin-truststore.jks -storepass changeit
chown hdfs:hdfs ranger-plugin-truststore.jks
chmod 400 ranger-plugin-truststore.jks
```

4. Under Ranger Settings, provide the value in the **External URL** box in the format `https://<hostname of policy manager>:<https port>`.

5. Select **Advanced ranger-hdfs-policymgr-ssl** and set the following properties:

- `xasecure.policymgr.clientssl.keystore` – Enter the location of the keystore created in the previous step.
- `xasecure.policymgr.clientssl.keystore.password` – Enter the keystore password.
- `xasecure.policymgr.clientssl.truststore` – Enter the location of the truststore created in the previous step.
- `xasecure.policymgr.clientssl.truststore.password` – Enter the truststore password.

Advanced ranger-hdfs-policymgr-ssl

xasecure.policymgr. clientssl.keystore	/etc/hadoop/conf/ranger-plugin-keystore.jks			
xasecure.policymgr. clientssl.keystore. credential.file	jceks://file{{credential_file}}			
xasecure.policymgr. clientssl.keystore. password	.....	.....		
xasecure.policymgr. clientssl.truststore	/etc/hadoop/conf/ranger-plugin-truststore.jks			
xasecure.policymgr. clientssl.truststore. credential.file	jceks://file{{credential_file}}			
xasecure.policymgr. clientssl.truststore. password	.....	.....		

6. Select Advanced ranger-hdfs-plugin-properties, then select the **Enable Ranger for HDFS** check box.

Advanced ranger-hdfs-plugin-properties

<input checked="" type="checkbox"/> Enable Ranger for HDFS				
Ranger repository config password	.....	.....		
Ranger repository config user	hadoop			
common.name.for. certificate	.....			
hadoop.rpc.protection	.....			
Policy user for HDFS	ambari-qa			

7. Click **Save** to save your changes.
  8. Start HDFS by selecting **Service Actions > Start**.
  9. Stop Ranger Admin by selecting **Service Actions > Stop**.
10. Use the following CLI commands to add the agent's self-signed cert to the Admin's trustedCACerts.

```
cd /etc/ranger/admin/conf
keytool -export -keystore /etc/hadoop/conf/ranger-plugin-keystore.jks
-alias rangerHdfsAgent -file ranger-hdfsAgent-trust.cer -storepass
myKeyFilePassword
keytool -import -file ranger-hdfsAgent-trust.cer -alias rangerHdfsAgentTrust
-keystore <Truststore file used by Ranger Admin - can be the JDK cacerts> -
storepass changeit
```

11. Restart Ranger Admin.
12. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of your repository (in this case, hadoopdev) and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.
13. Start the HDFS service.
14. In the Policy Manager UI, select **Audit > Plugins**. You should see an entry for your repo name with HTTP Response Code 200.

#### 4.19.2.4.2. Configuring the Ranger KMS Plugin for SSL

To configure the Ranger KMS (Key Management Service) plugin for SSL, use the procedure described in the previous section for HDFS, then perform the following additional step.

Log into the Policy Manager UI (as the keyadmin user) and click the **Edit** button of your KMS repository. Provide the CN name of the keystore as the value for Common Name For Certificate and save your changes. This property is not provided by default, so it must be added.

The screenshot shows the Ranger UI for creating a new service. The top navigation bar has tabs for 'Ranger', 'Access Manager', and 'Encryption'. Below the tabs, there are links for 'Service Manager' and 'Edit Service', with 'Create Service' being the active tab. The main form is titled 'Service Details:' and contains fields for 'Service Name' (cl1\_kms), 'Description' (kms repo), and 'Active Status' (radio buttons for Enabled and Disabled, with Enabled selected). The 'Config Properties:' section includes fields for 'KMS URL' (kms://https@ip-172-31-26-219.ec2), 'Username' (keyadmin), and 'Password' (redacted). It also features a table for 'Add New Configurations' with a single row: 'commonNameForCertificate' (Value: ip-172-31-26-219.ec2.internal) and a delete button. A 'Test Connection' button is located below the table. At the bottom of the form are 'Save', 'Cancel', and 'Delete' buttons.

#### 4.19.2.4.3. Configuring the Ranger KMS Server for SSL

Use the following steps to configure Ranger KMS (Key Management Service) Server for SSL.

1. Stop Ranger KMS by selecting **Service Actions > Stop**.
2. Use the following CLI commands to change to the Ranger KMS configuration directory and create a self-signed certificate.

```
cd /etc/ranger/kms/conf
keytool -genkey -keyalg RSA -alias rangerkms -keystore ranger-kms-keystore.jks
-jks -storepass rangerkms -validity 360 -keysize 2048
chown kms:kms ranger-kms-keystore.jks
chmod 400 ranger-kms-keystore.jks
```

When prompted, provide an identifiable string as the value for the "What is your first and last name?" question. Then provide answers to the subsequent questions to create the keystore. When prompted for a password, press the Enter key.

3. Select **Custom ranger-kms-site**, then add the following properties as shown below:

ranger.https.attrib.keystore.file

ranger.service.https.attrib.keystore.file (duplicate of above – workaround for now)

ranger.service.https.attrib.clientAuth

ranger.service.https.attrib.client.auth (duplicate of above – workaround for now)

ranger.service.https.attrib.keystore.keyalias

ranger.service.https.attrib.keystore.pass

ranger.service.https.attrib.ssl.enabled

ranger.service.https.port

The screenshot shows a configuration interface for the 'Custom ranger-kms-site' section. It lists several properties with their current values and status indicators (green or red).

Property	Value	Status
ranger.https.attrib.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	Green
ranger.service.https.attrib.client.auth	want	Green
ranger.service.https.attrib.clientAuth	false	Green
ranger.service.https.attrib.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	Green
ranger.service.https.attrib.keystore.keyalias	rangerkms	Green
ranger.service.https.attrib.keystore.pass	rangerkms	Green
ranger.service.https.attrib.ssl.enabled	true	Green
ranger.service.https.port	9393	Green

[Add Property ...](#)

4. Under Advanced kms\_env, update the value of **kms\_port** to match the value of **ranger.service.https.port**.

5. Save your changes and restart Ranger KMS.

When you attempt to access the Ranger KMS UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

6. Use the following CLI commands to export the Ranger KMS certificate.

```
cd /usr/hdp/<version>/ranger-kms/conf
keytool -export -keystore ranger-kms-keystore.jks -alias rangerkms -file
ranger-kms-trust.cer
```

7. Use the following CLI command to import the Ranger KMS certificate into the Ranger Admin truststore.

```
keytool -import -file ranger-kms-trust.cer -alias rangerkms -keystore
<Truststore file used by Ranger Admin - can be the JDK cacerts> -storepass
changeit
```

8. Use the following CLI command to import the Ranger KMS certificate into the Hadoop client truststore.

```
keytool -import -file ranger-kms-trust.cer -alias rangerkms -keystore /etc/
security/clientKeys/all.jks -storepass bigdata
```

9. Restart Ranger Admin and HDFS.

## 4.20. Configure Non-Ambari Ranger SSL

### 4.20.1. Configuring Non-Ambari Ranger SSL Using Public CA Certificates

If you have access to Public CA issued certificates, use the following steps to configure non-Ambari Ranger SSL.

#### 4.20.1.1. Configuring Ranger Admin

1. Use the following CLI command to stop Ranger Admin.

```
ranger-admin stop
```

2. Open the `ranger-admin-site.xml` file in a text editor.

```
vi /usr/hdp/current/ranger-admin/ews/webapp/WEB-INF/classes/conf/ranger-
admin-site.xml
```

3. Update `ranger-admin-site.xml` as follows:

- `ranger.service.http.port` – Comment out the value for this property.
- `ranger.service.http.enabled` – Set the value of this property to `false`.
- `ranger.service.https.attrib.ssl.enabled` – Set the value of this property to `true`.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.
- `ranger.https.attrib.keystore.file` – Provide the location of the Public CA issued keystore file.

- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore.
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key.
- `ranger.externalurl` – Set the value of this property in the format: `https://<hostname of policy manager>:<https port>`.
- Add or update the following properties with the values shown below:

```
<property>
 <name>ranger.service.https.attrib.clientAuth</name>
 <value>want</value>
</property>

<property>
 <name>ranger.service.https.attrib.client.auth</name>
 <value>want</value>
</property>

<property>
 <name>ranger.https.attrib.keystore.file</name>
 <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>

<property>
 <name>ranger.service.https.attrib.keystore.file</name>
 <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>
```

4. Save the changes to `ranger-admin-site.xml`, then use the following command to start Ranger Admin.

```
ranger-admin start
```

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS.

#### 4.20.1.2. Configuring Ranger Usersync

1. Use the following CLI command to stop the Ranger Usersync service.

```
ranger-usersync stop
```

2. Use the following commands to change to the Usersync install directory and open the `install.properties` file in a text editor.

```
cd /usr/hdp/current/ranger-usersync/
vi install.properties
```

3. Set the value of `POLICY_MGR_URL` in the format: `https://<hostname of policy manager>:<https port>` and save your changes.

4. Run the following commands to install the new settings.

```
cd /usr/hdp/current/ranger-usersync/
./setup.sh
```

5. Use the following command to start the Ranger Usersync service.

```
ranger-usersync start
```

### 4.20.1.3. Configuring Ranger Plugins

This section shows how to configure the Ranger HDFS plugin for SSL. You can use the same procedure for other Ranger components.

1. Use the following CLI command to stop the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh stop
namenode"
```

2. Open the HDFS `install.properties` file in a text editor.

```
vi /usr/hdp/<version>/ranger-hdfs-plugin/install.properties
```

3. Update `install.properties` as follows:

- **POLICY\_MGR\_URL** – Set this value in the format: `https://<hostname of policy manager>:<https port>`
- **SSL\_KEYSTORE\_FILE\_PATH** – The path to the location of the Public CA issued keystore file.
- **SSL\_KEYSTORE\_PASSWORD** – The keystore password.
- **SSL\_TRUSTSTORE\_FILE\_PATH** – The truststore file path.
- **SSL\_TRUSTSTORE\_PASSWORD** – The truststore password.  
Save the changes to the `install.properties` file.

4. Use the following command to see if `JAVA_HOME` is available.

```
echo $JAVA_HOME
```

5. If `JAVA_HOME` is not available , use the following command to set `JAVA_HOME` (Note that Ranger requires Java 1.7).

```
export JAVA_HOME=<path for java 1.7>
```

6. Run the following commands to switch to the HDFS plugin install directory and run the install agent to update the plugin with the new configuration settings.

```
cd /usr/hdp/<version>/ranger-hdfs-plugin/
./enable-hdfs-plugin.sh
```

7. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of your repository (in this case, hadoopdev) and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.

8. Use the following command to start the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh start namenode"
```

9. In the Policy Manager UI, select **Audit > Plugins**. You should see an entry for your repo name with HTTP Response Code 200.

## 4.20.2. Configuring Non-Ambari Ranger SSL Using a Self Signed Certificate

If you do not have access to Public CA issued certificates, use the following steps to create a self-signed certificate and configure Non-Ambari Ranger SSL.

### 4.20.2.1. Configuring Ranger Admin

1. Use the following CLI command to stop Ranger Admin.

```
ranger-admin stop
```

2. Use the following commands to change to the Ranger Admin directory and create a self-signed certificate.

```
cd /etc/ranger/admin/conf
keytool -genkey -keyalg RSA -alias rangeradmin -keystore ranger-admin-keystore.jks -storepass xasecure -validity 360 -keysize 2048
chown ranger:ranger ranger-admin-keystore.jks
chmod 400 ranger-admin-keystore.jks
```

When prompted, provide the host name as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore.



#### Note

When prompted for your password, press the Enter key. This will not work for Java keytool version 1.5.

3. Open the `ranger-admin-site.xml` file in a text editor.

```
vi /usr/hdp/current/ranger-admin/ews/webapp/WEB-INF/classes/conf/ranger-admin-site.xml
```

4. Update `ranger-admin-site.xml` as follows:

- `ranger.service.http.port` – Comment out the value for this property.
- `ranger.service.http.enabled` – Set the value of this property to `false`.
- `ranger.service.https.attrib.ssl.enabled` – Set the value of this property to `true`.
- `ranger.service.https.port` – Make sure that this port is available, or change the value to an available port number.

- `ranger.https.attrib.keystore.file` – Provide the location of the keystore file created previously: `/etc/ranger/admin/conf/ranger-admin-keystore.jks`.
- `ranger.service.https.attrib.keystore.pass` – Enter the password for the keystore (in this case, `xasecure`).
- `ranger.service.https.attrib.keystore.keyalias` – Enter the alias name for the keystore private key (in this case, `rangeradmin`).
- `ranger.externalurl` – Set the value of this property in the format: `https://<hostname of policy manager>:<https port>`.
- Add or update the following properties with the values shown below:

```
<property>
 <name>ranger.service.https.attrib.clientAuth</name>
 <value>want</value>
</property>

<property>
 <name>ranger.service.https.attrib.client.auth</name>
 <value>want</value>
</property>

<property>
 <name>ranger.https.attrib.keystore.file</name>
 <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>

<property>
 <name>ranger.service.https.attrib.keystore.file</name>
 <value>/etc/ranger/admin/conf/ranger-admin-keystore.jks</value>
</property>
```

5. Save the changes to `ranger-admin-site.xml`, then use the following command to start Ranger Admin.

```
ranger-admin start
```

When you attempt to access the Ranger Admin UI with the HTTPS protocol on the port specified by the `ranger.service.https.port` property, the browser should report that it does not trust the site. Click Proceed anyway and you should be able to access the Ranger Admin UI over HTTPS with the self-signed cert you just created.

#### 4.20.2.2. Configuring Ranger Usersync

1. Use the following CLI command to stop the Ranger Usersync service.

```
ranger-usersync stop
```

2. Check to see if `unixauthservice.jks` is in the `/etc/ranger/usersync/conf/` directory. If not, run the following commands in the CLI:

```
cd /etc/ranger/usersync/conf/
mkdir cert
keytool -genkeypair -keyalg RSA -alias selfsigned -keystore /etc/ranger/
usersync/conf/cert/unixauthservice.jks -keypass Unix529p -storepass Unix529p
-validity 3600 -keysize 2048 -dname 'cn=unixauthservice,ou=authenticator,ou=
mycompany,c=US'
chown -R ranger:ranger /etc/ranger/usersync/conf/cert
chmod -R 400 /etc/ranger/usersync/conf/cert
```

3. Use the following commands to change to the Usersync install directory and open the `install.properties` file in a text editor.

```
cd /usr/hdp/current/ranger-usersync/
vi install.properties
```

4. Set the value of `POLICY_MGR_URL` in the format: `https://<hostname of policy manager>:<https port>` and save your changes.
5. Use the following commands to create a truststore for the Ranger Admin's self-signed keystore. When prompted for a password, press the Enter key.

```
cd /etc/ranger/usersync/conf/
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -
alias rangeradmin -file ranger-admin-trust.cerchown -R ranger:ranger /etc/
ranger/usersync/conf/cert
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -
keystore mytruststore.jks -storepass changeit
chown ranger:ranger mytruststore.jks
```

6. Use the following commands to change to the Usersync conf directory and open the `ranger-ugsync-site.xml` file in a text editor.

```
cd /usr/hdp/current/ranger-usersync/conf/
vi ranger-ugsync-site.xml
```

Edit the following properties, then save your changes:

- `ranger.usersync.truststore.file` – Enter the path to the truststore file.
- `ranger.usersync.truststore.password` – Enter the truststore password.

7. Run the following commands to install the new settings.

```
cd /usr/hdp/current/ranger-usersync/
./setup.sh
```

8. Use the following command to start the Ranger Usersync service.

```
ranger-usersync start
```

### 4.20.2.3. Configuring Ranger Plugins

The following steps describe how to configure the Ranger HDFS plugin for SSL with a self-signed certificate in a non-Ambari cluster. You can use the same procedure for other Ranger components.

1. Use the following CLI command to stop the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh stop namenode"
```

2. Use the following commands to change to the Ranger HDFS plugin directory and create a self-signed certificate.

```
3. cd /etc/hadoop/conf
keytool -genkey -keyalg RSA -alias rangerHdfsAgent -keystore ranger-plugin-keystore.jks -storepass myKeyFilePassword -validity 360 -keysize 2048
chown hdfs:hdfs ranger-plugin-keystore.jks
chmod 400 ranger-plugin-keystore.jks
```

When prompted, provide an identifiable string as the value for the "What is your first and last name?" question. then provide answers to the subsequent questions to create the keystore. When prompted for a password, press the Enter key.



### Note

Important note: In the case where multiple servers talking to ranger admin for downloading policies for the same service/repository (e.g. HBase Master and Region servers, multiple NameNodes or Hive servers in an HA environment, be sure to use the repo name or a common string across all of the nodes (such as HbasePlugin, HdfsPlugin etc). (Note this and enter the same value in Common Name For Certificate field in the edit repository page in the Policy Manager UI).

4. Use the following CLI commands to create a truststore for the agent and add the Admin public key as a trusted entry. When prompted for a password, press the Enter key.

```
cd /etc/hadoop/conf
keytool -export -keystore /etc/ranger/admin/conf/ranger-admin-keystore.jks -alias rangeradmin -file ranger-admin-trust.cer
keytool -import -file ranger-admin-trust.cer -alias rangeradmintrust -keystore ranger-plugin-truststore.jks -storepass changeit
chown hdfs:hdfs ranger-plugin-truststore.jks
chmod 400 ranger-plugin-truststore.jks
```

5. Open the HDFS install.properties file in a text editor.

```
vi /usr/hdp/<version>/ranger-hdfs-plugin/install.properties
```

6. Update install.properties as follows:

- POLICY\_MGR\_URL – Set this value in the format: https://<hostname of policy manager>:<https port>
- SSL\_KEYSTORE\_FILE\_PATH – The path to the location of the keystore file.
- SSL\_KEYSTORE\_PASSWORD – The keystore password.
- SSL\_TRUSTSTORE\_FILE\_PATH – The truststore file path.
- SSL\_TRUSTSTORE\_PASSWORD – The truststore password.  
Save the changes to the install.properties file.

7. Use the following command to see if JAVA\_HOME is available.

```
echo $JAVA_HOME
```

8. If `JAVA_HOME` is not available , use the following command to set `JAVA_HOME` (Note that Ranger requires Java 1.7).

```
export JAVA_HOME=<path for java 1.7>
```

9. Run the following commands to switch to the HDFS plugin install directory and run the install agent to update the plugin with the new configuration settings.

```
cd /usr/hdp/<version>/ranger-hdfs-plugin/
./enable-hdfs-plugin.sh
```

10. Use the following command to stop Ranger Admin.

```
ranger-admin stop
```

11. Use the following commands to add the agent's self-signed cert to the Admin's trustedCACerts.

```
cd /etc/ranger/admin/conf
keytool -export -keystore /etc/hadoop/conf/ranger-plugin-keystore.jks
 -alias rangerHdfsAgent -file ranger-hdfsAgent-trust.cer -storepass
 myKeyFilePassword
keytool -import -file ranger-hdfsAgent-trust.cer -alias rangerHdfsAgentTrust
 -keystore <Truststore file used by Ranger Admin - can be the JDK cacerts> -
 storepass changeit
```

12. Use the following command to start Ranger Admin.

```
ranger-admin start
```

13. Log into the Ranger Policy Manager UI as the admin user. Click the **Edit** button of your repository (in this case, hadoopdev) and provide the CN name of the keystore as the value for **Common Name For Certificate**, then save your changes.

14. Use the following command to start the NameNode.

```
su -l hdfs -c "/usr/hdp/current/hadoop-client/sbin/hadoop-daemon.sh start
namenode"
```

15. In the Policy Manager UI, select **Audit > Plugins**. You should see an entry for your repo name with HTTP Response Code 200.

## 4.21. Connecting to SSL-Enabled Components

This section explains how to connect to SSL enabled HDP Components.



### Note

In order to access SSL enabled HDP Services through the Knox Gateway, additional configuration on the Knox Gateway is required, see [Apache Knox Gateway Administrator Guide](#), [Gateway Security](#), [Configure Wire Encryption](#).

## 4.21.1. Connect to SSL Enabled HiveServer2 using JDBC

HiveServer2 implemented encryption with the Java SASL protocol's quality of protection (QOP) setting that allows data moving between a HiveServer2 over JDBC and a JDBC client to be encrypted.

From the JDBC client specify `sasl.sop` as part of the JDBC-Hive connection string, for example `jdbc:hive://hostname/dbname;sasl.qop=auth-int`. For more information on connecting to Hive, see [Data Integration Services with HDP, Moving Data into Hive: Hive ODBC and JDBC Drivers](#).



### Tip

See [HIVE-4911](#) for more details on this enhancement.

## 4.21.2. Connect to SSL Enabled Oozie Server

On every Oozie client system, follow the instructions for the type of certificate used in your environment.

### 4.21.2.1. Use a Self-signed Certificate from Oozie Java Clients

When using a self-signed certificate, you must first install the certificate before the Oozie client can connect to the server.

1. Install the certificate in the keychain:

a. Copy or download the .cert file onto the client machine.

b. Run the following command (as root) to import the certificate into the JRE's keystore:

```
sudo keytool -import -alias tomcat -file path/to/certificate.cert -keystore <JRE_cacerts>
```

Where `$JRE_cacerts` is the path to the JRE's certs file. It's location may differ depending on the Operating System, but it's typically called `cacerts` and located at `$JAVA_HOME/lib/security/cacerts`. It can be under a different directory in `$JAVA_HOME`. The default password is `changeit`.

Java programs, including the Oozie client, can now connect to the Oozie Server using the self-signed certificate.

2. In the connection strings change HTTP to HTTPS, for example, replace

`http://oozie.server.hostname:11000/oozie` with `https://oozie.server.hostname:11443/oozie`.

Java does not automatically redirect HTTP addresses to HTTPS.

### 4.21.2.2. Connect to Oozie from Java Clients

In the connection strings change HTTP to HTTPS and adjust the port, for example, replace `http://oozie.server.hostname:11000/oozie` with `https://oozie.server.hostname:11443/oozie`.

Java does not automatically redirect HTTP addresses to HTTPS.

#### 4.21.2.3. Connect to Oozie from a Web Browser

Use `https://oozie.server.hostname:11443/oozie` though most browsers should automatically redirect you if you use `http://oozie.server.hostname:11000/oozie`.

When using a Self-Signed Certificate, your browser warns you that it can't verify the certificate. Add the certificate as an exception.

# 5. Auditing in Hadoop

## 5.1. Using Apache Solr for Ranger Audits

Apache Solr is an open-source enterprise search platform. Apache Ranger can use Apache Solr to store audit logs, and Solr can also provide a search capability of the audit logs through the Ranger Admin UI.



### Important

Solr must be installed and configured before installing RangerAdmin or any of the Ranger component plugins.

It is recommended that Ranger audits be written to both Solr and HDFS. Audits to Solr are primarily used to enable search queries from the Ranger Admin UI. HDFS is a long-term destination for audits – audits stored in HDFS can be exported to any SIEM system, or to another audit store.

### Configuration Options

- Solr Standalone – Solr Standalone is only recommended for testing and evaluation. Solr Standalone is a single instance of Solr that does not require ZooKeeper.
- SolrCloud – This is the recommended configuration for Ranger. **SolrCloud** is a scalable architecture that can run as single node or as a multi-node cluster. It includes features such as replication and sharding, which are useful for high availability (HA) and scalability. With SolrCloud, you need to plan the deployment based on the cluster size.

The following sections describe how to install and configure Apache Solr for Ranger Audits:

- [Prerequisites \[356\]](#)
- [Installing Solr \[357\]](#)
- [Configuring Solr Standalone \[357\]](#)
- [Configuring SolrCloud \[358\]](#)

### 5.1.1. Prerequisites

#### Solr Prerequisites

- Ranger supports Apache Solr 5.2 or higher.
- Apache Solr requires the Java Runtime Environment (JRE) version 1.7 or higher.
- 1 TB free space in the volume where Solr will store the index data.
- 32 GB RAM.

### SolrCloud Prerequisites

- SolrCloud supports replication and sharding. It is highly recommended that you use SolrCloud with at least two Solr nodes running on different servers with replication enabled.
- SolrCloud requires Apache ZooKeeper.

## 5.1.2. Installing Solr

Use the following command to install Solr:

```
yum install lucidworks-hdpsearch
```

## 5.1.3. Configuring Solr Standalone

Use the following procedure to configure Solr Standalone.

1. Download the `solr_for_audit_setup_v3` file to the `/usr/local/` directory:

```
wget https://issues.apache.org/jira/secure/attachment/12761323/
solr_for_audit_setup_v3.tgz -O /usr/local/solr_for_audit_setup_v3.tgz
```

2. Use the following commands to switch to the `/usr/local/` directory and extract the `solr_for_audit_setup_v3` file.

```
cd /usr/local
tar xvf solr_for_audit_setup_v3.tgz
```

The contents of the `.tgz` file will be extracted into a `/usr/local/solr_for_audit_setup` directory.

3. Use the following command to switch to the `/usr/local/solr_for_audit_setup` directory.

```
cd /usr/local/solr_for_audit_setup
```

4. Use the following command to open the `install.properties` file in the `vi` text editor.

```
vi install.properties
```

Set the following property values, then save the changes to the `install.properties` file.

**Table 5.1. Solr `install.properties` Values**

Property Name	Value	Description
JAVA_HOME	<path_to_jdk>, for example: <code>/usr/jdk64/jdk1.8.0_60</code>	Provide the path to the JDK install folder. For Hadoop, you can check <code>/etc/hadoop/conf/hadoop-env.sh</code> for the value of <code>JAVA_HOME</code> . As noted previously, Solr only supports JDK 1.7 and higher.
SOLR_USER	<code>solr</code>	The Linux user used to run Solr.
SOLR_INSTALL_FOLDER	<code>/opt/lucidworks-hdpsearch/solr</code>	The Solr installation directory.

Property Name	Value	Description
SOLR_RANGER_HOME	/opt/solr/ranger_audit_server	The location where the Ranger-related configuration and schema files will be copied.
SOLR_RANGER_PORT	6083	The Solr port for Ranger.
SOLR_DEPLOYMENT	standalone	The deployment type.
SOLR_RANGER_DATA_FOLDER	/opt/solr/ranger_audit_server/data	The folder where the index data will be stored. The volume for this folder should have at least 1 TB free space for the index data, and should be backed up regularly.
SOLR_LOG_FOLDER	/var/log/solr/ranger_audits	The folder for the Solr log files.
SOLR_MAX_MEM	2g	The memory allocation for Solr.

5. Use the following command to run the Solr for Ranger setup script.

```
./setup.sh
```

6. To start Solr, log in as the `solr` or `root` user and run the following command.

```
/opt/solr/ranger_audit_server/scripts/start_solr.sh
```

When Solr starts, a confirmation message appears.

```
Started Solr server on port 6083 (pid=). Happy searching!
```

7. You can use a web browser to open the Solr Admin Console at the following address:

```
http:<solr_host>:6083/solr
```



### Note

You can use the following command to stop Solr:

```
/opt/solr/ranger_audit_server/scripts/stop_solr.sh
```

## 5.1.4. Configuring SolrCloud

Use the following procedure to configure SolrCloud.

1. Download the `solr_for_audit_setup_v3` file to the `/usr/local/` directory:

```
wget https://issues.apache.org/jira/secure/attachment/12761323/
solr_for_audit_setup_v3.tgz -O /usr/local/solr_for_audit_setup_v3.tgz
```

2. Use the following commands to switch to the `/usr/local/` directory and extract the `solr_for_audit_setup_v3` file.

```
cd /usr/local
tar xvf solr_for_audit_setup_v3.tgz
```

The contents of the `.tgz` file will be extracted into a `/usr/local/solr_for_audit_setup` directory.

3. Use the following command to switch to the `/usr/local/solr_for_audit_setup` directory.

```
cd /usr/local/solr_for_audit_setup
```

4. Use the following command to open the `install.properties` file in the vi text editor.

```
vi install.properties
```

Set the following property values, then save the changes to the `install.properties` file.

**Table 5.2. Solr install.properties Values**

Property Name	Value	Description
JAVA_HOME	<path_to_jdk>, for example: /usr/jdk64/jdk1.8.0_40	Provide the path to the JDK install folder. For Hadoop, you can check <code>/etc/hadoop/conf/hadoop-env.sh</code> for the value of JAVA_HOME. As noted previously, Solr only supports JDK 1.7 and higher.
SOLR_USER	solr	The Linux user used to run Solr.
SOLR_INSTALL_FOLDER	/opt/lucidworks-hdpsearch/solr	The Solr installation directory.
SOLR_RANGER_HOME	/opt/solr/ranger_audit_server	The location where the Ranger-related configuration and schema files will be copied.
SOLR_RANGER_PORT	6083	The Solr port for Ranger.
SOLR_DEPLOYMENT	solrcloud	The deployment type.
SOLR_ZK	<ZooKeeper_host>:2181/ranger_audits	The Solr ZooKeeper host and port. It is recommended to provide a sub-folder to create the Ranger Audit related configurations so you can also use ZooKeeper for other Solr instances. Due to a Solr bug, if you are using a path (sub-folder), you can only specify one ZooKeeper host.
SOLR_SHARDS	1	If you want to distribute your audit logs, you can use multiple shards. Make sure the number of shards is equal or less than the number of Solr nodes you will be running.
SOLR_REPLICATION	1	It is highly recommend that you set up at least two nodes and replicate the indexes. This gives redundancy to index data, and also provides load balancing of Solr queries.
SOLR_LOG_FOLDER	/var/log/solr/ranger_audits	The folder for the Solr log files.
SOLR_MAX_MEM	2g	The memory allocation for Solr.

5. Use the following command to run the set up script.

```
./setup.sh
```

6. Run the following command **only once** from any node. This command adds the Ranger Audit configuration (including `schema.xml`) to ZooKeeper.

```
/opt/solr/ranger_audit_server/scripts/add_ranger_audits_conf_to_zk.sh
```

7. Log in as the `solr` or `root` user and run the following command to start Solr on each node.

```
/opt/solr/ranger_audit_server/scripts/start_solr.sh
```

When Solr starts, a confirmation message appears.

```
Started Solr server on port 6083 (pid=). Happy searching!
```

8. Run the following command **only once** from any node. This command creates the Ranger Audit collection.

```
/opt/solr/ranger_audit_server/scripts/create_ranger_audits_collection.sh
```

9. You can use a web browser to open the Solr Admin Console at the following address:

```
http:<solr_host>:6083/solr
```



#### Note

You can use the following command to stop Solr:

```
/opt/solr/ranger_audit_server/scripts/stop_solr.sh
```

## 5.2. Manually Enabling Audit Settings in Ambari Clusters

It is recommended that Ranger audits be written to both Solr and HDFS. Audits to Solr are primarily used to enable queries from the Ranger Admin UI. HDFS is a long-term destination for audits; audits stored in HDFS can be exported to any SIEM system, or to another audit store.

Solr and HDFS audits are generally enabled as part of the standard Ambari installation procedure. This section describes how to manually update Ambari audit settings for Solr and HDFS.

### 5.2.1. Manually Updating Ambari Solr Audit Settings

You can save and store Ranger audits to Solr if you have installed and configured the Solr service in your cluster.



#### Note

If you enabled Solr Audits as part of the standard Ambari installation procedure, audits to Solr are activated automatically when Ranger is enabled for a plugin.

To save Ranger audits to Solr:

1. From the Ambari dashboard, select the Ranger service. Select **Configs > Advanced**, then scroll down and select **Advanced ranger-admin-site**. Set the following property value:
  - `ranger.audit.source.type = solr`
2. On the Ranger Configs tab, select **Ranger Audit**. The SolrCloud button should be set to ON. The SolrCloud configuration settings are loaded automatically when the SolrCloud button is set from OFF to ON, but you can also manually update the settings.



### Note

Audits to Solr requires that you have already [installed Solr](#) and [configured SolrCloud](#).

3. Restart the Ranger service.
4. After the Ranger service has been restarted, you will then need to make specific configuration changes for each plugin to ensure that the plugin's data is captured in Solr.
5. For example, if you would like to configure HBase for audits to Solr, perform the following steps:
  - Select the Audit to Solr checkbox in Advanced ranger-hbase-audit.
  - Enable the Ranger plugin for HBase.
  - Restart the HBase component.
6. Verify that the Ranger audit logs are being passed to Solr by opening one of the following URLs in a web browser:  
[http://{RANGER\\_HOST\\_NAME}:6080/index.html#!/reports/audit/bigData](http://{RANGER_HOST_NAME}:6080/index.html#!/reports/audit/bigData)  
[http://{SOLR\\_HOST}:6083/solr/ranger\\_audits](http://{SOLR_HOST}:6083/solr/ranger_audits)

## 5.2.2. Manually Updating Ambari HDFS Audit Settings



### Note

HDFS audits are enabled by default in the standard Ranger Ambari installation procedure, and are activated automatically when Ranger is enabled for a plugin.

The following steps show how to save Ranger audits to HDFS for HBase. You can use the same procedure for other components.

1. From the Ambari dashboard, select the HBase service. On the Configs tab, scroll down and select **Advanced ranger-hbase-audit**. Select the **Audit to HDFS** check box.
2. Set the HDFS path where you want to store audits in HDFS:

```
xasecure.audit.destination.hdfs.dir = hdfs://
$NAMENODE_FQDN:8020/ranger/audit
```

Refer to the `fs.defaultFS` property in the **Advanced core-site settings**.



### Note

For NameNode HA, `NAMENODE_FQDN` is the cluster name. In order for this to work, `/etc/hadoop/conf/hdfs-site.xml` needs to be linked under `/etc/<component_name>/conf`.

3. Enable the Ranger plugin for HBase.
4. Make sure that the plugin sudo user should has permission on the HDFS Path:

```
hdfs://NAMENODE_FQDN:8020/ranger/audit
```

For example, we need to create a Policy for Resource : /ranger/audit, all permissions to user hbase.

5. Save the configuration updates and restart HBase.
6. Generate some audit logs for the HBase component.
7. Check the HDFS component logs on the NameNode:

```
hdfs://NAMENODE_FQDN:8020/ranger/audit
```



### Note

For a secure cluster, use the following steps to enable audit to HDFS for Storm, Kafka, and Knox:

- In core-site.xml set the hadoop.proxyuser.<component>.groups property with value “ \* ” or service user.
- For the Knox plugin there is one additional property to add to core-site.xml. Add hadoop.proxyuser.<component>.users property with value “ \* ” or service user (i.e knox).
- For Kafka and Knox, link to /etc/hadoop/conf/core-site.xml under /etc/<component\_name>/conf. For Storm, link to /etc/hadoop/conf/core-site.xml under /usr/hdp/<version>/storm/extlib-daemon/ranger-storm-plugin-impl/conf.
- Verify the service user principal.
- Make sure that the component user has permissions on HDFS.

## 5.3. Enabling Audit Logging in Non-Ambari Clusters

It is recommended that Ranger audits be written to both Solr and HDFS. Audits to Solr are primarily used to enable queries from the Ranger Admin UI. HDFS is a long-term destination for audits; audits stored in HDFS can be exported to any SIEM system, or to another audit store.

To enable auditing for HDFS, perform the steps listed below.

1. Set the XAAUDIT.HDFS.ENABLE value to "true" for the component plug-in in the install.properties file, which can be found here:

```
/usr/hdp/<version>/ranger-<component>=plugin
```

2. Configure the NameNode host in the XAAUDIT.HDFS.HDFS\_DIR field.

3. Create a policy in the HDFS service from the Ranger Admin for individual component users (hive/hbase/knox/storm/yarn/kafka/kms) to provide READ and WRITE permissions for the audit folder (i.e., for enabling Hive component to log Audits to HDFS, you need to create a policy for the hive user with Read and WRITE permissions for the audit directory).
4. Set the Audit to HDFS caches logs in the local directory, which can be specified in XAAUDIT.HDFS.LOCAL\_BUFFER\_DIRECTORY (this can be like /var/log/<component>/\*\*), which is the path where the audit is stored for a short time. This is similar for archive logs that need to be updated.

To enable auditing reporting from the Solr database, perform the steps listed below.

1. Modify the following properties in the Ranger service `install.properties` to enable auditing to the Solr database in Ranger:
  - `audit_store=solr`
  - `audit_solr_urls=http://solr_host:6083/solr/ranger_audits`
  - `audit_solr_user=ranger_solr`
  - `audit_solr_password=NONE`
2. Restart Ranger.

To enable auditing to the Solr database for a plug-in (e.g., HBase), perform the steps listed below.

1. Set the following properties in `install.properties` of the plug-in to begin audit logging to the Solr database:
  - `XAAUDIT.SOLR.IS.ENABLED=true`
  - `XAAUDIT.SOLR.ENABLE=true`
  - `XAAUDIT.SOLR.URL=http://solr_host:6083/solr/ranger_audits`
  - `XAAUDIT.SOLR.USER=ranger_solr`
  - `XAAUDIT.SOLR.PASSWORD=NONE`
  - `XAAUDIT.SOLR.FILE_SPOOL_DIR=/var/log/hadoop/hdfs/audit/solr/spool`
2. Enable the Ranger HBase plug-in.
3. Restart the HBase component.

## 5.4. Managing Auditing in Ranger

To explore options for auditing policies in Ranger, [access the Ranger console](#), then click **Audit** in the top menu.



There are four tabs on the Audit page:

- Access [365]
- Admin [366]
- Login Sessions [367]
- Plugins [368]



### Note

To access audit logs from the Ranger Audit UI, enable XAAUDIT.DB.IS\_ENABLED in your Ranger plug-in configuration.

## 5.4.1. View Operation Details

To view details on a particular operation, click the Policy ID, Operation name, or Session ID.

**Operation : update**

Policy ID : 2  
Policy Name : hbase-test-1-20160202224128  
Repository Type : hbase  
Updated Date : 02/16/2016 09:51:42 AM PST  
Updated By : Mal

Policy Details :

Fields	Old Value	New Value
table	*	*.y

**OK**

**Operation : create**

Policy ID : 13  
Policy Name : New-Service-1-20160211205602  
Repository Type :  
Created Date : 02/11/2016 12:56:02 PM PST  
Created By : Admin

Policy Details :

Fields	New Value
Policy Name	New-Service-1-20160211205602
Policy Description	Default Policy for Service: New-Service
Policy Status	enabled

Users/Groups Permissions :

New Value
Groups: <empty>
Users: admin

**OK**

The screenshot shows the Ranger Admin interface. At the top, there are tabs for Access, Admin (which is selected), Login Sessions, and Agents. Below the tabs is a search bar with placeholder text "Search for your access logs...". A blue arrow points from the "Access" tab area down to the audit log table.

The audit log table has columns: Operation, Audit type, User, Date (IST), Action, and Session Id. The data includes various events like "User profile password changed", "User updated", and "Policy updated". A blue arrow points from the "Operation : update" section to the "Deleted value" row in the table.

The "Operation : update" section contains details about a policy named "s1" for the "Storm" repository. It shows the "Old Value" and "New Value" for the "User Permissions" field. A blue arrow points from the "Deleted value" cell to the "Old Value" cell, and another arrow points from the "New value" cell to the "New Value" cell. The "Old Value" cell contains "Admin , Submit Topology , Kill Topology" and the "New Value" cell contains "Submit Topology , File Download , Admin".

On the right side of the dialog, there is a legend: "Added" (green square) and "Deleted" (red square). A blue arrow points from the "OK" button at the bottom right to the "OK" button in the bottom right corner of the dialog.

## 5.4.2. Access

Provides Service activity data for all Policies that have Audit set to **On**. The default service Policy is configured to log all user activity within the Service. This default policy does not contain user and group access rules.

You can filter the data based on the following criteria:

**Table 5.3. Search Criteria**

Search Criteria	Description
Access Enforcer	Access enforcer indicates who made the decision to allow or deny. In case of HDFS, the enforcer would XA (Ranger) or Hadoop.
Access Type	Type of access user attempted (E.G., REVOKE, GRANT, OPEN, USE).
Client IP	IP address of the user system that tried to access the resource.
Result	Shows whether the operation was successfull or not.
Service Name	The name of the service that the user tried to access.
Service Type	The type of the service that the user tried to access.
Start Date, End Date	Filters results for a particular date range.
User	Name of the user which tried to access the resource.

Access Audit Log									
Policy ID	Event Time	User	Service Name / Type	Resource Name	Access Type	Result	Access Enforcer	Client IP	Event Count
4	07/30/2015 05:43:37 PM	hbase	hbasedev hbase	testtable2/*/*	revoke	Allowed	ranger-adl	172.22.115.226	1
4	07/30/2015 05:14:59 PM	hbase	hbasedev hbase	testtable2/*/*	grant	Allowed	ranger-adl	172.22.115.226	1
4	07/30/2015 05:14:03 PM	hbase	hbasedev hbase	testtable2	open	Allowed	ranger-adl		1
4	07/30/2015 04:56:30 PM	hbase	hbasedev hbase	icowr/*/*	grant	Allowed	ranger-adl	172.22.115.207	1
4	07/30/2015 04:51:24 PM	hbase	hbasedev hbase	icowr	open	Allowed	ranger-adl		1
5	07/30/2015 03:24:26 PM	hive	hive dev hive		USE	Allowed	ranger-adl	172.22.115.226	1
5	07/30/2015 03:23:51 PM	hive	hive dev hive		USE	Allowed	ranger-adl	172.22.115.226	1
--	07/30/2015 11:41:26 AM	hbase	cl_hadoop hdfs	/apps/hbase/data/oldWALS	READ_EXECUTE	Allowed	hadoop-adl	172.22.115.226	1

### 5.4.3. Admin

The Admin tab contains all events for the HDP Security Administration Web UI, including Service, Service Manager, Log in, etc. (actions like create, update, delete, password change).

Audit Log						
Operation	Audit Type	User	Date ( PST )	Actions	Session Id	
Policy updated hbase-test-1-20160202224128	Ranger Policy	Mail	02/16/2016 09:51:42 AM	update	52509	
Policy updated Example-Service-1-20160211205602	Ranger Policy	admin	02/11/2016 12:56:48 PM	update	52478	
Service updated Example-Service	Ranger Service	admin	02/11/2016 12:56:34 PM	update	52478	
Policy created New-Service-1-20160211205602	Ranger Policy	admin	02/11/2016 12:56:02 PM	create	52478	
Service created New-Service	Ranger Service	admin	02/11/2016 12:56:02 PM	create	52478	
Policy updated hbase-test-1-20160202224128	Ranger Policy	admin	02/11/2016 10:27:15 AM	update	52461	
User updated Mail	XA User	admin	02/11/2016 10:26:06 AM	update	52461	
Group created UX	XA Group	admin	02/11/2016 10:25:21 AM	create	52461	
Policy created test-storm-1-20160211010740	Ranger Policy	admin	02/10/2016 05:07:40 PM	create	52391	

You can filter the data based on the following criteria:

**Table 5.4. Search Criteria**

Search Criteria	Description
Action	These are operations performed on resources (actions like create, update, delete, password change).
Audit Type	There are three values Resource,asset and xa user according to operations performed on Service,policy and users.
End Date	Login time and date is stored for each session. A date range is used to filter the results for that particular date range.
Session ID	The session count increments each time you try to login to the system

Search Criteria	Description
Start Date	Login time and date is stored for each session. A date range is used to filter the results for that particular date range.
User	Username who has performed create,update,delete operation.

## 5.4.4. Login Sessions

The Login Sessions tab logs the information related to the sessions for each login.

You can filter the data based on the following criteria:

**Table 5.5. Search Criteria**

Search Criteria	Description
Login ID	The username through which someone logs in to the system.
Session-id	The session count increments each time the user tries to log into the system.
Start Date, End Date	Specifies that results should be filtered based on a particular start date and end date.
Login Type	The mode through which the user tries to login (by entering username and password).
IP	The IP address of the system through which the user logged in.
User Agent	The login time and date for each session.
Login time	Logs whether or not the login was successful. Possible results can be Success, Wrong Password, Account Disabled, Locked, Password Expired or User Not Found.

Session Id	Login Id	Result	Login Type	IP	User Agent	Login Time ( PST )
52329	amb_ranger_admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 12:50:32 PM
52328	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 12:50:32 PM
52327	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 12:50:32 PM
52326	admin	Success	Username/Password	192.168.64.1	Mozilla/5.0 (Macintosh; Intel ...	02/09/2016 12:39:38 PM
52325	amb_ranger_admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 10:50:32 AM
52324	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 10:50:32 AM
52323	admin	Success	Username/Password	192.168.64.101	Python-urllib/2.6	02/09/2016 10:50:32 AM
52322	rangerusersync	Success	Username/Password	192.168.64.101	Java/1.8.0_60	02/09/2016 10:21:22 AM
52321	rangerusersync	Success	Username/Password	192.168.64.101	Java/1.8.0_60	02/09/2016 10:21:21 AM
52320	rangerusersync	Success	Username/Password	192.168.64.101	Java/1.8.0_60	02/09/2016 10:21:21 AM
52319	rangerusersync	Success	Username/Password	192.168.64.101	Java/1.8.0_60	02/09/2016 10:21:21 AM

## 5.4.5. Plugins

This tab shows the upload history of the Security Agents. This module displays all of the services exported from the system. You can filter the data based on the following criteria:

**Table 5.6. Agents Search Criteria**

Search Criteria	Description
Plugin IP	IP Address of the agent that tried to export the service.
Plugin ID	Name of the agent that tried to export the service.
HTTP Response Code	The HTTP code returned when trying to export the service.
Start Date, End Date	Export time and date is stored for each agent. A date range is used to filter the results for that particular date range.
Service Name	The service name we are trying to export.

# 6. Data Protection: HDFS Encryption

## 6.1. Ranger KMS Administration Guide

The Ranger Key Management Service (Ranger KMS) is a open source, scalable cryptographic key management service supporting HDFS "data at rest" encryption.

Ranger KMS is based on the Hadoop KMS originally developed by the Apache community. The Hadoop KMS stores keys in a file-based Java keystore by default. Ranger extends the native Hadoop KMS functionality by allowing you to store keys in a secure database.

Ranger provides centralized administration of the key management server through the Ranger admin portal.

There are three main functions within the Ranger KMS:

1. **Key management.** Ranger admin provides the ability to create, update or delete keys using the Web UI or REST APIs. All [Hadoop KMS APIs](#) work with Ranger KMS using the keyadmin username and password.
2. **Access control policies.** Ranger admin also provides the ability to manage access control policies within Ranger KMS. The access policies control permissions to generate or manage keys, adding another layer of security for data encrypted in Hadoop.
3. **Audit.** Ranger provides full audit trace of all actions performed by Ranger KMS.

Ranger KMS along with HDFS encryption are recommended for use in all environments. In addition to secure key storage using a database, Ranger KMS is also scalable, and multiple versions of Ranger KMS can be run behind a load balancer.

For more information about HDFS encryption, see [HDFS "Data at Rest" Encryption](#).

### 6.1.1. Installing the Ranger Key Management Service

This section describes how to install the Ranger Key Management Service (KMS) using Ambari on a Kerberized cluster.

#### Prerequisites

Ranger KMS requires HDFS and Ranger to be installed and running on the cluster.

To install Ranger using Ambari, refer to the [Ranger Installation Guide](#). (For more information about the Ambari Add Service Wizard, see [Adding a Service](#) in the *Ambari User's Guide*.)

To use 256-bit keys, install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all hosts in the cluster. For installation information, see [Install the JCE](#). Make sure that the Java location is specified in the \$PATH environment variable.




#### Note

If you use the OpenJDK package, the JCE file is already built into the package.

### 6.1.1.1. Install Ranger KMS using Ambari (Kerberized Cluster)

To install Ranger KMS on a Kerberized cluster, complete the following steps.

1. Go to the Ambari Web UI, <http://<gateway-URL>:8080>.
2. From the Ambari dashboard, go to the **Actions** menu. Choose **Add Service**.
3. On the next screen, check the box next to **Ranger KMS**:



4. Then, choose **Next**.
5. (Optional) In **Assign Masters**, if you wish to override the default host setting, specify the Ranger KMS host address. For example:

### Add Service Wizard

HiveServer2: vp-os-rh6-my-sec-nokms-1507

HBase Master: vp-os-rh6-my-sec-nokms-1507

Oozie Server: vp-os-rh6-my-sec-nokms-1507

ZooKeeper Server: vp-os-rh6-my-sec-nokms-1507

ZooKeeper Server: vp-os-rh6-my-sec-nokms-1507

ZooKeeper Server: vp-os-rh6-my-sec-nokms-1507

Nimbus: vp-os-rh6-my-sec-nokms-1507

DRPC Server: vp-os-rh6-my-sec-nokms-1507

Storm UI Server: vp-os-rh6-my-sec-nokms-1507

Kafka Broker: vp-os-rh6-my-sec-nokms-1507

Kafka Broker: vp-os-rh6-my-sec-nokms-1507

Kafka Broker: vp-os-rh6-my-sec-nokms-1507

Metrics Collector: vp-os-rh6-my-sec-nokms-1507

Ranger KMS Server: vp-os-rh6-my-sec-nokms-1507

Knox Gateway: vp-os-rh6-my-sec-nokms-1507-2.openstacklocal (15.6 GB, 2 cores)  
vp-os-rh6-my-sec-nokms-1507-3.openstacklocal (15.6 GB, 2 cores)  
vp-os-rh6-my-sec-nokms-1507-4.openstacklocal (15.6 GB, 2 cores)  
vp-os-rh6-my-sec-nokms-1507-5.openstacklocal (15.6 GB, 2 cores)

Ranger Admin: vp-os-rh6-my-sec-nokms-1507

Ranger UserSync: vp-os-rh6-my-sec-nokms-1507

[← Back](#) [Next →](#)

6. In **Customize Services**, set required values (marked in red). Review other configuration settings, and determine whether you'd like to change any of the default values. (For more information about these properties, see [Ranger KMS Properties](#).)

a. Set the following required settings, marked in red in the "Advanced kms-properties" section:

- KMS\_MASTER\_KEY\_PASSWD
- db\_password
- db\_root\_password



#### Note

If do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. For more information, see [Setting up Database Users Without Sharing DBA Credentials](#).

The screenshot shows the "Customize Services" step of the "Add Service Wizard". The left sidebar lists steps: Choose Services, Assign Masters, Assign Slaves and Clients, **Customize Services**, Configure Identities, Review, Install, Start and Test, and Summary. The main area is titled "Customize Services" with a sub-section for "Ranger KMS". It displays configuration groups: Advanced dbks-site, Advanced kms-env, Advanced kms-log4j, and Advanced kms-properties (which is expanded to show DB\_FLAVOR set to MySQL, KMS\_MASTER\_KEY\_PA password fields, REPOSITORY\_CONFIG\_PASSWORD password fields, REPOSITORY\_CONFIG\_USERNAME set to keyadmin, SQL\_CONNECTOR\_JAR set to /usr/share/java/mysql-connector-java.jar, db\_host set to vp-os-rh6-my-sec-nokms-150727-1736-5.openstacklocal, db\_name set to rangerkms, db\_password password fields, db\_root\_password password fields, db\_root\_user set to root, and db\_user set to rangerkms).

Also specify the username for REPOSITORY\_CONFIG\_USERNAME, so that Ranger will be able to connect to the Ranger KMS Server and look up keys for creating access policies. This user will need to be set to proxy into Ranger KMS in a Kerberos mode (steps included below).

- Add values for the following properties in the "Custom kms-site" section. These properties allow the specified system users (hive, oozie, and others) to proxy on behalf of other users when communicating with Ranger KMS. This helps individual services (such as Hive) use their own keytabs, but retain the ability to access Ranger KMS as the end user (use access policies associated with the end user).
  - hadoop.kms.proxyuser.hive.users
  - hadoop.kms.proxyuser.oozie.users
  - hadoop.kms.proxyuser.HTTP.users
  - hadoop.kms.proxyuser.ambari.users
  - hadoop.kms.proxyuser.yarn.users
  - hadoop.kms.proxyuser.hive.hosts

- hadoop.kms.proxyuser.oozie.hosts
  - hadoop.kms.proxyuser.HTTP.hosts
  - hadoop.kms.proxyuser.ambari.hosts
  - hadoop.kms.proxyuser.yarn.hosts
- c. Add the following properties to the Custom KMS-site section of the configuration. These properties use the REPOSITORY\_CONFIG\_USERNAME specified in the first step in this section.

If you are using an account other than keyadmin to access Ranger KMS, replace "keyadmin" with the configured user for the Ranger KMS repository in Ranger admin:

- hadoop.kms.proxyuser.keyadmin.groups=\*
- hadoop.kms.proxyuser.keyadmin.hosts=\*
- hadoop.kms.proxyuser.keyadmin.users=\*

### Add Property

Type	kms-site.xml	X
Properties key=value (one per line)	<pre>hadoop.kms.proxyuser.keyadmin.groups=* hadoop.kms.proxyuser.keyadmin.hosts=* hadoop.kms.proxyuser.keyadmin.users=*</pre>	Cancel Add

- d. Confirm settings of the following values in the "advanced kms-site" group:

- hadoop.kms.authentication.type=kerberos
- hadoop.kms.authentication.kerberos.keytab=/etc/security/keytabs/spnego.service.keytab
- hadoop.kms.authentication.kerberos.principal=\*

7. Then, choose **Next**.

8. Review the default values on the **Configure Identities** screen. Determine whether you'd like to change any of the default values. Then, choose **Next**.
9. In **Review**, make sure the configuration values are correct. Ranger KMS will be listed under **Services**.

10. Then, choose **Deploy**.

11. Monitor the progress of installing, starting, and testing the service. When the service installs and starts successfully, choose **Next**.

12. The Summary screen displays the results. Choose **Complete**.

13. Restart the Ranger and Ranger KMS services.

#### 6.1.1.1. Setting up Database Users Without Sharing DBA Credentials

If you do not wish to provide system Database Administrator (DBA) account details to the Ambari Ranger installer, you can use the `dba_script.py` Python script to create Ranger DB database users without exposing DBA account information to the Ambari Ranger installer. You can then run the normal Ambari Ranger installation without specifying a DBA user name and password.

To create Ranger DB users using the `dba_script.py` script:

1. Download the Ranger rpm using the `yum install` command.

```
yum install ranger-kms
```

2. You should see one file named `dba_script.py` in the `/usr/hdp/current/ranger-admin` directory.

3. Get the script reviewed internally and verify that your DBA is authorized to run the script.

4. Execute the script by running the following command:

```
python dba_script.py
```

5. Pass all values required in the argument. These should include `db flavor`, `JDBC jar`, `db host`, `db name`, `db user`, and other parameters.

- If you would prefer not to pass runtime arguments via the command prompt, you can update the `/usr/hdp/current/ranger-admin/install.properties` file and then run:

- `python dba_script.py -q`

When you specify the `-q` option, the script will read all required information from the `install.properties` file

- You can use the `-d` option to run the script in "dry" mode. Running the script in dry mode causes the script to generate a database script.

```
python dba_script.py -d /tmp/generated-script.sql
```

Anyone can run the script, but it is recommended that the system DBA run the script in dry mode. In either case, the system DBA should review the generated script, but should only make minor adjustments to the script, for example, change the location of a particular database file. No major changes should be made that substantially alter the script – otherwise the Ranger install may fail.

The system DBA must then run the generated script.

6. Log in to the host where KMS is to be installed. Run the following commands to back up files:

```
cp /var/lib/ambari-agent/cache/common-services/RANGER_KMS/0.5.0.2.3/package/
scripts/kms.py /var/lib/ambari-agent/cache/common-services/RANGER_KMS/0.5.0.
2.3/package/scripts/kms.py.bak
cp /var/lib/ambari-server/resources/common-services/RANGER_KMS/0.5.0.2.3/
package/scripts/kms.py /var/lib/ambari-server/resources/common-services/
RANGER_KMS/0.5.0.2.3/package/scripts/kms.py.bak
```

7. In both of the `kms.py` files copied in the previous step, find and comment out the following line (shown here commented out).

```
#Execute(dba_setup, environment=env_dict, logoutput=True, user=params.
kms_user)
```

8. Run the Ranger Ambari install procedure, but set **Setup Database and Database User** to **No** in the Ranger Admin section of the Customize Services screen.

#### 6.1.1.1.2. Configure HDFS Encryption to use Ranger KMS Access

At this point, Ranger KMS should be installed and running. If you plan to use Ranger KMS for HDFS data at rest encryption, complete the following steps:

1. Create a link to `/etc/hadoop/conf/core-site.xml` under `/etc/ranger/kms/conf`:

```
sudo ln -s /etc/hadoop/conf/core-site.xml /etc/ranger/kms/conf/
core-site.xml
```

2. Configure HDFS to access Ranger KMS.

- a. In the left panel of the Ambari main menu, choose HDFS.
- b. Choose the **Configs** tab at the top of the page, and then choose the **Advanced** tab partway down the page.
- c. Specify the provider path (the URL where the Ranger KMS server is running) in the following two properties, if the path is not already specified:
  - In "Advanced core-site", specify `hadoop.security.key.provider.path`
  - In "Advanced hdfs-site", specify `dfs.encryption.key.provider.uri`

The Ranger KMS host is where Ranger KMS is installed. The Ranger KMS host name should have the following format:

kms://http@<kmshost>:9292/kms

3. Under Custom core-site.xml, set the value of the `hadoop.proxyuser.kms.groups` property to \* or service user.
4. Restart the Ranger KMS service and the HDFS service.

#### 6.1.1.1.3. Use a Kerberos Principal for the Ranger KMS Repository

In Ranger, all access policies are configured within a repository for each service. For more information, refer to the [Ranger User Guide](#).

To manage access policies for Ranger KMS, a repository is needed with Ranger for the Ranger KMS service. Ambari creates the repository automatically using the repository config user and password provided.

The repository config user also needs to be created as a principal in Kerberos with a password. Use the following steps to use a Kerberos principle for the Ranger KMS repository.

1. Create system user `keyadmin` which should be sync in User Tabs in Ranger Admin.
2. Create principal `keyadmin@EXAMPLE.COM` with password `keyadmin`:

```
kadmin.local -q 'addprinc -pw keyadmin keyadmin'
```

3. On the Add Service wizard Customize Services page, set the required values (marked in red).
4. Under ranger-kms-properties, set the principal and password in the REPOSITORY\_CONFIG\_USERNAME and REPOSITORY\_CONFIG\_PASSWORD fields.
5. To check logs, select **Audit to DB** under Advanced ranger-kms-audit.
6. Click **Next** to continue with the Ranger KMS Add Service wizard.

Advanced kms-properties	
REPOSITORY_CONFIG_USERNAME	keyadmin@EXAMPLE.COM
SQL_CONNECTOR_JAR	/usr/share/java/mysql-connector-java.jar
db_host	mp-secranger-2406-3.openstacklocal
db_user	rangerkms
db_password	.....
DB_FLAVOR	MYSQL
db_root_user	root
db_root_password	.....
db_name	rangerkms
KMS_MASTER_KEY_PASWD	.....
REPOSITORY_CONFIG_PASSWORD	.....

## 6.1.2. Enable Ranger KMS Audit

Ranger KMS supports audit to DB, HDFS, and Solr. Solr is well-suited for short-term auditing and UI access (for example, one month of data accessible via quick queries in the Web UI). HDFS is typically used for archival auditing. They are not mutually exclusive; we recommend configuring audit to both Solr and HDFS.

First, make sure Ranger KMS logs are enabled:

1. Go to the Ambari UI: <http://<gateway>:8080>
2. Select `ranger-kms` from the service.
3. Click the Configs tab, and go to the accordion menu.
4. In the Advanced ranger-kms-audit list, set `xasecure.audit.is.enabled` to true.
5. Select "Audit to Solr" and/or "Audit to HDFS", depending on which database(s) you plan to use:

## 6. Save the configuration and restart the Ranger KMS service.

Next, check to see if the Ranger KMS Plugin is enabled:

1. Go to the Ranger UI: <http://<gateway>:6080>
2. Login with your keyadmin user ID and password (the defaults are keyadmin, keyadmin). The default repository will be added under KMS service.
3. Run a test connection for the service. You should see a 'connected successfully' popup message. If the connection is not successful, make sure that the configured user exists (in KDC for a secure cluster).
4. Choose the Audit > Plugin tab.
5. Check whether plugins are communicating. The UI should display `Http Response code 200` for the respective plugin.

The next two subsections describe how to save audit to Solr and HDFS.

### 6.1.2.1. Save Audits to Solr



#### Note

Saving audits to Solr requires that you have already [installed Solr](#) and [configured SolrCloud](#).

To save audits to Solr:

1. From the Ambari dashboard, select the Ranger service. Select **Configs > Advanced**, then scroll down and select **Advanced ranger-admin-site**. Set the following property value:
  - `ranger.audit.source.type = solr`

2. On the Ranger Configs tab, select **Ranger Audit**. The SolrCloud button should be set to ON. The SolrCloud configuration settings are loaded automatically when the SolrCloud button is set from OFF to ON, but you can also manually update the settings.
3. Restart the Ranger service.
4. Next, to enable Ranger KMS auditing to Solr, set the following properties in the Advanced ranger-kms-audit list:
  - a. Check the box next to `Enable audit to solr` in the Ranger KMS component.
  - b. Check the `Audit provider summary enabled` box, and make sure that `xasecure.audit.is.enabled` is set to true.
  - c. Restart Ranger KMS.



#### Note

Check audit logs on Ranger UI, to make sure that they are getting through Solr: `http://RANGER_HOST_NAME:6080/index.html#!/reports/audit/bigData` or `http://solr_host:6083/solr/ranger_audits`.

#### 6.1.2.2. Save Audits to HDFS

There are no configuration changes needed for Ranger properties.

To save Ranger KMS audits to HDFS, set the following properties in the Advanced ranger-kms-audit list.

**Note:** the following configuration settings must be changed in each Plugin.

1. Check the box next to `Enable Audit to HDFS` in the Ranger KMS component.
2. Set the HDFS path to the path of the location in HDFS where you want to store audits:

```
xasecure.audit.destination.hdfs.dir = hdfs://NAMENODE_FQDN:8020/ranger/audit
```

3. Check the `Audit provider summary enabled` box, and make sure that `xasecure.audit.is.enabled` is set to true.
4. Make sure that the plugin's root user (`kms`) has permission to access HDFS Path `hdfs://NAMENODE_FQDN:8020/ranger/audit`
5. Restart Ranger KMS.
6. Generate audit logs for the Ranger KMS.
7. **(Optional)** To verify audit to HDFS without waiting for the default sync delay (approximately 24 hours), restart Ranger KMS. Ranger KMS will start writing to HDFS after the changes are saved post-restart.

To check for audit data:

```
hdfs dfs -ls /ranger/audit/
```

To test Ranger KMS audit to HDFS, complete the following steps:

1. Under custom core-site.xml, set hadoop.proxyuser.kms.groups to "\*" or to the service user.
2. In the custom kms-site file, add hadoop.kms.proxyuser.keyadmin.users and set its value to "\*". (If you are not using keyadmin to access Ranger KMS Admin, replace "keyadmin" with the user account used for authentication.)
3. In the custom kms-site file, add hadoop.kms.proxyuser.keyadmin.hosts and set its value to "\*". (If you are not using keyadmin to access Ranger KMS Admin, replace "keyadmin" with the user account used for authentication.)
4. Copy the core-site.xml to the component's class path (/etc/ranger/kms/conf)  
OR  
`ln -s /etc/hadoop/conf/core-site.xml /etc/ranger/kms/conf/core-site.xml`
5. Verify the service user principal. (For Ranger KMS it will be the http user.)
6. Make sure that the component user has permission to access HDFS. (For Ranger KMS the http user should also have permission.)

### 6.1.3. Enabling SSL for Ranger KMS

If you do not have access to Public CA-issued certificates, complete the following steps to create and configure self-signed certificates.



#### Note

The following examples contain sample values (folder locations, passwords, and filenames). Change these values according to your environment.

Considerations:

- Copy keystore/truststore files into a different location (e.g. /etc/security/serverKeys) than the /etc/<component>/conf folders.
- Make sure JKS file names are different from each other.
- Make sure correct permissions are applied.
- Make sure all passwords are secured.
- For the test connection to be successful after enabling SSL, self-signed certificates should be imported to the Ranger admin's trust store (typically JDK cacerts).
- Property ranger.plugin.service.policy.rest.ssl.config.file should be verified; for example:

```
ranger.plugin.kms.policy.rest.ssl.config.file ==> /etc/ranger/kms/conf/ranger-policymgr-ssl.xml
```

To enable SSL:

1. Stop the Ranger KMS service:



2. Go to the Ranger KMS (and plugin) installation location, and create a self-signed certificate:

```
cd /etc/ranger/kms/conf/
```

```
keytool -genkey -keyalg RSA -alias rangerKMSAgent -keystore <ranger-kms-ks> -storepass myKeyFilePassword -validity 360 -keysize 2048
```

```
chown kms:kms <ranger-kms-ks>
```

```
chmod 400 <ranger-kms-ks>
```

where

<ranger-kms-ks> is the name of the Ranger KMS keystore (for example, ranger-plugin-keystore.jks)

3. Provide an identifiable string in response to the question "What is your first and last name?"

**Important:** In case multiple servers need to communicate with Ranger admin for downloading policies for the same service/repository, make sure to use the repo name or a common string across all nodes. Remember exactly what you entered, because this value will be required for the Common Name for Certificate field on the edit repository page in the policy manager UI.

To create the keystore, provide answers to the subsequent questions. **Note:** Press enter when prompted for a password.

4. Create a truststore for the Ranger KMS plugin, and add the public key of admin as a trusted entry into the truststore:

```
cd /etc/ranger/kms/conf/
```

```
keytool -export -keystore <ranger-admin-ks> -alias rangeradmin -file <cert-filename>
```

```
keytool -import -file <cert-filename> -alias rangeradmintrust -keystore <ranger-kms-ts> -storepass changeit
```

```
chown kms:kms <ranger-kms-ts>
```

```
chmod 400 <ranger-kms-ts>
```

where

<ranger-admin-ks> is the location of the Ranger Admin keystore (for example, /etc/ranger/admin/conf/ranger-admin-keystore.jks)

<ranger-kms-ts> is the name of the Ranger KMS plugin truststore (for example, ranger-plugin-truststore.jks)

<cert-filename> is the name of the Ranger Admin certificate file (for example, ranger-admin-trust.cer)

**Note:** Press enter when prompted for a password.

5. Change the policy manager URL to point to HTTPS, and specify the keystore & truststore in ews/webapp/WEB-INF/classes/conf/ranger-policymgr-ssl.xml.
  - a. In xasecure.policymgr.clientssl.keystore, provide the location for the keystore that you created in the previous step.
  - b. In xasecure.policymgr.clientssl.keystore.password, provide the password for the keystore (myKeyFilePassword).
  - c. In xasecure.policymgr.clientssl.truststore, provide the location for the truststore that you created in the previous step.
  - d. In xasecure.policymgr.clientssl.truststore.password, provide the password for the truststore (changeit).
6. Add the plugin's self-signed cert into Admin's trustedCACerts:

```
cd /etc/ranger/admin/conf
```

```
keytool -export -keystore <ranger-kms-ks> -alias rangerKMSAgent
-file <cert-filename> -storepass myKeyFilePassword
```

```
keytool -import -file <cert-filename> -alias rangerkmsAgentTrust
-keystore <ranger-admin-ts> -storepass changeit
```

where

<ranger-kms-ks> is the path to the Ranger KMS keystore (for example, /etc/ranger/kms/conf/ranger-plugin-keystore.jks)

<cert-filename> is the name of the certificate file (for example, ranger-kmsAgent-trust.cer)

<ranger-admin-ts> is the name of the Ranger Admin truststore file (for example, the JDK cacerts file)

7. Log into the Policy Manager UI (as keyadmin user) and click on the Edit button of your KMS repository. Provide the CN name of the keystore for **Common Name For Certificate** (commonNameForCertificate), and save it. This property is not added by default.

The screenshot shows the 'Create Service' page in the Ranger UI. The 'Service Manager' tab is selected. In the 'Service Details' section, 'Service Name' is set to 'cl1\_kms' and 'Description' is 'kms repo'. The 'Active Status' is set to 'Enabled'. In the 'Config Properties' section, 'KMS URL' is 'kms://https://ip-172-31-26-219.ec2.internal', 'Username' is 'keyadmin', and 'Password' is '\*\*\*\*\*'. A table titled 'Add New Configurations' contains a single row with 'Name' 'commonNameForCertificate' and 'Value' 'ip-172-31-26-219.ec2.internal'. Below the table is a 'Test Connection' button. At the bottom are 'Save', 'Cancel', and 'Delete' buttons.

## Configuring the Ranger KMS Server

1. Go to the Ranger KMS config location and create a self-signed certificate:

```
cd /etc/ranger/kms/conf

keytool -genkey -keyalg RSA -alias rangerkms -keystore <ranger-kms-ks> -storepass rangerkms -validity 360 -keysize 2048

chown kms:kms ranger-kms-keystore.jks

chmod 400 ranger-kms-keystore.jks
```

where

<ranger-kms-ks> is the name of the Ranger KMS keystore (for example, ranger-plugin-keystore.jks)

Provide an identifiable string in response to the question "What is your first and last name?" To create the keystore, provide answers to all subsequent questions to create the keystore **Note:** Press enter when prompted for a password.

2. Add the following properties and values to the Custom ranger-kms-site list:

Custom ranger-kms-site

ranger.https.attrib.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.attrib.client.auth	want	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.attrib.clientAuth	false	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.attrib.keystore.file	/etc/ranger/kms/conf/ranger-kms-keystore.jks	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.attrib.keystore.keyalias	rangerkms	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.attrib.keystore.pass	rangerkms	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.attrib.ssl.enabled	true	<span style="color: green;">●</span>	<span style="color: red;">●</span>
ranger.service.https.port	9393	<span style="color: green;">●</span>	<span style="color: red;">●</span>

[Add Property ...](#)

3. Update the value of `kms_port` (in Advanced `kms_env`) to the `ranger.service.https.port` value.
4. Save your changes and start Ranger KMS.
5. In your browser (or from Curl) when you access the Ranger KMS UI using the HTTPS protocol on the `ranger.service.https.port` listed in Ambari, the browser should respond that it does not trust the site. Proceed, and you should be able to access Ranger KMS on HTTPS with the self-signed cert that you just created.
6. Export the Ranger KMS certificate:

```
cd /usr/hdp/<version>/ranger-kms/conf
keytool -export -keystore <ranger-kms-ks> -alias rangerkms -file <cert-filename>
```

where

<ranger-kms-ks> is the name of the Ranger KMS keystore (for example, `ranger-kms-keystore.jks`)

<cert-filename> is the name of the certificate file (for example, `ranger-kms-trust.cer`)

7. Import the Ranger KMS certificate into the Ranger admin truststore:

```
keytool -import -file <cert-filename> -alias rangerkms -keystore <ranger-admin-ts> -storepass changeit
```

where

<cert-filename> is the name of the certificate file (for example, ranger-kms-trust.cer)

<ranger-admin-ts> is the name of the Ranger Admin truststore file (for example, JDK cacerts)

#### 8. Import the Ranger KMS certificate into the Hadoop client truststore:

```
keytool -import -file <cert-filename> -alias rangerkms -keystore <ts-filename> -storepass bigdata
```

where

<cert-filename> is the name of the certificate file (for example, ranger-kms-trust.cer)

<ts-filename> is the name of Hadoop client truststore file (for example, /etc/security/clientKeys/all.jks)

#### 9. Restart Ranger Admin and Ranger KMS.

10. Now in the Policy Manager UI, Audit → Plugin tab, you should see an entry for your service name with HTTP Response Code = 200.

### 6.1.4. Install Multiple Ranger KMS

Multiple services can be set up for high availability of Ranger KMS. HDFS interacts with the active process.

Prerequisite: an instance with more than one node.

To install Ranger KMS on multiple nodes:

1. First install Ranger KMS on a single node (see [Installing the Ranger Key Management Service](#)).
2. Next, add the Ranger KMS service to another node.


In the Ambari Web UI for the additional node, go to Ranger KMS service # Summary # Service Actions # Add Ranger KMS server.



3. After adding Ranger KMS server, Ambari will show a pop-up message.

4. Press OK. Ambari will modify two HDFS properties, hadoop.security.key.provider.path and dfs.encryption.key.provider.uri.

5. Restart the HDFS service:



6. For the Ranger KMS service, go to the Advanced kms-site list and change the following property values:

```
hadoop.kms.cache.enable=false
```

```
hadoop.kms.cache.timeout.ms=0
```

```
hadoop.kms.current.key.cache.timeout.ms=0
```

```
hadoop.kms.authentication.signer.secret.provider=zookeeper
```

```
hadoop.kms.authentication.signer.secret.provider.zookeeper.connection.string
ip of first node}:2181,{internal ip of second node}:2181, ...
```

```
hadoop.kms.authentication.signer.secret.provider.zookeeper.auth.type=none
```

7. Save your configuration changes and restart the Ranger KMS service.

Next, check connectivity from Ranger admin for the newly-added Ranger KMS server:

1. Go to the Ranger UI: `http://<gateway>:6080`
2. Login with your keyadmin user ID and password (the defaults are keyadmin, keyadmin; these should be changed as soon as possible after installation). The default repository will be added under Ranger KMS service.
3. Under Config properties of the Ranger KMS URL, add the newly added Ranger KMS server FQDN. For example:

Previous Ranger KMS URL = `kms://http@<internal host name>:9292/kms`

New Ranger KMS URL = `kms://http@<internal host name1>;<internal host name2>...:9292/kms`

4. Run a test connection for the service. You should see a 'connected successfully' message.
5. Choose the Audit > Plugin tab.
6. Check whether plugins are communicating. The UI should display HTTP Response Code = 200 for the respective plugin.

## 6.1.5. Using the Ranger Key Management Service

Ranger KMS can be accessed at the Ranger admin URL, `http://<hostname>:6080`. Note, however, that the login user for Ranger KMS is different than that for Ranger. Logging on as the Ranger KMS admin user leads to a different set of screens.

## Role Separation

By default, Ranger admin uses a different admin user (`keyadmin`) to manage access policies and keys for Ranger KMS.

The person accessing Ranger KMS via the `keyadmin` user should be a different person than the administrator who works with regular Ranger access policies. This approach separates encryption work (encryption keys and policies) from Hadoop cluster management and access policy management.

### 6.1.5.1. Accessing the Ranger KMS Web UI

To access Ranger KMS, log in as user `keyadmin`, password `keyadmin`.



#### Important

Change the password after you log in.

After logging in, you will see the Service Manager screen. To view or edit Ranger KMS repository properties, click on the edit button next to the repository name:

The screenshot shows the Ranger Service Manager interface. At the top, there is a navigation bar with tabs for 'Ranger', 'Access Manager', and 'Encryption'. On the far right of the bar, it shows the user is logged in as 'keyadmin'. Below the bar, there is a breadcrumb trail labeled 'Service Manager'. The main area is titled 'Service Manager' and contains a list of repositories. One repository is named 'cl1\_kms'. To the right of this repository name, there is an edit icon (pencil symbol). The entire interface has a clean, modern design with a light gray background and white text.

You will see a list of service details and config properties for the repository:

The screenshot shows the Ranger Web UI interface for creating a new service. At the top, there are tabs for 'Ranger', 'Access Manager', and 'Encryption'. The 'Encryption' tab is selected. Below the tabs, a navigation bar includes 'Service Manager' and 'Edit Service'. The main area is titled 'Create Service'.

**Service Details:**

- Service Name \*: d1\_kms
- Description: kms repo
- Active Status: Enabled (radio button selected)

**Config Properties:**

- KMS URL \*: kms://http@vp-os-rh6-my-sec-150
- Username \*: keyadmin@EXAMPLE.COM
- Password \*: \*\*\*\*

Add New Configurations:

Name	Value	X
		X

**Buttons:**

- + (Add new configuration)
- Test Connection (button)
- Save (green button)
- Cancel (black button)
- Delete (red button)

### 6.1.5.2. Listing and Creating Keys

To list existing keys:

1. Choose the Encryption tab at the top of the Ranger Web UI screen.
2. Select the Ranger KMS service from the drop-down list.

The screenshot shows the Ranger Key Management interface under the KMS tab. A search bar at the top has 'cl1\_kms' selected. Below it is a table listing six keys:

Key Name	Cipher	Version	Attributes	Length	Created Date	Action
sensitivefolder	AES/CTR/NoPadding	1	key.acl.name → SensitiveFolder	128	08/06/2015 01:30:44 PM	<input type="checkbox"/> <input type="button"/>
test	AES/CTR/NoPadding	1	key.acl.name → test	128	08/13/2015 01:49:35 PM	<input type="checkbox"/> <input type="button"/>
testkeyfromcli	AES/CTR/NoPadding	1	key.acl.name → testkeyfromcli	128	07/24/2015 06:04:36 PM	<input type="checkbox"/> <input type="button"/>
testkeyfromui	AES/CTR/NoPadding	1	key.acl.name → testkeyfromui	128	07/24/2015 06:04:16 PM	<input type="checkbox"/> <input type="button"/>
testkeygmi	AES/CTR/NoPadding	1	key.acl.name → testkeyGMI	128	08/06/2015 02:02:40 PM	<input type="checkbox"/> <input type="button"/>
tk1	AES/CTR/NoPadding	1	key.acl.name → tk1	128	08/25/2015 12:22:23 PM	<input type="checkbox"/> <input type="button"/>

To create a new key:

1. Click on "Add New Key".
2. Add a valid key name.
3. Select the cipher name. Ranger supports AES/CTR/NoPadding as the cipher suite.
4. Specify the key length, 128 or 256 bits.
5. Add other attributes as needed, and then save the key.

The screenshot shows the Ranger Key Create interface under the KMS tab. The path 'cl1\_kms > Key Create' is visible. The 'Key Detail' section contains the following fields:

- Key Name \*:
- Cipher:
- Length:
- Description:
- Attributes: A table with columns 'Name' and 'Value'. It contains one row with empty fields and a delete button (x).

At the bottom are 'Save' and 'Cancel' buttons.

### 6.1.5.3. Rolling Over an Existing Key

Rolling over (or "rotating") a key retains the same key name, but the key will have a different version. This operation re-encrypts existing file keys, but does not re-encrypt the actual file. Keys can be rolled over at any time.


After a key is rotated in Ranger KMS, new files will have the file key encrypted by the new master key for the encryption zone.

To rotate a key, click the edit button next to the key name in the list of keys, as shown in the following screenshot:

Policy ID	Policy Name	Status	Audit Logging	Groups	Users	Action
1	cl1_kms-1-20150724233747	Enabled	Enabled	public	keyadmin	

Edit the key information, and then press Save.

When asked to confirm the rollover, click "OK":



### 6.1.5.4. Deleting a Key



#### Warning

Deleting a key associated with an existing encryption zone will result in data loss.

To delete an existing key:

1. Choose the Encryption tab at the top of the Ranger Web UI screen.
2. Select Ranger KMS service from the drop-down list.
3. Click on the delete symbol next to the key.
4. You will see a confirmation popup window; confirm or cancel.

## 6.1.6. Ranger KMS Properties

This chapter describes configuration properties for the Ranger Key Management Service (KMS).

**Table 6.1. Properties in Advanced dbks-site Menu (dbks-site.xml)**

Property Name	Default Value	Description
ranger.ks.masterkey.credential.alias	ranger.ks.masterkey.password	Credential alias used for masterkey.
ranger.ks.jpa.jdbc.user	rangerkms	Database username used for operation.
ranger.ks.jpa.jdbc.url	jdbc:log4jdbc:mysql://localhost:3306/rangerkms	JDBC connection URL for database.
ranger.ks.jpa.jdbc.password	_ (default it's encrypted)	Database user's password.
ranger.ks.jpa.jdbc.driver	net.sf.log4jdbc.DriverSpy	Driver used for database.
ranger.ks.jpa.jdbc.dialect	org.eclipse.persistence.platform.database.MySQLPlatform	Dialect used for database.
ranger.ks.jpa.jdbc.credential.provider.path	/etc/ranger/kms/rangerkms.jceks	Credential provider path.
ranger.ks.jpa.jdbc.credential.alias	ranger.ks.jdbc.password	Credential alias used for password.
ranger.ks.jdbc.sqlconnectorjar	/usr/share/java/mysql-connector-java.jar	Driver jar used for database.
ranger.db.encrypt.key.password	_ (Default; it's encrypted)	Password used for encrypting the Master Key.
hadoop.kms.blacklist.DECRYPT_EEK	hdfs	Blacklist for decrypt EncryptedKey CryptoExtension operations. This can have multiple user IDs in a comma separated list. e.g stormuser,yarn,hdfs.

**Table 6.2. Properties in Advanced kms-env**

Property Name	Default Value	Description
Kms User	kms	Ranger KMS process will be started using this user.
Kms Group	kms	Ranger KMS process will be started using this group.
LD library path		LD library path (basically used when the db flavor is SQLA). Example: /opt/sqlanywhere17/lib64
kms_port	9292	Port used by Ranger KMS.
kms_log_dir	/var/log/ranger/kms	Directory where the Ranger KMS log will be generated.

**Table 6.3. Properties in Advanced kms-properties (install.properties)**

Property Name	Default Value	Description
db_user	rangerkms	Database username used for the operation.
db_root_user		Database root username. Default is blank. Specify the root user.
db_root_password		Database root user's password. Default is blank. Specify the root user password.

Property Name	Default Value	Description
db_password		Database user's password for the operation. Default is blank. Specify the Ranger KMS database password.
db_name	rangerkms	Database name for Ranger KMS.
db_host	<FQDN of instance where the Ranger KMS is installed>	Hostname where the database is installed. <b>Note:</b> Check the hostname for DB and change it accordingly.
SQL_CONNECTOR_JAR	/usr/share/java/mysql-connector.jar	Location of DB client library.
REPOSITORY_CONFIG_USERNAME	keyadmin	User used in default repo for Ranger KMS.
REPOSITORY_CONFIG_PASSWORD	keyadmin	Password for user used in default repo for Ranger KMS.
KMS_MASTER_KEY_PASSWD		Password used for encrypting the Master Key. Default value is blank. Set the master key to any string.
DB_FLAVOR	MYSQL	Database flavor used for Ranger KMS. Supported values: MYSQL, SQLA, ORACLE, POSTGRES, MSSQL

**Table 6.4. Properties in Advanced kms-site (kms-site.xml)**

Property Name	Default Value	Description
hadoop.security.keystore.JavaKeyStoreProvider.password	none	If using the JavaKeyStoreProvide, the password for the keystore file.
hadoop.kms.security.authorization.manager	org.apache.ranger.authorization.kms.authorizer.RangerKmsAuthorizer	Ranger KMS security authorizer.
hadoop.kms.key.provider.uri	dbks://http@localhost:9292/kms	URI of the backing KeyProvider for the KMS.
hadoop.kms.current.key.cache.timeout.ms	30000	Expiry time for the KMS current key cache, in milliseconds. This affects getCurrentKey operations.
hadoop.kms.cache.timeout.ms	600000	Expiry time for the KMS key version and key metadata cache, in milliseconds. This affects getKeyVersion and getMetadata.
hadoop.kms.cache.enable	true	Whether the KMS will act as a cache for the backing KeyProvider. When the cache is enabled, operations like getKeyVersion, getMetadata, and getCurrentKey will sometimes return cached data without consulting the backing KeyProvider. Cached values are flushed when keys are deleted or modified.  <b>Note:</b> This setting is beneficial if Single KMS and single mode are used. If this is set to true when multiple KMSs are used, or when the key operations are from different modes (Ranger UI, CURL, or hadoop command), it might cause inconsistency.
hadoop.kms.authentication.type	simple	Authentication type for the Ranger KMS. Can be either "simple" or "kerberos".

Property Name	Default Value	Description
hadoop.kms.authentication.signer.secret.provider.zookeeper.path	/hadoop-kms/hadoop-auth-signature-secret	The ZooKeeper ZNode path where the Ranger KMS instances will store and retrieve the secret from.
hadoop.kms.authentication.signer.secret.provider.zookeeper.kerberos.principal	kms/#HOSTNAME#	The Kerberos service principal used to connect to ZooKeeper
hadoop.kms.authentication.signer.secret.provider.zookeeper.kerberos.keytab	/etc/hadoop/conf/kms.keytab	The absolute path for the Kerberos keytab with the credentials to connect to ZooKeeper.
hadoop.kms.authentication.signer.secret.provider.zookeeper.connection.string	#HOSTNAME#:#PORT#,...	The ZooKeeper connection string, a list of hostnames and port comma separated. For example: <FQDN for first instance>:2181,<FQDN for second instance>:2181
hadoop.kms.authentication.signer.secret.provider.zookeeper.auth.type	kerberos	ZooKeeper authentication type: 'none' or 'sasl' (Kerberos)
hadoop.kms.authentication.signer.secret.provider	random	Indicates how the secret to sign authentication cookies will be stored. Options are 'random' (default), 'string', and 'zookeeper'. If you have multiple Ranger KMS instances, specify 'zookeeper'.
hadoop.kms.authentication.kerberos.principal	HTTP/localhost	The Kerberos principal to use for the HTTP endpoint. The principal must start with 'HTTP/' as per the Kerberos HTTP SPNEGO specification.
hadoop.kms.authentication.kerberos.name.rules	DEFAULT	Rules used to resolve Kerberos principal names.
hadoop.kms.authentication.kerberos.keytab	\${user.home}/kms.keytab	Path to the keytab with credentials for the configured Kerberos principal.
hadoop.kms.audit.aggregation.window.ms	10000	Specified in ms. Duplicate audit log events within this aggregation window are quashed to reduce log traffic. A single message for aggregated events is printed at the end of the window, along with a count of the number of aggregated events.

**Table 6.5. Properties in Advanced ranger-kms-audit (ranger-kms-audit.xml)**

Property Name	Default Value	Description
Audit provider summary enabled		Enable audit provider summary.
xasecure.audit.is.enabled	true	Enable audit.
xasecure.audit.destination.solr.zookeepers	none	Specify solr zookeeper string.
xasecure.audit.destination.solr.urls	{ {ranger_audit_solr_urls} }	Specify solr URL. <b>Note:</b> In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.solr.batch.filespool.dir	/var/log/ranger/kms/audit/solr/spool	Directory for solr audit spool.
Audit to SOLR		Enable audit to solr.
xasecure.audit.destination.hdfs.dir	hdfs://NAMENODE_HOST:8020/ranger/audit	HDFS directory to write audit.

Property Name	Default Value	Description
		<b>Note:</b> Make sure the service user has required permissions.
xasecure.audit.destination.hdfs.batch.filespool.dir	/var/log/ranger/kms/audit/hdfs/spool	Directory for HDFS audit spool.
Audit to HDFS		Enable hdfs audit.
xasecure.audit.destination.db.user	{ {xa_audit_db_user} }	xa audit db user  <b>Note:</b> In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.db.password	encrypted (it's in encrypted format)	xa audit db user password  <b>Note:</b> In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.db.jdbc.url	{ {audit_jdbc_url} }	Database JDBC URL for xa audit.  <b>Note:</b> In Ambari the value for this is populated from the Ranger Admin by default.
xasecure.audit.destination.db.jdbc.driver	{ {jdbc_driver} }	Database JDBC driver.  <b>Note:</b> In Ambari this value is populated from the Ranger Admin by default.
xasecure.audit.destination.db.batch.filespool.dir	/var/log/ranger/kms/audit/db/spool	Directory for database audit spool.
Audit to DB		Enable audit to database.
xasecure.audit.credential.provider.file	jceks://file{ {credential_file} }	Credential provider file.

**Table 6.6. Properties in Advanced ranger-kms-policymgr-ssl**

Property Name	Default Value	Description
xasecure.policymgr.clientssl.truststore.password	changeit	Password for the truststore.
xasecure.policymgr.clientssl.truststore	/usr/hdp/current/ranger-kms/conf/ranger-plugin-truststore.jks	jks file for truststore
xasecure.policymgr.clientssl.keystore.password	myKeyFilePassword	Password for keystore.
xasecure.policymgr.clientssl.keystore.credential.file	jceks://file{ {credential_file} }	Java keystore credential file.
xasecure.policymgr.clientssl.keystore	/usr/hdp/current/ranger-kms/conf/ranger-plugin-keystore.jks	Java keystore file.
xasecure.policymgr.clientssl.truststore.credential.file	jceks://file{ {credential_file} }	Java truststore file.

**Table 6.7. Properties in Advanced ranger-kms-security**

Property Name	Default Value	Description
ranger.plugin.kms.service.name	<default name for Ranger KMS Repo>	Name of the Ranger service containing policies for the KMS instance. <b>Note:</b> In Ambari the default value is <clusterName>_kms.
ranger.plugin.kms.policy.source.impl	org.apache.ranger.admin.client.RangerAdminRESTClient	Class to retrieve policies from the source.
ranger.plugin.kms.policy.rest.url	{ {policymgr_mgr_url} }	URL for Ranger Admin.

Property Name	Default Value	Description
ranger.plugin.kms.policy.rest.ssl.config.file	/etc/ranger/kms/conf/ranger-policymgr-ssl.xml	Path to the file containing SSL details for contacting the Ranger Admin.
ranger.plugin.kms.policy.pollIntervalMs	30000	Time interval to poll for changes in policies.
ranger.plugin.kms.policy.cache.dir	/etc/ranger/{{repo_name}}/policycache	Directory where Ranger policies are cached after successful retrieval from the source.

## 6.1.7. Troubleshooting Ranger KMS

**Table 6.8. Troubleshooting Suggestions**

Issue	Action
Not able to install Ranger KMS	Check to see if ranger admin is running, verify DB.
Not able to start Ranger KMS	Check the Ranger KMS log. If there is a message about illegal key size, make sure unlimited strength JCE is available.
Hadoop key commands fail	Make sure Ranger KMS client properties are updated in hdfs config.
Not able to create keys from Ranger UI	Make sure that the keyadmin user (or any custom user) configured in the KMS repository is added to proxy properties in the custom kms-site.xml file.

## 6.2. HDFS "Data at Rest" Encryption

Encryption is a form of data security that is required in industries such as healthcare and the payment card industry. Hadoop provides several ways to encrypt stored data.

- The lowest level of encryption is volume encryption, which protects data after physical theft or accidental loss of a disk volume. The entire volume is encrypted; this approach does not support finer-grained encryption of specific files or directories. In addition, volume encryption does not protect against viruses or other attacks that occur while a system is running.
- Application level encryption (encryption within an application running on top of Hadoop) supports a higher level of granularity and prevents "rogue admin" access, but adds a layer of complexity to the application architecture.
- A third approach, HDFS data at rest encryption, encrypts selected files and directories stored ("at rest") in HDFS. This approach uses specially designated HDFS directories known as "encryption zones."

This chapter focuses on the third approach, HDFS data at rest encryption. The chapter is intended as an introductory quick start to HDFS data at rest encryption. Content will be updated regularly.

### 6.2.1. HDFS Encryption Overview

HDFS data at rest encryption implements end-to-end encryption of data read from and written to HDFS. End-to-end encryption means that data is encrypted and decrypted only by the client. HDFS does not have access to unencrypted data or keys.

HDFS encryption involves several elements:


- **Encryption key:** A new level of permission-based access protection, in addition to standard HDFS permissions.
- **HDFS encryption zone:** A special HDFS directory within which all data is encrypted upon write, and decrypted upon read.
- Each encryption zone is associated with an encryption key that is specified when the zone is created.
- Each file within an encryption zone has a unique encryption key, called the "data encryption key" (DEK).
- HDFS does not have access to DEKs. HDFS DataNodes only see a stream of encrypted bytes. HDFS stores "encrypted data encryption keys" (EDEKs) as part of the file's metadata on the NameNode.
- Clients decrypt an EDEK and use the associated DEK to encrypt and decrypt data during write and read operations.
- **Ranger Key Management Service (Ranger KMS):** An open source key management service based on Hadoop's KeyProvider API.

For HDFS encryption, the Ranger KMS has three basic responsibilities:

- Provide access to stored encryption zone keys.
- Generate and manage encryption zone keys, and create encrypted data keys to be stored in Hadoop.
- Audit all access events in Ranger KMS.

**Note:** This chapter is intended for security administrators who are interested in configuring and using HDFS encryption. For more information about Ranger KMS, see the [Ranger KMS Administration Guide](#).

**Figure 6.1. HDFS Encryption Components**



### Role Separation

Access to the key encryption/decryption process is typically restricted to end users. This means that encrypted keys can be safely stored and handled by HDFS, because the HDFS admin user does not have access to them.

This role separation requires two types of HDFS administrator accounts:

- HDFS service user: the system-level account associated with HDFS (`hdfs` by default).
- HDFS admin user: an account in the `hdfs` supergroup, which is used by HDFS administrators to configure and manage HDFS.



### Important

For clear segregation of duties, we recommend that you restrict use of the `hdfs` account to system/interprocess use. Do not provide its password to physical users. A (human) user who administers HDFS should only access HDFS through an admin user account created specifically for that purpose. For more information about creating an HDFS admin user, see [Creating an HDFS Admin User](#).

Other services may require a separate admin account for clusters with HDFS encryption zones. For service-specific information, see [Configuring HDP Services for HDFS Encryption](#).

## 6.2.2. Configuring and Starting the Ranger Key Management Service (Ranger KMS)

In a typical environment, a security administrator will set up the Ranger Key Management Service. For information about installing and configuring the Ranger KMS, see the [Ranger KMS Administration Guide](#).

## 6.2.3. Configuring and Using HDFS Data at Rest Encryption

After the Ranger KMS has been set up and the NameNode and HDFS clients have been configured, an HDFS administrator can use the `hadoop key` and `hdfs crypto` command-line tools to create encryption keys and set up new encryption zones.

The overall workflow is as follows:

1. Create an HDFS encryption zone key that will be used to encrypt the file-level data encryption key for every file in the encryption zone. This key is stored and managed by Ranger KMS.
2. Create a new HDFS folder. Specify required permissions, owner, and group for the folder.
3. Using the new encryption zone key, designate the folder as an encryption zone.
4. Configure client access. The user associated with the client application needs sufficient permission to access encrypted data. In an encryption zone, the user needs file/directory access (through Posix permissions or Ranger access control), as well as access for certain key operations. To set up ACLs for key-related operations, see the [Ranger KMS Administration Guide](#).

After permissions are set, Java API clients and HDFS applications with sufficient HDFS and Ranger KMS access privileges can write and read to/from files in the encryption zone.

### 6.2.3.1. Prepare the Environment

HDP supports hardware acceleration with Advanced Encryption Standard New Instructions (AES-NI). Compared with the software implementation of AES, hardware acceleration offers an order of magnitude faster encryption/decryption.

To use AES-NI optimization you need CPU and library support, described in the following subsections.

#### 6.2.3.1.1. CPU Support for AES-NI optimization

AES-NI optimization requires an extended CPU instruction set for AES hardware acceleration.

There are several ways to check for this; for example:

```
$ cat /proc/cpuinfo | grep aes
```

Look for output with flags and 'aes'.

#### 6.2.3.1.2. Library Support for AES-NI optimization

You will need a version of the `libcrypto.so` library that supports hardware acceleration, such as OpenSSL 1.0.1e. (Many OS versions have an older version of the library that does not support AES-NI.)

A version of the `libcrypto.so` library with AES-NI support must be installed on HDFS cluster nodes and MapReduce client hosts – that is, any host from which you issue HDFS or MapReduce requests. The following instructions describe how to install and configure the `libcrypto.so` library.

### RHEL/CentOS 6.5 or later

On HDP cluster nodes, the installed version of `libcrypto.so` supports AES-NI, but you will need to make sure that the symbolic link exists:

```
$ sudo ln -s /usr/lib64/libcrypto.so.1.0.0.1e /usr/lib64/libcrypto.so
```

On MapReduce client hosts, install the `openssl-devel` package:

```
$ sudo yum install openssl-devel
```

### 6.2.3.1.3. Verifying AES-NI Support

To verify that a client host is ready to use the AES-NI instruction set optimization for HDFS encryption, use the following command:

```
hadoop checknative
```

You should see a response similar to the following:

```
15/08/12 13:48:39 INFO bzip2.Bzip2Factory: Successfully loaded & initialized native-bzip2 library system-native
14/12/12 13:48:39 INFO zlib.ZlibFactory: Successfully loaded & initialized native-zlib library
Native library checking:
hadoop: true /usr/lib/hadoop/lib/native/libhadoop.so.1.0.0
zlib: true /lib64/libz.so.1
snappy: true /usr/lib64/libsnappy.so.1
lz4: true revision:99
bzip2: true /lib64/libbz2.so.1
openssl: true /usr/lib64/libcrypto.so
```

If you see `true` in the `openssl` row, Hadoop has detected the right version of `libcrypto.so` and optimization will work.

If you see `false` in this row, you do not have the correct version.

### 6.2.3.2. Create an Encryption Key

Create a "master" encryption key for the new encryption zone. Each key will be specific to an encryption zone.

Ranger supports AES/CTR/NoPadding as the cipher suite. (The associated property is listed under HDFS -> Configs in the Advanced `hdfs-site` list.)

Key size can be 128 or 256 bits.

*Recommendation:* create a new superuser for key management. In the following examples, superuser `enrcr` creates the key. This separates the data access role from the encryption role, strengthening security.

#### Create an Encryption Key using Ranger KMS (Recommended)

In the Ranger Web UI screen:

1. Choose the Encryption tab at the top of the screen.

2. Select the KMS service from the drop-down list.

The screenshot shows the Ranger interface with the 'Encryption' tab selected. Under the 'Key Management' section, there is a dropdown menu labeled 'Select Service :'. The dropdown contains two entries: 'cl1\_kms' (which is highlighted) and 'dt1\_kms'. Below the dropdown is a search bar with the placeholder 'Search for your key'. To the right of the search bar is a green 'Add New Key' button. A table below lists existing keys with columns for Key Name, Cipher, Version, Attributes, Length, Created Date, and Action (with edit and delete icons).

Key Name	Cipher	Version	Attributes	Length	Created Date	Action
sensitivefolder	AES/CTR/NoPadding	1	key.acl.name → SensitiveFolder	128	08/06/2015 01:30:44 PM	
test	AES/CTR/NoPadding	1	key.acl.name → test	128	08/13/2015 01:49:35 PM	
testkeyfromcli	AES/CTR/NoPadding	1	key.acl.name → testkeyfromcli	128	07/24/2015 06:04:36 PM	
testkeyfromui	AES/CTR/NoPadding	1	key.acl.name → testkeyfromui	128	07/24/2015 06:04:16 PM	
testkeygmi	AES/CTR/NoPadding	1	key.acl.name → testkeyGMI	128	08/06/2015 02:02:40 PM	
tk1	AES/CTR/NoPadding	1	key.acl.name → tk1	128	08/25/2015 12:22:23 PM	

To create a new key:

1. Click on "Add New Key":
2. Add a valid key name.
3. Select the cipher name. Ranger supports AES/CTR/NoPadding as the cipher suite.
4. Specify the key length, 128 or 256 bits.
5. Add other attributes as needed, and then save the key.

The screenshot shows the 'Key Detail' form for creating a new key. The path 'KMS > cl1\_kms > Key Create' is visible at the top. The form includes fields for 'Key Name \*' (with a required asterisk), 'Cipher' (set to 'AES/CTR/NoPadding'), 'Length' (set to '128'), 'Description' (a text area), and an 'Attributes' table. The 'Attributes' table has columns for 'Name' and 'Value'. A red 'x' icon is shown in the 'Value' column of the first row, indicating it can be deleted. At the bottom of the form are 'Save' and 'Cancel' buttons.

Name	Value

For information about rolling over and deleting keys, see [Using the Ranger Key Management Service](#).



## Warning

Do not delete an encryption key while it is in use for an encryption zone. This will result in loss of access to data in that zone.

### Create an Encryption Key using the CLI

The full syntax of the hadoop key create command is as follows:

```
[create <keyname> [-cipher <cipher>]
[-size <size>]
[-description <description>]
[-attr <attribute=value>]
[-provider <provider>]
[-help]]
```

Example:

```
su - encr

hadoop key create <key_name> [-size <number-of-bits>]
```

The default key size is 128 bits. The optional `-size` parameter supports 256-bit keys, and requires the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all hosts in the cluster. For installation information, see [Installing the JCE](#).

Example:

```
su - encr

hadoop key create key1
```

To verify creation of the key, list the metadata associated with the current user:

```
hadoop key list -metadata
```

For information about rolling over and deleting keys, see [Using the Ranger Key Management Service](#).



## Warning

Do not delete an encryption key while it is in use for an encryption zone. This will result in loss of access to data in that zone.

### 6.2.3.3. Create an Encryption Zone

Each encryption zone must be defined using an empty directory and an existing encryption key. An encryption zone cannot be created on top of a directory that already contains data.

*Recommendation:* use one unique key for each encryption zone.

Use the `crypto createZone` command to create a new encryption zone. The syntax is:

```
-createZone -keyName <keyName> -path <path>
```

where:

- `-keyName`: specifies the name of the key to use for the encryption zone.
- `-path` specifies the path of the encryption zone to be created. It must be an empty directory.



## Note

The `hdfs` service account can create zones, but cannot write data unless the account has sufficient permission.

*Recommendation:* Define a separate user account for the HDFS administrator, and do not provide access to keys for this user in Ranger KMS.

Steps:

1. As HDFS administrator, create a new empty directory. For example:

```
hdfs dfs -mkdir /zone_encr
```

2. Using the encryption key, make the directory an encryption zone. For example:

```
hdfs crypto -createZone -keyName key1 -path /zone_encr
```

When finished, the NameNode will recognize the folder as an HDFS encryption zone.

3. To verify creation of the new encryption zone, run the `crypto -listZones` command as an HDFS administrator:

```
-listZones
```

You should see the encryption zone and its key. For example:

```
$ hdfs crypto -listZones
/zone-encr key1
```



## Note

The following property (in the `hdfs-default.xml` file) causes `listZone` requests to be batched. This improves NameNode performance. The property specifies the maximum number of zones that will be returned in a batch.

```
dfs.namenode.list.encryption.zones.num.responses
```

The default is 100.

To remove an encryption zone, delete the root directory of the zone. For example:

```
hdfs dfs -rm -R /zone_encr
```

#### 6.2.3.4. Copy Files from/to an Encryption Zone

To copy existing files into an encryption zone, use a tool like `distcp`.

*Note:* for separation of administrative roles, do not use the `hdfs` user to create encryption zones. Instead, designate another administrative account for creating encryption keys and zones. See [Creating an HDFS Admin User](#) for more information.

The files will be encrypted using a file-level key generated by the Ranger Key Management Service.

##### DistCp Considerations

`DistCp` is commonly used to replicate data between clusters for backup and disaster recovery purposes. This operation is typically performed by the cluster administrator, via an HDFS superuser account.

To retain this workflow when using HDFS encryption, a new virtual path prefix has been introduced, `/ .reserved/raw/`. This virtual path gives super users direct access to the underlying encrypted block data in the file system, allowing super users to `distcp` data without requiring access to encryption keys. This also avoids the overhead of decrypting and re-encrypting data. The source and destination data will be byte-for-byte identical, which would not be true if the data were re-encrypted with a new EDEK.



##### Warning

When using `/ .reserved/raw/` to `distcp` encrypted data, make sure you preserve extended attributes with the `-px` flag. This is necessary because encrypted attributes such as the EDEK are exposed through extended attributes; they *must* be preserved to be able to decrypt the file. For example:

```
sudo -u encr hadoop distcp -px hdfs:/cluster1-namenode:50070/.reserved/raw/apps/enczone hdfs:/cluster2-namenode:50070/.reserved/raw/apps/enczone
```

This means that if the `distcp` operation is initiated at or above the encryption zone root, it will automatically create a new encryption zone at the destination (if one does not already exist).

*Recommendation:* To avoid potential mishaps, first create identical encryption zones on the destination cluster.

##### Copying between encrypted and unencrypted locations

By default, `distcp` compares file system checksums to verify that data was successfully copied to the destination.

When copying between an unencrypted and encrypted location, file system checksums will not match because the underlying block data is different. In this case, specify the `-skipcrccheck` and `-update` flags to avoid verifying checksums.

### 6.2.3.5. Read and Write Files from/to an Encryption Zone

Clients and HDFS applications with sufficient HDFS and Ranger KMS permissions can read and write files from/to an encryption zone.

Overview of the client write process:

1. The client writes to the encryption zone.
2. The NameNode checks to make sure that the client has sufficient write access permissions. If so, the NameNode asks Ranger KMS to create a file-level key, encrypted with the encryption zone master key.
3. The Namenode stores the file-level encrypted data encryption key (EDEK) generated by Ranger KMS as part of the file's metadata, and returns the EDEK to the client.
4. The client asks Ranger KMS to decode the EDEK (to DEK), and uses the DEK to write encrypted data. Ranger KMS checks for permissions for the user before decrypting EDEK and producing the DEK for the client.

Overview of the client read process:

1. The client issues a read request for a file in an encryption zone.
2. The NameNode checks to make sure that the client has sufficient read access permissions. If so, the NameNode returns the file's EDEK and the encryption zone key version that was used to encrypt the EDEK.
3. The client asks Ranger KMS to decrypt the EDEK. Ranger KMS checks for permissions to decrypt EDEK for the end user.
4. Ranger KMS decrypts and returns the (unencrypted) data encryption key (DEK).
5. The client uses the DEK to decrypt and read the file.

The preceding steps take place through internal interactions between the DFSClient, the NameNode, and Ranger KMS.

In the following example, the `/zone_encr` directory is an encrypted zone in HDFS.

To verify this, use the `crypto -listZones` command (as an HDFS administrator). This command lists the root path and the zone key for the encryption zone. For example:

```
hdfs crypto -listZones
/zone_encr key1
```

Additionally, the `/zone_encr` directory has been set up for read/write access by the `hive` user:

```
hdfs dfs -ls /
..
drwxr-x--- - hive hive 0 2015-01-11 23:12 /zone_encr
```

The `hive` user can, therefore, write data to the directory.

The following examples use the `copyFromLocal` command to move a local file into HDFS.

```
[hive@blue ~]# hdfs dfs -copyFromLocal web.log /zone_encr
[hive@blue ~]# hdfs dfs -ls /zone_encr
Found 1 items
-rw-r--r-- 1 hive hive 1310 2015-01-11 23:28 /zone_encr/web.log
```

The `hive` user can read data from the directory, and can verify that the file loaded into HDFS is readable in its unencrypted form.

```
[hive@blue ~]# hdfs dfs -copyToLocal /zone_encr/web.log read.log
[hive@blue ~]# diff web.log read.log
```



### Note

For more information about accessing encrypted files from Hive and other components, see [Configuring HDP Services for HDFS Encryption](#).

Users without access to KMS keys will be able to see file names (via the `-ls` command), but they will not be able to write data or read from the encrypted zone. For example, the `hdfs` user lacks sufficient permissions, and cannot access the data in `/zone_encr`:

```
[hdfs@blue ~]# hdfs dfs -copyFromLocal install.log /zone_encr
copyFromLocal: Permission denied: user=hdfs, access=EXECUTE, inode="/
zone_encr":hive:hive:drwxr-x---
```

```
[hdfs@blue ~]# hdfs dfs -copyToLocal /zone_encr/web.log read.log
copyToLocal: Permission denied: user=hdfs, access=EXECUTE, inode="/
zone_encr":hive:hive:drwxr-x---
```

## 6.2.3.6. Delete Files from an Encryption Zone with Trash Enabled

The trash location for encrypted HDFS files is different than the default trash location for unencrypted files (`/user/$USER/.Trash/Current/OriginalPathToDeleteFile`).

When trash is enabled and an encrypted file is deleted, the file is moved to the `.Trash` subdirectory under the root of the encryption zone as `/EncryptionZoneRoot/.Trash/$USER/Current/OriginalPathToDeleteFile`. The file remains encrypted without additional decryption/re-encryption overhead during the move to trash. The move operation preserves the name of the user who executes the deletion, and the full path of the deleted file.

For example, if user `hdp-admin` deletes file `/zone_name/file1` using the following command:

```
hdfs dfs -rm /zone_name/file1
```

`file1` will remain encrypted, and it will be moved to the following location within the encryption zone:

```
/zone_name/.Trash/hdp-admin/Current/zone_name/file1
```

A trash checkpoint will be created for the `.Trash` subdirectory in each encryption zone. Checkpoints will be deleted/created according to the value of `fs.trash.checkpoint.interval` (number of minutes between trash checkpoints). A checkpoint for this example would be:

```
/zone_name/.Trash/hdp-admin/<CheckPointTimeStamp>/zone_name/
file1
```

For additional information, see Apache [HDFS-8831](#).

## 6.2.4. Configuring HDP Services for HDFS Encryption

HDFS data at rest encryption is supported on the following HDP components:

- Hive
- Hive on Tez
- HBase
- Sqoop
- YARN
- MapReduce
- Oozie
- WebHDFS

HDFS data at rest encryption is not supported on the following components:

- Spark
- HDP Search
- Storm
- Accumulo
- Falcon

The remainder of this section describes scenarios and access considerations for accessing HDFS-encrypted files from supporting HDP components.

### 6.2.4.1. Hive

**Recommendation:** Store Hive data in an HDFS path called /apps/hive.

#### 6.2.4.1.1. Configuring Hive Tables for HDFS Encryption

Before enabling encryption zones, decide whether to store your Hive tables across one zone or multiple encryption zones.

##### Single Encryption Zone

To configure a single encryption zone for your entire Hive warehouse:

1. Rename /apps/hive to /apps/hive-old

2. Create an encryption zone at /apps/hive
3. distcp all of the data from /apps/hive-old to /apps/hive.

To configure the Hive scratch directory (`hive.exec.scratchdir`) so that it resides inside the encryption zone:

1. Set the directory to /apps/hive/tmp.
2. Make sure that the permissions for /apps/hive/tmp are set to 1777.

### Multiple Encryption Zones

To access encrypted databases and tables with different encryption keys, configure multiple encryption zones.

For example, to configure two encrypted tables, `ez1.db` and `ez2.db`, in two different encryption zones:

1. Create two new encryption zones, /apps/hive/warehouse/ez1.db and /apps/hive/warehouse/ez2.db.
2. Load data into Hive tables `ez1.db` and `ez2.db` as usual, using LOAD statements. (For additional considerations, see "Loading Data into an Encrypted Table.")

#### 6.2.4.1.2. Loading Data into an Encrypted Table

By design, HDFS-encrypted files cannot be moved or loaded from one encryption zone into another encryption zone, or from an encryption zone into an unencrypted directory. Encrypted files can only be copied.

Within an encryption zone, files can be copied, moved, loaded, and renamed.

Recommendations:

- When loading unencrypted data into encrypted tables (e.g., `LOAD DATA INPATH`), we recommend placing the source data (to be encrypted) into a landing zone within the destination encryption zone.
- An attempt to load data from one encryption zone into another will result in a copy operation. Distcp will be used to speed up the process if the size of the files being copied is higher than the value specified by the `hive.exec.copyfile.maxsize` property. The default limit is 32 MB.

Here are two approaches for loading unencrypted data into an encrypted table:

- To load unencrypted data into an encrypted table, use the `LOAD DATA . . .` statement.  
If the source data does not reside inside the encryption zone, the `LOAD` statement will result in a copy. If your data is already inside HDFS, though, you can use `distcp` to speed up the copying process.
- If the data is already inside a Hive table, create a new table with a `LOCATION` inside an encryption zone, as follows:

```
CREATE TABLE encrypted_table [STORED AS] LOCATION ... AS SELECT *
FROM <unencrypted_table>
```



### Note

The location specified in the `CREATE TABLE` statement must be within an encryption zone. If you create a table that points `LOCATION` to an unencrypted directory, your data will not be encrypted. You must copy your data to an encryption zone, and then point `LOCATION` to that encryption zone.

If your source data is already encrypted, use the `CREATE TABLE` statement. Point `LOCATION` to the encrypted source directory where your data resides:

```
CREATE TABLE encrypted_table [STORED AS] LOCATION ... AS SELECT *
FROM <encrypted_source_directory>
```

This is the fastest way to create encrypted tables.

#### 6.2.4.1.3. Encrypting Other Hive Directories

- **LOCALSCRATCHDIR** : The MapJoin optimization in Hive writes HDFS tables to a local directory and then uploads them to distributed cache. To enable encryption, either disable MapJoin (set `hive.auto.convert.join` to `false`) or encrypt the local Hive Scratch directory (`hive.exec.local.scratchdir`). **Performance note**: disabling MapJoin will result in slower join performance.
- **DOWNLOADED\_RESOURCES\_DIR**: Jars that are added to a user session and stored in HDFS are downloaded to `hive.downloaded.resources.dir`. If you want these Jar files to be encrypted, configure `hive.downloaded.resources.dir` to be part of an encryption zone. This directory needs to be accessible to the HiveServer2.
- **NodeManager Local Directory List**: Hive stores Jars and MapJoin files in the distributed cache, so if you'd like to use MapJoin or encrypt Jars and other resource files, the YARN configuration property NodeManager Local Directory List (`yarn.nodemanager.local-dirs`) must be configured to a set of encrypted local directories on all nodes.

Alternatively, to disable MapJoin, set `hive.auto.convert.join` to `false`.

#### 6.2.4.1.4. Additional Changes in Behavior with HDFS-Encrypted Tables

- Users reading data from read-only encrypted tables must have access to a temp directory that is encrypted with at least as strong encryption as the table.
- By default, temp data related to HDFS encryption is written to a staging directory identified by the `hive-exec.stagingdir` property created in the `hive-site.xml` file? associated with the table folder.
- Previously, an `INSERT OVERWRITE` on a partitioned table inherited permissions for new data from the existing partition directory. With encryption enabled, permissions are inherited from the table.

- When using encryption with Trash enabled, table deletion operates differently than the default trash mechanism. For more information see [Delete Files from an Encryption Zone](#).

### 6.2.4.2. HBase

HBase stores all of its data under its root directory in HDFS, configured with `hbase.rootdir`. The only other directory that the HBase service will read or write is `hbase.bulkload.staging.dir`.

On HDP clusters, `hbase.rootdir` is typically configured as `/apps/hbase/data`, and `hbase.bulkload.staging.dir` is configured as `/apps/hbase/staging`. HBase data, including the root directory and staging directory, can reside in an encryption zone on HDFS.

The HBase service user needs to be granted access to the encryption key in the Ranger KMS, because it performs tasks that require access to HBase data (unlike Hive or HDFS).

By design, HDFS-encrypted files cannot be bulk-loaded from one encryption zone into another encryption zone, or from an encryption zone into an unencrypted directory. Encrypted files can only be copied. An attempt to load data from one encryption zone into another will result in a copy operation. Within an encryption zone, files can be copied, moved, bulk-loaded, and renamed.

#### 6.2.4.2.1. Recommendations

- Make the parent directory for the HBase root directory and bulk load staging directory an encryption zone, instead of just the HBase root directory. This is because HBase bulk load operations need to move files from the staging directory into the root directory.
- In typical deployments, `/apps/hbase` can be made an encryption zone.
- Do not create encryption zones as subdirectories under `/apps/hbase`, because HBase may need to rename files across those subdirectories.
- The landing zone for unencrypted data should always be within the destination encryption zone.

#### 6.2.4.2.2. Steps

On a cluster without HBase currently installed:

1. Create the `/apps/hbase` directory, and make it an encryption zone.
2. Configure `hbase.rootdir=/apps/hbase/data`.
3. Configure `hbase.bulkload.staging.dir=/apps/hbase/staging`.

On a cluster with HBase already installed, perform the following steps:

1. Stop the HBase service.
2. Rename the `/apps/hbase` directory to `/apps/hbase-tmp`.
3. Create an empty `/apps/hbase` directory, and make it an encryption zone.

4. DistCp -skipcrccheck -update all data from /apps/hbase-tmp to /apps/hbase, preserving user-group permissions and extended attributes.
5. Start the HBase service and verify that it is working as expected.
6. Remove the /apps/hbase-tmp directory.

#### 6.2.4.2.3. Changes in Behavior after HDFS Encryption is Enabled

The HBase bulk load process is a MapReduce job that typically runs under the user who owns the source data. HBase data files created as a result of the job are then bulk loaded in to HBase RegionServers. During this process, HBase RegionServers move the bulk-loaded files from the user's directory and move (rename) the files into the HBase root directory (/apps/hbase/data). When data at rest encryption is used, HDFS cannot do a rename across encryption zones with different keys.

Workaround: run the MapReduce job as the hbase user, and specify an output directory that resides in the same encryption zone as the HBase root directory.

#### 6.2.4.3. Sqoop

Following are considerations for using Sqoop to import or export HDFS-encrypted data.

##### 6.2.4.3.1. Recommendations

- **For Hive:**

Make sure that you are using Sqoop with the --target-dir parameter set to a directory that is inside the Hive encryption zone. Specify the -D option after sqoop import.

For example:

```
sqoop import \
-D sqoop.test.import.rootDir=<root-directory> \
--target-dir <directory-inside-encryption-zone> \
<additional-arguments>
```

- **For append or incremental import:**

Make sure that the sqoop.test.import.rootDir property points to the encryption zone specified in the --target-dir argument.

- **For HCatalog:**

No special configuration is required.

#### 6.2.4.4. MapReduce on YARN

**Recommendation:** Make /apps/history a single encryption zone. History files are moved between the intermediate and done directories, and HDFS encryption will not allow you to move encrypted files across encryption zones.

#### 6.2.4.4.1. Steps

On a cluster with MapReduce over YARN installed, create the `/apps/history` directory and make it an encryption zone.

If `/apps/history` already exists and is not empty:

1. Create an empty `/apps/history-tmp` directory
2. Make `/apps/history-tmp` an encryption zone
3. Copy (`distcp`) all data from `/apps/history` into `/apps/history-tmp`
4. Remove `/apps/history`
5. Rename `/apps/history-tmp` to `/apps/history`

#### 6.2.4.5. Oozie

##### 6.2.4.5.1. Recommendations

A new Oozie administrator role (`oozie-admin`) has been created in HDP 2.3.

This role enables role separation between the Oozie daemon and administrative tasks. Both the `oozie-admin` role and the `oozie` role must be specified in the `adminusers.txt` file. This file is installed in HDP 2.3 with both roles specified. Both are also defined in Ambari 2.1 as well. Modification is only required if administrators choose to change the default administrative roles for Oozie.

If `oozie-admin` is used as the Oozie administrator user in your cluster, then the role is automatically managed by ambari.

If you plan to create an Oozie admin user other than `oozie-admin`, add the chosen username to `adminusers.txt` under the `$OOZIE_HOME/conf` directory.

Here is a sample `adminusers.txt` file:

```

Licensed to the Apache Software Foundation (ASF) under one
or more contributor license agreements. See the NOTICE file
distributed with this work for additional information
regarding copyright ownership. The ASF licenses this file
to you under the Apache License, Version 2.0 (the
"License"); you may not use this file except in compliance
with the License. You may obtain a copy of the License at

http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software
distributed under the License is distributed on an "AS IS" BASIS,
WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
See the License for the specific language governing permissions and
limitations under the License.

Users should be set using following rules:

One user name per line
```

```
Empty lines and lines starting with '#' are ignored
#
oozie
oozie-admin
```

## 6.2.4.6. WebHDFS

### 6.2.4.6.1. Recommendations

WebHDFS is supported for writing and reading files to and from encryption zones.

#### 6.2.4.6.1.1. Steps

To access encrypted files via WebHDFS, complete the following steps:

1. To enable WebHDFS in `hdfs-site.xml`, set the `dfs.webhdfs.enabled` property to true:

```
<property>
 <name>dfs.webhdfs.enabled</name>
 <value>true</value>
</property>
```

2. Make sure that you have separate HDFS administrative and service users, as described in [Creating an HDFS Admin User](#).
3. KMS supports a blacklist and a whitelist for key access (through `kms-acls.xml`).

By default the `hdfs` service user is included in the blacklist for `decrypt_eek` operations. To support WebHDFS, the HDFS service user must not be on the key access blacklist. Remove the HDFS service user from the blacklist:

- a. To edit the blacklist using Ambari, go to Ranger KMS -> Configs, and search for "blacklist" or open the Advanced dbks-site list.
- b. Remove `hdfs` from the `hadoop.kms.blacklist.DECRYPT_EEK` property:

The screenshot shows the Ambari interface for managing Ranger KMS configurations. On the left, a sidebar lists various services: HDFS, MapReduce2, YARN, Tez, Hive, HBase, Pig, Oozie, ZooKeeper, Storm, Ambari Metrics, Kafka, Kerberos, Knox, and Ranger. The 'Ranger KMS' service is currently selected. The main panel has tabs for 'Summary' and 'Configs'. Under 'Configs', there's a 'Group' dropdown set to 'Ranger KMS Default (4)', a 'Manage Config Groups' button, and a search bar containing 'blacklist'. Below these are four configuration cards labeled V4, V3, V2, and V1, each showing 'admin' as the author and 'about a month ago' as the last update. At the bottom, there's a 'Discard' button and a 'Save' button. A modal window titled 'Advanced dbks-site' is open, showing the 'hadoop.kms.blacklist.DECRYPT\_EEK' property with the value 'hdfs' in a text input field. There are also 'Add' and 'Edit' icons next to the input field.

- c. Restart Ranger KMS.
4. The HDFS service user must have GENERATE\_EEK and DECRYPT\_EEK permissions. To add the permissions using the Ranger Web UI, select the Access Manager tab-> Resource Based Policies (the default Access Manager view). Select the key store, select the policy, and click the edit icon. In the Permissions column click the edit icon and check the boxes for GenerateEEK and DecryptEEK. Then click Save.

5. Because the HDFS service user will have access to all keys, the HDFS service user should not be the administrative user. Specify a different administrative user in `hdfs-site.xml` for the administrative user.

For more information about operational tasks using Ranger KMS, see the [Ranger KMS Administration Guide](#).

## 6.2.5. Appendix: Creating an HDFS Admin User

To capitalize on the capabilities of HDFS data at rest encryption, you will need two separate types of HDFS administrative accounts:

- HDFS administrative user: an account in the `hdfs` supergroup that is used to manage encryption keys and encryption zones. Examples in this chapter use an administrative user account named `enrcr`.
- HDFS service user: the system-level account traditionally associated with HDFS. By default this is user `hdfs` in HDP. This account owns the HDFS DataNode and NameNode processes.



### Important

This is a system-only account. Physical users should not be given access to this account.

Complete the following steps to create a new HDFS administrative user.

**Note:** These steps use sample values for group (`operator`) and user account (`opt1`).

1. Create a new group called `operator`.
2. Add a new user (for example, `opt1`) to the group.
3. Add principal `opt1@EXAMPLE.COM` and create a keytab.
4. Login as `opt1`, and do a `kinit` operation.
5. In Ambari, replace the current value of `dfs.permissions.superusergroup` with the group name "operator".

In Ambari, add `operator` to `dfs.permissions.superusergroup`.



### Note

You can assign only one administrator group for the `dfs.permissions.superusergroup` parameter.

6. In Ambari, add `hdfs,operator` to `dfs.cluster.administrators`:

7. Add `opt1` to the KMS blacklist. Set the corresponding property in Ambari:

```
hadoop.kms.blacklist.DECRYPT_EEK=opt1
```

8. Restart HDFS.

### Validation

Make sure the `opt1` account has HDFS administrative access:

```
hdfs dfsadmin -report
```

Make sure the `opt1` account cannot access encrypted files. For example, if `/data/test/file.txt` is in an encryption zone, the following command should return an error:

```
hdfs dfs -cat /data/test/file.txt
```

### Additional Administrative User Accounts

If you plan to use HDFS data at rest encryption with YARN, we recommend that you create a separate administrative user account for YARN administration.

If you plan to use HDFS data at rest encryption with Oozie, refer to the [Oozie](#) section of this chapter.